

Metalogix® StoragePoint 6.0.

Azure Adapter Guide



© 2021 Quest Software Inc. ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.
Attn: LEGAL Dept.
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<https://www.quest.com>) for regional and international office information.

Patents

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

Trademarks

Quest, the Quest logo, and Metalogix are trademarks and registered trademarks of Quest Software Inc. and its affiliates. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Legend



CAUTION: A caution icon indicates potential damage to hardware or loss of data if instructions are not followed.



IMPORTANT, NOTE, TIP, MOBILE OR VIDEO: An information icon indicates supporting information.

Contents

Azure Adapter Configuration	4
Azure Adapter Connection String Parameters	5
Example Storage Endpoint Using Azure Adapter	12
Appendix: Troubleshooting	13
Problem: Receiving errors on storage or retrieval of externalized content.	13
About Us	14
Contacting Quest	14
Technical Support Resources	14

Azure Adapter Configuration

This section will provide you details on how to configure a storage endpoint's connection string to utilize the Azure Adapter. Please refer to the StoragePoint Reference Guide for information on managing Storage Endpoints.

On the Application Management page, click *Storage and Backup Endpoints*.

Click *Create New Endpoint* or click the name of an existing storage endpoint that you want to edit.

Click the *Show* link next to the Advanced Adapter Settings to see the additional fields.

Adapter

Azure 

Adapter Settings Show Connection String

Use SSL

Yes

Account Name

Container

Key

Advanced Adapter Settings *(Hide)*

Retry Policy

N


Strict SSL

No

Time Out Duration (in seconds)

Azure Adapter Connection String Parameters

Setting	Value/Options
<p>Name</p>	<p>Enter the unique name of the Storage or Backup Endpoint.</p>
<p>Type</p>  <p>See Backup Services Settings in the Reference Guide for more information on how Backup Endpoints are used.</p>	<p><i>Primary</i>– this endpoint will be available for externalization when creating storage profiles.</p> <p><i>Backup</i>– this endpoint will be in the Backup Services dropdown on the profile page.</p> <p>The selection is locked down when saving.</p>
<p>Status</p> 	<p><i>Online</i>– Storage Endpoint should be available to associate to a Storage Profile and accept BLOBs. (default)</p> <p><i>Offline (Read Only)</i>– A storage endpoint can be configured, but not made available for externalizing content. The BLOBs already on</p>

Setting	Value/Options
	the endpoint are still read only.
<p>Adapter</p> 	Select the adapter for the endpoint that is being created.
<p>Use SSL</p> 	<i>(yes/no)</i> – Determines whether or not the adapter negotiates an SSL connection for all data (and metadata) transfers. Default = No.
<p>Account Name</p> 	This is the name you gave your application in the Azure web UI.
<p>Container</p> 	This is the top level container name in which the profile blobs are stored in Azure. It must be lower case and may NOT include the underscore character. This container will be created by the adapter automatically. You may create a different name for each profile.

Setting	Value/Options
<p>Key</p> <input data-bbox="247 315 874 360" type="text" value="enter an account key"/>	<p>This is the Primary or Secondary storage key of your storage application in the Azure Web UI</p>
<p>Advanced Adapter Settings <i>(Hide)</i></p> <p>Retry Policy</p> <input data-bbox="236 674 432 712" type="text" value="N"/> <input data-bbox="432 674 555 712" type="text" value="2"/>	<p>None – no retries.</p> <p>N,{max} – where {max} is the number of times you want it to retry the operation. N,2 is the default value if this parameter is not supplied.</p> <p>ExponentialN, {max} – the same as N,{max} except the delays between retries will become exponentially larger.</p>
<p>Strict SSL</p> <input data-bbox="252 1507 347 1547" type="text" value="No"/>	<p><i>(Yes/No)</i> If <i>UseSSL</i> is <i>Yes</i>, the <i>StrictSSL</i> flag controls whether or not the use of "self-issued" or otherwise suspicious certificates on the Azure system will be tolerated. Note that the default certificate</p>

Setting	Value/Options
	<p>out of the box with Azure is self-issued and will not work unless this flag is set to No (default).</p>
<p>Time Out Duration (in seconds)</p> <input data-bbox="236 600 451 645" type="text" value="300"/>	<p>The amount of seconds to wait for operations to complete before forcing a timeout. Default = 300.</p>
<p>Is WORM Device</p> <input data-bbox="300 920 389 958" type="button" value="No"/>	<p>If the endpoint is on a WORM (Write Once, Read Many) device, Unused BLOB Cleanup will ignore this endpoint.</p>
<p>Folder Content in BLOB Store</p> <input data-bbox="229 1249 320 1283" type="button" value="Yes"/> <p>Folder Scheme</p> <input data-bbox="229 1339 560 1373" type="text" value="YYYY/MM/DD/HH/MM"/>	<p><i>No</i>– Externalized content BLOBs are not placed in folders (default).</p> <p><i>Yes</i>– Externalized content BLOBs are placed in folders .</p> <p>If <i>Folder Content in BLOB Store</i> is <i>Yes</i> then you can select a date/time folder scheme from the dropdown.</p>

Setting	Value/Options
	YYYY/MM/DD/H H/MM is the default.
<div data-bbox="240 443 533 488" style="border: 1px solid black; padding: 2px; display: inline-block;">Test Storage Settings</div>	<p>The Test Storage Settings button can be used at this point, or after completing the endpoint configuration, to verify that the endpoint is accessible. For some adapters, testing the connection will create the container if it doesn't already exist.</p>
<p>Compress Content in BLOB Store</p> <div data-bbox="229 1189 316 1223" style="border: 1px solid black; padding: 2px; display: inline-block;">No</div> <p><i>Content is compressed using the GZip/Deflate method.</i></p>	<p><i>No</i>– Externalized content BLOBs are not compressed (default).</p> <p><i>Yes</i>– Externalized content BLOBs are compressed.</p>
<p>Encryption Method for Content in BLOB Store</p> <div data-bbox="229 1592 437 1626" style="border: 1px solid black; padding: 2px; display: inline-block;">None</div>	<p><i>None</i>– Encryption will not be applied to externalized BLOBs (default).</p> <p><i>AES (128 bit)</i>– 128 bit AES encryption will be applied to</p>

Setting	Value/Options
	<p>externalized BLOBs.</p> <p><i>AES (256 bit)</i>– 256 bit AES encryption will be applied to externalized BLOBs.</p>
<p>Encryption Key Passphrase</p> <p><input type="text"/> <input type="button" value="Generate Key"/></p> <p><i>Enter a passphrase to be used to generate a key or leave blank to generate a random key. The passphrase entered is not saved with the Endpoint.</i></p>	<p>Enter a passphrase to use when generating the encryption key. Using a passphrase will help you re-create the encryption key if necessary. You can generate a random key by leaving the box blank and clicking the <i>Generate Key</i> button. The encryption key passphrase will be hidden.</p>
<p>Generate warning notification if:</p> <p><input checked="" type="checkbox"/> <input type="text" value="10"/> or more successive errors are encountered</p> <p><input checked="" type="checkbox"/> there is less than <input type="text" value="10"/> <input checked="" type="radio"/> MB <input type="radio"/> % of free space</p>	<p>A warning email can be sent if it encounters errors.</p>
<p>Automatically take endpoint offline if:</p> <p><input checked="" type="checkbox"/> <input type="text" value="25"/> or more successive errors are encountered</p> <p><input checked="" type="checkbox"/> there is less than <input type="text" value="1"/> <input checked="" type="radio"/> MB <input type="radio"/> % of free space</p>	<p>An online storage endpoint can be automatically taken offline if it encounters errors. If a storage endpoint</p>

Setting	Value/Options
	is taken offline automatically, BLOBs that were intended to be written to that endpoint will go to the content database.
<p>Send Offline Notifications to:</p> <p><input checked="" type="checkbox"/> Use Notification Defaults</p> <p>Additional Contacts</p> <p><u>admin@company.com</u></p> <p><i>Provide a semi-colon delimited list of e-mail addresses.</i></p>	<p>Default email addresses for system error and offline notification can be entered. Check the box to include the list of Default Notification Contacts specified on the General Settings page.</p>

Example Storage Endpoint Using Azure Adapter

Adapter
Azure 

Adapter Settings Show Connection String

Use SSL
Yes

Account Name

Container

Key

Advanced Adapter Settings *(Hide)*


Retry Policy
N

Strict SSL
Yes

Time Out Duration (in seconds)

Click the *Show Connection String* checkbox to edit the connection string. Otherwise, fill in the connection fields shown for the adapter selected. Notice that the connection string parameters are

name/value pairs separated by semi-colons when editing using the Show Connection String option.



The screenshot shows a configuration window for an Azure adapter. At the top, there is a dropdown menu labeled 'Adapter' with 'Azure' selected and a help icon. Below it, 'Adapter Settings' includes a checked checkbox for 'Show Connection String'. The 'Connection' section contains a text box with the following connection string: `USESSL=True;ACCOUNTNAME=AccountName;KEY=fmngs.kdjnkjrdkjklsdfkgj;ositjghosijdng;osidgh;CONTAINER=Portal;RETRYPOLICY=N,2;STRICTSSL=True;TIMEOUT=300;`. Below the text box is a note: 'Provide adapter-specific connection attributes. Please refer to the adapter documentation for connection string details.'

i | **NOTE:** Adapter parameters are not case-sensitive.

i | **NOTE:** You should always use a passphrase when generating encryption keys. The passphrase gives you a means of re-creating keys should they become unrecoverable or corrupt. It is very important to remember or record the passphrase outside of Metalogix StoragePoint. Otherwise, encrypted content could become irretrievable in the event of a database failure.

If you choose to externalize content you should test the storage profile settings by clicking the *Test Storage Settings* button. A message under the button will indicate whether or not the test was successful. If the test fails the message will include the error that was the root cause of the failure.

i | **NOTE:** When testing access to an endpoint from within Central Administration, the Identity of the Application Pool hosting the Central Administration Site is the one that is being used for the test. If there are different Identities used for other Web Applications in the Farm then those identities will also need access but cannot be tested from within Central Admin itself. See BLOB Store Security and Metalogix StoragePoint Required Privileges in the Metalogix StoragePoint Reference Guide.

Appendix: Troubleshooting

Problem: Receiving errors on storage or retrieval of externalized content.

Wherever possible, StoragePoint surfaces error messages returned by the adapter either directly to the user or within the SharePoint ULS logs. You should refer to your storage platform/provider documentation for resolution to errors logged by the adapter.

About Us

Quest creates software solutions that make the benefits of new technology real in an increasingly complex IT landscape. From database and systems management, to Active Directory and Office 365 management, and cyber security resilience, Quest helps customers solve their next IT challenge now. Around the globe, more than 130,000 companies and 95% of the Fortune 500 count on Quest to deliver proactive management and monitoring for the next enterprise initiative, find the next solution for complex Microsoft challenges and stay ahead of the next threat. Quest Software. Where next meets now. For more information, visit www.quest.com.

Contacting Quest

For sales or other inquiries, visit www.quest.com/contact.

Technical Support Resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product