

Rapid Recovery 6.7

Commands and Scripting Reference Guide



© 2022 Quest Software Inc. ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.

Attn: LEGAL Dept

4 Polaris Way

Aliso Viejo, CA 92656

Refer to our Web site (<https://www.quest.com>) for regional and international office information.

Patents

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

Trademarks

Quest, the Quest logo, and Join the Innovation are trademarks and registered trademarks of Quest Software Inc. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Legend

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

 **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Contents

Introduction to Rapid Recovery	22
Command Line Management utility	24
Commands	25
ApplyLicense	25
Usage	25
Command Options	25
Examples:	26
Archive	26
Usage	26
Command Options	26
Examples:	28
CancelActiveJobs	29
Usage	29
Command Options	29
Example:	30
CheckRepository	30
Usage	30
Command Options	30
Example:	32
ConfigureAgentMigration	32
Usage	32
Command Options	32
Example:	33
CreateArchiveRepository	33
Usage	33
Command Options	33
Examples:	34
CreateBootCD	34
Usage	35
Command Options	35
Example:	35
CreateEncryptionKey	35
Usage	35
Command Options	36
Example:	36
CreateNASRepository	36
Usage	36
Command Options	37
Examples:	37
CreateRepository	37
Usage	37

Command Options	38
Examples:	38
DedupCacheConfig	39
Usage	39
Command Options	39
Examples:	39
DeleteReplication	40
Usage	40
Command Options	40
Example:	41
DeleteRepository	41
Usage	41
Command Options	41
Example:	42
DeleteTieredRepository	42
Usage	42
Command Options	42
Example:	43
DeployToAzure	43
Usage	43
Command Options	43
Example:	44
Dismount	45
Usage	45
Command Options	45
Example:	46
DismountArchiveRepository	46
Usage	46
Command Options	46
Examples:	47
DismountRemote	47
Usage	47
Command Options	47
Example:	48
EditEsxServer	48
Usage	48
Command Options	48
Examples:	49
EditHyperVCluster	49
Usage	49
Command Options	49
Example:	50
EditHyperVServer	50
Usage	50
Command Options	51
Example:	51
EditOracleDBVerifyNightlyJob	51

Usage	51
Command Options	52
Example:	52
EditOracleLogTruncationNightlyJob	52
Usage	52
Command Options	53
Examples:	54
EnableOracleArchiveLogMode	54
Usage	54
Command Options	54
Example:	55
FileSearch	55
Usage	55
Command Options	55
Examples:	56
Force	56
Usage	56
Command Options	57
Example:	57
ForceAttach	57
Usage	57
Command Options	57
Example:	58
ForceChecksum	58
Usage	58
Command Options	58
Example:	59
ForceLogTruncation	59
Usage	59
Command Options	59
Example:	60
ForceMount	60
Usage	60
Command Options	60
Example:	61
ForceOptimizationJob	61
Usage	61
Command Options	61
Example:	62
ForceReplication	62
Usage	62
Command Options	62
Example:	63
ForceRollup	63
Usage	63
Command Options	63
Example:	63

ForceScheduledArchive	64
Usage	64
Command Options	64
Examples:	64
ForceVirtualStandby	65
Usage	65
Command Options	65
Examples:	65
GetOracleInstanceMetadata	65
Usage	66
Command Options	66
Example:	66
Help	66
Usage	66
Example:	67
List	67
Usage	67
Command Options	67
Examples:	69
ListAzureVMSizes	69
Usage	69
Command Options	69
Examples:	70
ListOracleInstances	70
Usage	70
Command Options	70
Example:	71
ManagementCertificates	71
Usage	71
Command Options	71
Examples:	72
Mount	72
Usage	72
Command Options	72
Examples:	73
MountArchiveRepository	73
Usage	73
Command Options	74
Examples:	74
NewCloudAccount	74
Usage	74
Command Options	74
Examples:	76
OpenDvmRepository	76
Usage	76
Command Options	76
Example:	76

Pause	76
Usage	77
Command Options	77
Examples:	79
Protect	79
Usage	79
Command Options	79
Example:	80
ProtectCluster	80
Usage	80
Command Options	80
Example:	81
ProtectEsxServer	81
Usage	81
Command Options	82
Example:	82
ProtectHyperVCluster	82
Usage	82
Command Options	83
Example:	83
ProtectHyperVServer	84
Usage	84
Command Options	84
Example:	84
RemoveAgent	85
Usage	85
Command Options	85
Example:	85
RemoveArchiveRepository	85
Usage	86
Command Options	86
Examples:	86
RemovePoints	86
Usage	86
Command Options	86
Example:	87
RemoveScheduledArchive	87
Usage	87
Command Options	87
Examples:	88
RemoveVirtualStandby	88
Usage	88
Command Options	88
Examples:	89
Replicate	89
Usage	89
Command Options	89

Example:	90
Replication	90
Usage	90
Command Options	91
Examples:	92
ResizeDedupeCache	93
Usage	93
Command Options	93
Examples:	93
RestartCoreService	93
Usage	94
Command Options	94
Example:	94
RestoreAgent	94
Usage	94
Command Options	95
Example:	95
RestoreArchive	95
Usage	95
Command Options	96
Examples:	96
RestoreUrc	96
Usage	97
Command Options	97
Example:	97
Resume	97
Usage	98
Command Options	98
Examples:	98
ResumeScheduler	99
Usage	99
Command Options	99
Example:	99
SeedDrive	100
Usage	100
Command Options	100
Examples:	101
SetAgentMetadataCredentials	101
Usage	101
Command Options	101
Example:	102
SetOracleMetadataCredentials	102
Usage	102
Command Options	103
Examples:	103
StartExport	104
Usage	104

Command Options	104
Examples:	106
StartExportAzure	106
Usage	106
Command Options	107
Examples:	108
StartOracleDBVerifyJob	109
Usage	109
Command Options	109
Example:	110
StartOracleLogTruncationJob	110
Usage	110
Command Options	110
Examples:	111
StopCoreService	111
Usage	111
Command Options	112
Example:	112
SuspendScheduler	112
Usage	112
Command Options	112
Example:	113
UpdateRepository	113
Usage	113
Command Options	113
Examples:	114
Version	114
Usage	114
Command Options	115
Example:	115
VirtualStandby	115
Usage	115
Command Options	115
Examples:	117
Localization	118
PowerShell module	119
Prerequisites for using PowerShell	120
powershell.exe.config	120
Working with commands and cmdlets	120
Getting cmdlet help and examples	120
Rapid Recovery PowerShell module cmdlets	121
Add-EsxAutoProtectObjects	121
Usage	121
Command Options	121
Example:	122

Add-EsxVirtualMachines	122
Usage	122
Command Options	122
Example:	123
Add-HyperVClusterSharedVirtualDisks	123
Usage	123
Command Options	123
Example:	124
Add-HyperVClusterVirtualMachines	124
Usage	124
Command Options	124
Example:	125
Add-HyperVVirtualMachines	125
Usage	125
Command Options	125
Example:	126
Disable-HyperVAutoProtection	126
Usage	126
Command Options	126
Example:	127
Edit-AzureVirtualStandby	127
Usage	127
Command Options	127
Example:	128
Edit-EsxiVirtualStandby	128
Usage	128
Command Options	129
Example:	129
Edit-HyperVVirtualStandby	130
Usage	130
Command Options	130
Example:	131
Edit-OracleDBVerifyNightlyJob	131
Usage	131
Command Options	131
Examples:	132
Edit-OracleLogTruncationNightlyJob	132
Usage	132
Command Options	133
Examples:	134
Edit-Replication	134
Usage	134
Command Options	134
Examples:	135
Edit-ScheduledArchive	135
Usage	135
Command Options	136

Example:	137
Edit-VBVirtualStandby	137
Usage	137
Command Options	138
Example:	138
Edit-VMVirtualStandby	139
Usage	139
Command Options	139
Example:	140
Enable-HyperVAutoProtection	140
Usage	140
Command Options	140
Example:	141
Enable-OracleArchiveLogMode	141
Usage	141
Command Options	141
Example:	142
Get-ActiveJobs	142
Usage	142
Command Options	142
Example:	143
Get-CloudAccounts	143
Usage	143
Command Options	143
Example:	144
Get-Clusters	144
Usage	144
Command Options	144
Example:	144
Get-CompletedJobs	145
Usage	145
Command Options	145
Example:	146
Get-ExchangeMailStores	146
Usage	146
Command Options	146
Example:	147
Get-Failed	147
Usage	147
Command Options	147
Example:	147
Get-FailedJobs	148
Usage	148
Command Options	148
Example:	149
Get-HyperVClusterSharedVirtualDisks	149
Usage	149

Command Options	149
Example:	150
Get-ListAzureVMSizes	150
Usage	150
Command Options	150
Example:	151
Get-Mounts	151
Usage	151
Command Options	151
Example:	152
Get-OracleInstances	152
Usage	152
Command Options	152
Example:	152
Get-Passed	153
Usage	153
Command Options	153
Example:	153
Get-ProtectedServers	153
Usage	153
Command Options	154
Example:	154
Get-ProtectionGroups	154
Usage	154
Command Options	154
Example:	155
Get-QueuedJobs	155
Usage	155
Command Options	155
Example:	156
Get-RecoveryPoints	156
Usage	156
Command Options	157
Example:	157
Get-ReplicatedServers	157
Usage	157
Command Options	157
Example:	158
Get-Repositories	158
Usage	158
Command Options	158
Example:	159
Get-ScheduledArchives	159
Usage	159
Command Options	159
Example:	159
Get-SqlDatabases	159

Usage	160
Command Options	160
Example:	160
Get-TransferQueueEntries	160
Usage	160
Command Options	160
Example:	161
Get-UnprotectedVolumes	161
Usage	161
Command Options	161
Example:	163
Get-Version	163
Usage	163
Command Options	163
Example:	163
Get-VirtualizedServers	163
Usage	164
Command Options	164
Example:	165
Get-Volumes	165
Usage	165
Command Options	165
Example:	166
New-AzureVirtualStandby	166
Usage	166
Command Options	166
Example:	167
New-Base	167
Usage	167
Command Options	167
Example:	168
New-BootCD	168
Usage	168
Command Options	168
Example:	169
New-CloudAccount	169
Usage	169
Command Options	170
Example:	171
New-EncryptionKey	171
Usage	171
Command Options	171
Example:	171
New-EsxiVirtualStandby	172
Usage	172
Command Options	172
Example:	173

New-FileSearch	173
Usage	173
Command Options	174
Examples:	174
New-HyperVVirtualStandby	175
Usage	175
Command Options	175
Example:	176
New-Mount	176
Usage	176
Command Options	177
Example:	177
New-Replication	178
Usage	178
Command Options	178
Example:	178
New-Repository	179
Usage	179
Command Options	179
Example:	179
New-ScheduledArchive	180
Usage	180
Command Options	180
Examples:	181
New-Snapshot	182
Usage	182
Command Options	182
Example:	183
New-VBVirtualStandby	183
Usage	183
Command Options	183
Example:	184
New-VMVirtualStandby	184
Usage	184
Command Options	185
Example:	185
Push-Replication	186
Usage	186
Command Options	186
Example:	186
Push-Rollup	187
Usage	187
Command Options	187
Example:	187
Remove-Agent	187
Usage	188
Command Options	188

Example:	188
Remove-EsxAutoProtectObjects	188
Usage	188
Command Options	189
Example:	189
Remove-HyperVClusterSharedVirtualDisks	189
Usage	189
Command Options	189
Example:	190
Remove-HyperVClusterVirtualMachines	190
Usage	190
Command Options	190
Example:	191
Remove-HyperVVirtualMachines	191
Usage	191
Command Options	191
Example:	192
Remove-Mount	192
Usage	192
Command Options	192
Example:	193
Remove-Mounts	193
Usage	193
Command Options	193
Example:	194
Remove-RecoveryPoints	194
Usage	194
Command Options	194
Example:	195
Remove-RemoteMount	195
Usage	195
Command Options	195
Examples:	196
Remove-RemoteMounts	196
Usage	196
Command Options	196
Example:	197
Remove-Replication	197
Usage	197
Command Options	197
Example:	198
Remove-Repository	198
Usage	198
Command Options	198
Example:	199
Remove-ScheduledArchive	199
Usage	199

Command Options	199
Example:	200
Remove-VirtualStandby	200
Usage	200
Command Options	200
Example:	201
Restart-CoreService	201
Usage	201
Command Options	201
Example:	201
Resume-Replication	202
Usage	202
Command Options	202
Example:	202
Resume-ScheduledArchive	203
Usage	203
Command Options	203
Examples:	203
Resume-Snapshot	204
Usage	204
Command Options	204
Example:	204
Resume-VirtualStandby	205
Usage	205
Command Options	205
Example:	205
Set-AgentMetadataCredentials	205
Usage	206
Command Options	206
Example:	206
Set-DedupCacheConfiguration	207
Usage	207
Command Options	207
Examples:	207
Set-License	208
Usage	208
Command Options	208
Examples:	208
Set-OracleMetadataCredentials	209
Usage	209
Command Options	209
Examples:	210
Set-ReplicationResponse	210
Usage	210
Command Options	211
Examples:	211
Start-Archive	211

Usage	211
Command Options	212
Example:	212
Start-AttachabilityCheck	212
Usage	212
Command Options	213
Example:	213
Start-AzureDeploy	213
Usage	214
Command Options	214
Examples:	215
Start-AzureExport	216
Usage	216
Command Options	216
Examples:	218
Start-ChecksumCheck	219
Usage	219
Command Options	219
Example:	220
Start-ConsumeSeedDrive	220
Usage	220
Command Options	220
Examples:	221
Start-CopySeedDrive	221
Usage	221
Command Options	221
Examples:	222
Start-EsxiExport	222
Usage	223
Command Options	223
Start-HypervExport	224
Usage	224
Command Options	224
Example:	226
Start-LogTruncation	226
Usage	226
Command Options	226
Example:	226
Start-MountabilityCheck	227
Usage	227
Command Options	227
Example:	227
Start-OptimizationJob	228
Usage	228
Command Options	228
Example:	228
Start-OracleDBVerifyJob	228

Usage	228
Command Options	229
Example:	229
Start-OracleLogTruncationJob	229
Usage	229
Command Options	230
Examples:	230
Start-Protect	231
Usage	231
Command Options	231
Example:	231
Start-ProtectCluster	232
Usage	232
Command Options	232
Example:	233
Start-ProtectEsxServer	233
Usage	233
Command Options	233
Example:	234
Start-ProtectHyperVCluster	234
Usage	234
Command Options	234
Example:	235
Start-ProtectHyperVServer	235
Usage	235
Command Options	235
Example:	236
Start-RepositoryCheck	236
Usage	236
Command Options	236
Example:	237
Start-RestoreAgent	237
Usage	237
Command Options	237
Example:	238
Start-RestoreArchive	238
Usage	238
Command Options	239
Example:	239
Start-ScheduledArchive	240
Usage	240
Command Options	240
Example:	240
Start-VBExport	240
Usage	241
Command Options	241
Example:	242

Start-VirtualStandby	242
Usage	242
Command Options	242
Example:	244
Start-VMExport	244
Usage	244
Command Options	244
Example:	245
Stop-ActiveJobs	245
Usage	246
Command Options	246
Example:	246
Stop-CoreService	247
Usage	247
Command Options	247
Example:	247
Suspend-Replication	247
Command Options	248
Example:	248
Suspend-ScheduledArchive	249
Usage	249
Command Options	249
Example:	249
Suspend-Scheduler	250
Usage	250
Command Options	250
Example:	250
Suspend-Snapshot	250
Usage	250
Command Options	251
Example:	251
Suspend-VirtualStandby	251
Usage	251
Command Options	251
Example:	252
Suspend-VMExport	252
Usage	252
Command Options	252
Example:	253
Update-Repository	253
Usage	253
Command Options	253
Example:	254
Localization	254
Qualifiers	254
Scripting	256

Using PowerShell scripting with Rapid Recovery	256
Prerequisites for PowerShell scripting	256
powershell.exe.config	257
Testing PowerShell Scripts	257
Localization	257
Qualifiers	257
Input Parameters for PowerShell Scripting	258
AgentProtectionStorageConfiguration (namespace Replay.Common.Contracts.Agents) ..	258
AgentTransferConfiguration (namespace Replay.Common.Contracts.Transfer)	259
BackgroundJobRequest (namespace Replay.Core.Contracts.BackgroundJobs)	260
ChecksumCheckJobRequest (namespace Replay.Core.Contracts.Exchange.ChecksumChecks)	261
DatabaseCheckJobRequestBase (namespace Replay.Core.Contracts.Exchange)	261
ExportJobRequest (namespace Replay.Core.Contracts.Export)	261
NightlyAttachabilityJobRequest (namespace Replay.Core.Contracts.Sql)	261
RollupJobRequest (namespace Replay.Core.Contracts.Rollup)	262
TakeSnapshotResponse (namespace Replay.Agent.Contracts.Transfer)	262
TransferJobRequest (namespace Replay.Core.Contracts.Transfer)	262
TransferPrescriptParameter (namespace Replay.Common.Contracts.PowerShellExecution)	264
TransferPostscriptParameter (namespace Replay.Common.Contracts.PowerShellExecution)	264
TransferScriptParameterBase (namespace Replay.Common.Contracts.PowerShellExecution)	267
VirtualMachineLocation (namespace Replay.Common.Contracts.Virtualization)	267
VolumeImageldsCollection (namespace Replay.Core.Contracts.RecoveryPoints)	268
VolumeName (namespace Replay.Common.Contracts.Metadata.Storage)	268
VolumeNameCollection (namespace Replay.Common.Contracts.Metadata.Storage)	268
VolumeSnapshotInfo (namesapce Replay.Common.Contracts.Transfer)	269
VolumeSnapshotInfoDictionary (namespace Replay.Common.Contracts.Transfer)	269
Sample PowerShell scripts	269
PreTransferScript.ps1	269
PostTransferScript.ps1	270
PreExportScript.ps1	270
PostExportScript.ps1	271
PreNightlyJobScript.ps1	272
PostNightlyJobScript.ps1	273
Using Bourne shell and Bash scripting with Rapid Recovery	276
Prerequisites for shell scripting	276
Execution timing for pre and post scripts	277
Supported transfer and post-transfer script parameters	277
Testing shell scripting	278
Input parameters for shell scripting	278
TransferPrescriptParameters_VolumeNames	278
TransferPostscriptParameter	279
Sample shell scripts	280
PreTransferScript.sh	281

PostTransferScript.sh	281
PreSnapshotScript.sh	282
PostSnapshotScript.sh	282
PostExportScript.sh	282
About us	284
Technical support resources	284

Introduction to Rapid Recovery

Rapid Recovery is a backup, replication, and recovery solution that offers near-zero recovery time objectives and recovery point objectives. Rapid Recovery offers data protection, disaster recovery, data migration and data management. You have the flexibility of performing bare-metal restore (to similar or dissimilar hardware), and you can restore backups to physical or virtual machines (VMs), regardless of origin. Rapid Recovery lets you create backup archives to a wide range of supported systems including archiving to the cloud. With Rapid Recovery, you can replicate to one or more targets for added redundancy and security.

Rapid Recovery offers:

- **Flexibility.** You can perform universal recovery to multiple platforms, including restoring from physical to virtual, virtual to physical, virtual to virtual, and physical to physical.
- **Cloud integration.** You can export a VM, archive and replicate to the cloud, and perform bare metal restore from archives in the cloud. Compatible cloud services include Microsoft Azure, Amazon Web Services (AWS), any OpenStack-based provider (including Rackspace), and Google Cloud. US government-specific platforms include AWS GovCloud (US) and Azure Government.
- **Intelligent deduplication.** You can reduce storage requirements by storing data once, and referencing it thereafter (once per repository or encryption domain).
- **Live Recovery.** Using the Live Recovery feature of Rapid Recovery Agent, you have instant access to critical data first, while remaining restore operations complete in parallel. You can use Live Recovery to restore data from a recovery point of any non-system volume of a Windows machine, physical or virtual. Live Recovery is not supported for agentlessly protected machines, Linux machines, or cluster-shared volumes.
- **File-level recovery.** You can recover data at the file level on-premises, from a remote location, or from the cloud.
- **File-level search.** Using criteria you specify, you can search a range of recovery points for one or more files. From the search results, you can then select and restore the files you want to the local Core machine directly from the Rapid Recovery Core Console.
- **Virtual machine export.** Rapid Recovery supports one-time virtual export, letting you generate a VM from a recovery point; and virtual standby, in which the VM you generate is continually updated after each backup. Compatible VM hypervisors include VMware vCenter/ESXi, VMware Workstation, Microsoft Hyper-V, Oracle VM VirtualBox, and Microsoft Azure. You can even perform virtual export to Hyper-V cluster-shared volumes.
- **Rapid Snap for Virtual support.** Enhanced support for virtualization includes agentless protection for vCenter/ESXi VMs and for Hyper-V VMs. Rapid Snap for Virtual includes protection and autodiscovery for VMware ESXi 6.0 and higher with no software agent installed. Host-based protection supports installing Rapid Recovery Agent on a Microsoft Hyper-V host only, letting you agentlessly protect all its guest VMs.
- **Application support.** Rapid Recovery is built with application support. When you protect SQL Server or Microsoft Exchange machines (whether using Rapid Recovery Agent or agentless protection), the backup snapshots captured are automatically application-aware; open transactions and rolling transaction logs are completed and caches are flushed to disk before creating snapshots. Specific application features are supported, including SQL attachability checks (for SQL Server) and database checksum and mountability checks (for Exchange Server). If you protect Oracle 12c or 18c servers with Rapid Recovery Agent, you can also perform DBVERIFY database integrity checks.

See the following resources for more information about Rapid Recovery.


- The Rapid Recovery product support website at <https://support.quest.com/rapid-recovery/>.
- The documentation website at <https://support.quest.com/rapid-recovery/technical-documents/>.

Command Line Management utility

Rapid Recovery consists of several software components. Key components relevant to this topic include the following:

- The Rapid Recovery Core manages authentication for protected machines, schedules for transferring data for backup and replication, export to virtual machines, reporting, and bare metal restore (BMR) to similar or dissimilar hardware.
- The Rapid Recovery Agent is responsible for volume snapshots and fast transfer of the data to the repository managed by the Core.
- The Rapid Recovery Command Line Management utility, `cmdutil.exe`, provides third-party access to manage system functionality. This tool permits scripting of the Rapid Recovery Core management functions.

Rapid Recovery Command Line Management provides command-line functions



Rapid Recovery Command Line Management is a Windows command line utility that lets users interact with the Rapid Recovery Core server. It offers some of the same functions that the Rapid Recovery Core Console graphic user interface provides. For example, Rapid Recovery Command Line Management utility can mount recovery points or force a snapshot.

The Rapid Recovery Command Line Management utility is embedded in every installation of the Rapid Recovery Core. To open the Command Line Management utility for a default installation, open the Command Prompt with Run as Administrator, and change the directory to the path `C:\Program Files\AppRecovery\Core\CoreService\`, which is the location of the `cmdutil.exe` file. From this directory, you can pass action flags to the Rapid Recovery

Command Line Management utility through a selection of command options and qualifiers to perform limited management functions.

Commands

This section describes the commands and options available for the Rapid Recovery Command Line Management utility.

ApplyLicense

There may be times when you need to change the Rapid Recovery license applied to a machine, such as when moving from a trial license to a subscription or perpetual license. In such instances, you can change the license in the Command Prompt by using the `applylicense` command.

Usage

The usage for the command is as follows:

```
/applylicense -core [host name] -user [user name] -password [password] -licensekey  
[license key] -licensepath [license file path] -licensenumbr [license number] -  
email [email address]
```

Command Options

The following table describes the options available for the `applylicense` command:

Table 1: ApplyLicense command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-licensekey	Optional. A 30-character key comprising six groups of five alphanumeric characters, each separate by a hyphen. Use this key when a license file is not available.
-licensepath	Optional. The path to the file that ends with the .lic extension. If a license file is available, you can use this option instead of the <code>-licensekey</code> .
-licensenumbr	Optional. You may have received this nine-digit license number in an order confirmation email. If you provide this number, use the email address that received it for verification.

Option	Description
-email	Optional. If you use the -licensenumbr, you must include the email address that received it for verification.

Examples:

Change the license key associated with this Core to JL09F-89FSD-6THFS-DSE34-KS3D5-65DF2:

```
>cmdutil /applylicense -core 10.10.10.10 -user admin -password 676df#df -licensekey JL09F-89FSD-6THFS-DSE34-KS3D5-65DF2
```

Change the license key associated with this Core to the key contained in the license file:

```
>cmdutil /applylicense -core 10.10.10.10 -user admin -password 676df#df -licensepath C:\MyLicenseFile.lic
```

Change the license number associated with this Core to 111-111-111 using john.doe@example.com to verify the license:

```
>cmdutil /applylicense -core 10.10.10.10 -user admin -password 676df#df -licensenumbr 111-111-111 -email john.doe@example.com
```

Archive

Businesses often use long-term storage to archive both compliant and non-compliant data. The archive feature in Rapid Recovery supports extended retention for compliant and non-compliant data. The administrator can save an archive on the local storage or network location by specifying the -path parameter and credentials.

Usage

The usage for the command is as follows:

```
/archive -core [host name] -user [user name] -password [password] -all | -protectedserver [name | IP address | "[name1 | IP address1]" "[name2 | IP address2]"] -path [location] -startdate [time string] -enddate [time string] -archiveusername [name] -archivepassword [password] -comment [text] -cloudaccountname [name] -cloudcontainer [name] -recycleaction [type] -scheduletype [type] -dayofweek [name] -dayofmonth [number] -time [time] -usecompatibleformat -scheduled -edit -id [id] -initialpause -useglacierfordatfiles
```

Command Options

The following table describes the options available for the archive command:

Table 2: Archive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Archive all recovery points for all protected machines on the Core.
-protectedserver	Protected machine with recovery points to be archived. You can specify several machine names enclosed in double quotes and separated by spaces.
-path	Path where archived data should be placed; for example: d:\work\archive or network path \\servername\sharename.
-startdate	Start date for selecting recovery points by creation date. The value must be enclosed in double quotes; for example, "04/30/2012 02:55 PM".
-enddate	Optional. End date for selecting recovery points by creation date. Value must be enclosed in double quotes; for example, "05/31/2012 11:00 AM". The current time system is used by default.
-archiveusername	Optional. User name for the remote machine. Required for network path only.
-archivepassword	Optional. Password to the remote machine. Required for network path only.
-comment	Optional. Comment text must be enclosed in double quotes; for example: -comment "comment goes here...".
-usecompatibleformat	Not supported for scheduled archives. The new format has improved performance, but it is not compatible with Cores older than release 6.2. Use this flag to create an archive that can be used with the old format.
-cloudaccountname	Optional. The name of the cloud account to which you want to save the archive.
-cloudcontainer	Optional. The name of the cloud container in the specified cloud account to which you want to save the archive.
-recycleaction	Specifies one of the following recycle action types: <ul style="list-style-type: none"> "donotreuse" - This type is not supported for scheduled archive. It does not overwrite or clear any existing archived data from the location. If the location is not empty, the archive write fails. "replacethiscore" - This type overwrites any pre-existing archived data that pertains to this Core, but leaves the data for other Cores intact. "erasecompletely" - This type clears all archived data from the directory before writing the new archive.

Option	Description
	<ul style="list-style-type: none"> "incremental" - This type lets you add recovery points to an existing archive. It compares recovery points to avoid duplicating data that already exists in the archive.
-scheduled	Optional. Specify this option to configure a scheduled archive job.
-edit	Optional. Use only for scheduled archives. Specify this option to edit an existing scheduled archive configuration.
-id	The identifier (ID) of the scheduled archive that you want to edit.
-scheduletype	<p>The type of interval that you want to use for the scheduled archive. It should specify according to one of the following four values:</p> <ul style="list-style-type: none"> "daily" - To automatically create an archive every day. "weekly" - To automatically create an archive once each week. "monthly" - To automatically create an archive once each month. "lastdayofmonth" - To automatically create an archive on the last day of each month.
-dayofweek	Only applies to the "weekly" option of the -scheduletype parameter. Specify the day on which you want to automatically create an archive (for example, "Monday").
-dayofmonth	Only applies to the "monthly" option of the -scheduletype parameter. Specify the date of the month on which you want to automatically create an archive using a number (for example "1" for the first day of the month).
-time	The hour of the day at which you want to automatically create an archive.
-initialpause	Optional. Specify whether you want to initially pause the archive job when you create it.
-useglacierfordatafiles	Optional. Only when archiving to an Amazon cloud. Specify this option if you want to use Amazon Glacier for archiving data files.

Examples:

Archive all recovery points with creation dates starting from 04/30/2012 02:55 PM for all machines on the Core:

```
>cmdutil /archive -core 10.10.10.10 -user administrator -password 23WE@#$$sdd -path d:\work\archive -startdate "04/30/2012 02:55 PM" -all
```

Archive recovery points that fall within a date range for two protected machines:

```
>cmdutil /archive -core 10.10.10.10 -user administrator -password 23WE@#$$sdd -protectedserver "10.20.30.40" "20.20.10.1" -path d:\work\archive -startdate "04/30/2012 02:55 PM" -enddate "05/31/2012 11:00 AM"
```

Archive all recovery points with creation dates starting from 04/30/2012 02:55 PM for all machines on the Core to a cloud storage account with the name "Amazon S3" and container named "Container":

```
>cmdutil /archive -scheduled -core 10.10.10.10 -user administrator -password 23WE@#$$sdd -path "ArchiveOnCloud" -cloudaccountname "Amazon S3" -cloudcontainer "Container" -startdate "04/30/2012 02:55 PM" -all -recycleaction incremental
```

Create a scheduled archive for the last day of every month for machine 10.20.30.40 and replace pre-existing archived data pertaining to this Core:

```
>cmdutil /archive -scheduled -core 10.10.10.10 -user administrator -password 23WE0#$sdd -path "d:\work\archive" -recycleaction replacethiscore -scheduletype lastdayofmonth -time "10:00 PM"
```

Edit the path of an existing scheduled archive configuration:

```
>cmdutil /archive -scheduled -edit -id F595F697-2126-4F77-AE93-27AE2A022AF1 -protectedserver 10.20.30.40 -path "d:\work\Newarchive"
```

Edit the path and schedule type of an existing scheduled archive configuration:

```
>cmdutil /archive -scheduled -edit -id F595F697-2126-4F77-AE93-27AE2A022AF1 -protectedserver 10.20.30.40 -path "d:\work\Newarchive" -scheduletype daily -time "10:00 PM"
```

CancelActiveJobs

Use the `cancelactivejobs` command to cancel the execution of all in-progress jobs of a specific type, such as transfer or replication.

Usage

The usage for the command is as follows:

```
/cancelactivejobs [-protectedserver [name : IP address] : -a[ll]] -core [host name] -user [user name] -password [password] -jobtype [job type filter]
```

Command Options

The following table describes the options available for the `cancelactivejobs` command:

Table 3: CancelActiveJobs command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote core host machine. If you specify a password, you must also provide a user name. If none is provided, the logged-in user's credentials are used.
-protectedserver	Determines the protected machine on which the jobs should be canceled.

Option	Description
-all	Select and cancel events of specified type for all protected servers.
-jobtype	Optional. Specifies job type filter. Available values are: <ul style="list-style-type: none"> • 'transfer' (data transfer) • 'repository' (repository maintenance) • 'replication' (local and remote replications) • 'backup' (backup and restore) • 'bootcdbuilder' (create boot CDs) • 'diagnostics' (upload logs) • 'exchange' (Exchange Server files check) • 'export' (recovery point export) • 'pushinstall' (deploy agents) • 'restore' (recovery point restore) • 'rollup' (recovery point rollups) • 'sqlattach' (agent attachability checks) • 'mount' (mount repository) <p>By default, all jobs of the specified type are canceled.</p>

Example:

Cancel all transfer jobs on Core 10.10.10.10:

```
>cmdutil /cancelactivejobs -core 10.10.10.10:8006 -user administrator -password
23WE@#$sdd -jobtype transfer
```

CheckRepository

You can use the CheckRepository command to verify the integrity of an existing DVM repository created in AppAssure Core or Rapid Recovery Core.

Usage

The usage for the command is as follows:

```
/checkrepository -repository [repository name] | -all [check all repositories] -core
[host name] -user [user name] -password [password] name] -force
```

Command Options

The following table describes the options available for the CheckRepository command:

**Table 4: CheckRepository
command options**

Option	Description
-?	Display this help message. Optional.
-core	Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine. Optional.
-user	The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used. Optional.
-password	The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-all	Optional. This option checks all DVM repositories associated with the Core.
-repository	The name of the DVM repository. Optional.
-force	This option performs the check without your confirmation.

Example:

Start checking the DVM repository:

```
>cmdutil /checkrepository -repository "Repository1" -core 10.10.10.10 -user administrator -password 23WE@#sdd
```

ConfigureAgentMigration

This command lets you move the recovery points of a protected machine from an AppAssure repository to a Rapid Recovery repository. This command also reassigns the protected machine to the new repository.

Usage

The usage for the command is as follows:

```
/configureagentmigration -core [host name] -user [user name] -password [password] name] -agentname [name of the protected machine] -targetrepository [repository name] -lastrecoverypointdate [MM/dd/yyyy HH:mm:ss tt] -asnightlyjob
```

Command Options

The following table describes the options available for the `ConfigureAgentMigration` command:

Table 5: ConfigureAgentMigration command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local

Option	Description
	machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-agentname	The name of the protect machine you want to migrate.
-targetrepositoryname	The name of the repository to which you want to migrate the protected machine.
-lastrecoverypointdate	Optional. The date and time of the last recovery point you want to migrate. Migration will not occur for recovery points older than the specified date and time. If you do not specify a date and time, then all recovery points for the protected machine will migrate.
-asnightlyjob	Optional. Use this option if you want the command to occur as a nightly job rather than during peak business hours.

Example:

Migrate the protected machine from an AppAssure repository to a Rapid Recovery repository:

```
>cmdutil /configureagentmigration -agentname localhost -targetrepositoryname repository1 -lastRecoveryPointDate "10/15/2014 3:19:10 PM" -asNightlyJob
```

CreateArchiveRepository

When you create an archive repository, you create a destination for the contents of a scheduled archive. This feature lets you mount an archived recovery point and restore a machine without importing the archive.

Usage

The usage for the command is as follows:

```
/createarchiverepository -core [host name] -user [user name] -password [password] name] -name [archive repository name] -path [path to the archive] -archiveusername [network user name] -archivepassword [network password] -cloudaccountname [name of the cloud account] -cloudcontainer [name of the cloud container]
```

Command Options

The following table describes the options available for the `CreateArchiveRepository` command:

Table 6: CreateArchiveRepository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Required. The name of the archive repository.
-path	The path to the existing archive. It can be a local, network, or cloud location. For example: d:\work\archive or \\servername\sharename.
-archiveusername	Optional. This option is the login to the remote machine. It is required for a network path only.
-archivepassword	Optional. This option is the password for the remote machine. It is only required for a network path only.
-cloudaccountname	Optional. This option is the display name for an existing cloud account. It is required for a cloud path only.
-cloudcontainer	Optional. The cloud container is where the archive is located. It is required for a cloud path only.

Examples:

Create an archive repository with the name "NewArchive:"

```
>cmdutil /createarchiverepository -name NewArchive -core 10.10.10.10 -user administrator -password 23WE@#$sdd -path d:\work\archive
```

Additionally, if an archive contains more than one location, then the command should include paths for all of the segments ordered from 1 to N, where N equals the number of segments.

Create an archive repository with the name "NewSegmentArchive:"

```
>cmdutil /createarchiverepository -name NewSegmentArchive -path1 \\RemmoteServer1\Share\Archive\Segment1 - archiveusername1 Administrator - archivepassword1 23WE@#$sdd -path2 Archives\NewSegment -cloudcontainer2 ArchiveContainer -cloudaccountname AmazonS3Local - path3 d:\work\archive\Third
```

CreateBootCD

This command lets you create a bare metal restore (BMR) boot CD without using the Rapid Recovery Core Console.

Usage

The usage for the command is as follows:

```
/createbootcd -ip [IP address] -mask [mask] -defaultgateway [defaultgateway] -  
dnsserver [dnsserver] -vncpassword [vncpassword] -vncport [vncport] -isofilepath  
[destination for the boot image]
```

Command Options

The following table describes the options available for the `CreateBootCD` command:

Table 7: CreateBootCD command options

Option	Description
-?	Display this help message.
-ip	Optional. This option specifies the IP address of the target BMR machine. By default, it generates automatically.
-mask	Optional. This option specifies the subnet mask of the target BMR machine. By default, it generates automatically.
-defaultgateway	Optional. This option specifies the default gateway of the target BMR machine. By default, it generates automatically.
-dnsserver	Optional. This option specifies the DNS server for the target BMR machine. By default, it generates automatically.
-vncpassword	Optional. This option specifies the user password for an existing UltraVNC account. By default, this option is empty.
-vncport	Optional. This option specifies the port to use for UltraVNC. You can change it only if you used the <code>-vncpassword</code> option. By default, the port is 5900.
-isofilepath	Optional. This option specifies the patch to the boot CD file. The default path is <code>C:\ProgramData\AppRecovery\Boot CDs</code> .

Example:

Create a boot CD:

```
>cmdutil /createbootcd -ip 192.168.20.188 -mask 255.255.255.0 -defaultgateway  
192.168.20.2 -dnsserver 192.168.20.2 -isofilepath D:\bcd\newbcd3.iso
```

CreateEncryptionKey

The `createencryptionkey` command lets you create a phrase to use for securing the data associated with a specified Core.

Usage

The usage for the command is as follows:

```
/createencryptionkey -core [host name] -user [user name] -password [password name] -name [encryption key name] -comment [comment or description of key]
```

Command Options

The following table describes the options available for the `CreateEncryptionKey` command:

Table 8: CreateEncryptionKey command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Required. The name of the repository.
-passphrase	The passphrase of the encryption key that you want to create.
-comment	Optional. A comment on or a description of the encryption key that you want to create.

Example:

Create an encryption key without a comment:

```
>cmdutil /createencryptionkey -name EKname -passphrase password
```

Create an encryption key with a comment:

```
>cmdutil /createencryptionkey -name EKname -passphrase password -comment "This is a comment."
```

CreateNASRepository

Use the `createnasrepository` command to create a new NAS repository in Azure.

Usage

The usage for the command when creating a NAS repository is as follows:

```
/createnasrepository -name [repository name] -storageaccountid [storageaccountid] -datadirectory [datadirectory] -maxsize [maxsize] -dedupe cachesize [dedupe cachesize] -concurrentOperations [concurrentOperations] -comment [comment] -core [host name] -user [login] -password [password]
```

Command Options

The following table describes the options available for the `createnasrepository` command:

Table 9: CreateNASRepository command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Repository name.
-storageaccountid	ID of the Azure storage account that will serve as the container for repository data.
-datadirectory	Path to a directory on the local file system for storing deduplication and metadata caches, index files, logs, and other information.
-maxsize	Maximum size of repository. Available units are GB and TB.
-dedup cachesize	Optional. Amount of memory to be allocated for deduplication cache. Available units are B, KB, MB, and GB. The default value is 1.5 GB.
-comment	Optional. Description of repository.
-concurrentoperations	Optional. Maximum number of operations that can be pending at one time. Value by default: 64.

Examples:

Create a NAS repository:

```
>cmdutil /createnasrepository -name "Repository 1" -storageaccountid AzureStorageID  
-maxsize 200 Gb -datadirectory d:\repository\data -core 10.10.10.10:8006 -user  
administrator -password 23WE@#$sdd
```

CreateRepository

Use the `createrepository` command to create a new DVM repository on a local machine or on a shared location.

Note: This command is deprecated.

Usage

The usage for the command when creating a DVM repository is as follows:

```
/createrepository -name [repository name] -size [size allocated for repository] [[-
datapath [datapath] -metadatapath [metdatapath] -uncpath [path for data and
metadata] -shareusername [user name for share location] -sharepassword [password for
share user name] -concurrentoperations [number of operations to occur at one time] -
core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `createrepository` command:

Table 10: CreateRepository command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Repository name.
-size	Size of repository storage location. Available units are b, Kb, Mb, Gb, Tb, and Pb.
-datapath	For local location only. Determines data path of repository storage location.
-metadatapath	For local location only. Determines metadata path of repository storage location.
-uncpath	For share location only. Determines data and metadata paths of repository storage location.
-shareusername	For share location only. Determines the user name to the share location.
-sharepassword	For share location only. Determines password to share location.
-comment	Optional. Description of repository.
-concurrentoperations	Optional. Maximum number of operations that can be pending at one time. Value by default: 64.

Examples:

Create a DVM repository at a local location:

```
>cmdutil /createrepository -name "Repository 1" -size 200 Gb -datapath
d:\repository -metadatapath d:\repository -core 10.10.10.10:8006 -user
administrator -password 23WE@#sdd
```

Create a DVM repository at a share location:

```
>cmdutil /createrepository -name "Repository 1" -size 200 Gb -uncpath
\\share\repository -shareusername login -sharepassword pass123 -comment "First
repository." -concurrentoperations 8 -core 10.10.10.10:8006 -user administrator -
password 23WE@#$$dd
```

DedupCacheConfig

This command lets you use the Command Line Utility to set the location, size, and metadata location for the primary and secondary cache of a DVM repository.

Usage

The usage for the command when creating a DVM repository is as follows:

```
/dedupcacheconfig -core [host name] -user [user name] -password [password] -primary
[cache location] -secondary [cache location] -metadata [metadata location] -size
[cache size] -restoredefault
```

Command Options

The following table describes the options available for the `dedupcacheconfig` command:

Table 11: DedupCacheConfig command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-primary	Optional. Primary cache location.
-secondary	Optional. Secondary cache location.
-metadata	Optional. Metadata cache location.
-size	Optional. Deduplication cache size in GB.
-restoredefault	Optional. Restore to default deduplication cache configuration. If this parameter is specified, all other parameters are ignored.

Examples:

Set primary deduplication cache location and deduplication cache size:

```
>cmdutil /dedupcacheconfig -primary D:\primary -size 6
```

Set secondary and metadata deduplication location:

```
>cmdutil /dedupcacheconfig -secondary D:\secondary -metadata D:\metadata
```

Restore default deduplication configuration:

```
>cmdutil /dedupcacheconfig -restoredefault
```

DeleteReplication

This command lets you remove a replication configuration from a source Core or target Core, as well as remove replicated recovery points.

Usage

The usage for the command is as follows:

```
/deletereplication -incoming [replication IDs] -outgoing [replication IDs] -  
deleterecoverypoints
```

Command Options

The following table describes the options available for the DeleteReplication command:

Table 12: DeleteReplication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-incoming	The identifier (ID) of the incoming replication that should be deleted. It could be a remote Core ID or a host name. Use the word "all" to delete all replications. Note: You can specify different protected machines for different replications by using the following pattern: Replication1:Agent1,Agent2;Replication2:Agent2,Agent3. If you do not specify a machine after the colon (:), the replication is deleted for all replicated machines.
-outgoing	The identifier (ID) of the outgoing replication that should be deleted. It could be a remote Core ID or a host name. Use the word "all" to delete all replications. Note: You can specify different protected machines for different replications by using the following pattern: Replication1:Agent1,Agent2;Replication2:Agent2,Agent3. If you do not

Option	Description
	specify a machine after the colon (:), the replication is deleted for all replicated machines.
-deletepoints	Specify which recovery points, if any, of the replicated machine that you want to remove.

Example:

Delete all incoming and all outgoing replications:

```
>cmdutil /deletereplication -incoming all -outgoing all
```

Delete two outgoing replications with all machines:

```
>cmdutil /deletereplication -outgoing TargetCore1;TargetCore2
```

Delete one protected machine from incoming replication and delete recovery points:

```
>cmdutil /deletereplication -incoming TargetCore1:10.10.10.10 -deletepoints
```

DeleteRepository

You can use the DeleteRepository command to remove an entire DVM repository created in AppAssure Core or Rapid Recovery Core.

i NOTE: This command is deprecated.

Usage

The usage for the command is as follows:

```
/deleterepository -core [host name] -user [user name] -password [password] name] -  
name [repository name] | -a [all repositories]
```

Command Options

The following table describes the options available for the DeleteRepository command:

Table 13: DeleteRepository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also

Option	Description
	have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-a	Optional. This option deletes all DVM repositories associated with the Core.
-name	The name of the DVM repository you want to delete.

Example:

Delete all DVM repositories:

```
>cmdutil /deleterepository -a
```

Delete the repository with the name "RepositoryName:"

```
>cmdutil /deleterepository -name RepositoryName
```

DeleteTieredRepository

You can use the `DeleteTieredRepository` command to remove a tiering repository created from a Rapid Recovery Core.

NOTE: This command is deprecated.

Usage

The usage for the command is as follows:

```
/deletetieredrepository -name [repository name] -deletecontent [delete all repository content] -rdshost [tiered repository host name]
```

Command Options

The following table describes the options available for the `DeleteTieredRepository` command:

Table 14: DeleteTieredRepository command options

Option	Description
-?	Display this help message.
-name	Required. The name of the tiered repository.
-deletecontent	Required. Specifies whether all repository content should be deleted. If you want to delete all, use <code>true</code> ; if you do not want to delete all content, use <code>false</code> .
-rdshost	Optional. The name of the tiered repository host, such as the DR server. Use this option when the repository does not exist on the current Core.

Example:

Delete tiering repository:

```
>cmdutil /deletetieredrepository -name NewTieredRepo -deletecontent true -  
rdshost localhost
```

DeployToAzure

You can use the `deploytoazure` command to export a virtual machine (VM) to a Microsoft Azure cloud account.

Usage

The usage for the command is as follows:

```
/deploytoazure -core [host name] -user [user name for Core]  
                -password [password for Core] -protectedserver [name | IP  
address] -volumes  
                [volume names | all] -destinationcontainer [Azure destination  
container]  
                -deploymentname [name of deployment] -subscriptionid [Azure  
subscription ID]  
                -cloudservicename [cloud service name] -vmname [virtual machine  
name] -vmsize  
                [virtual machine size] -endpointname [rdp | ssh] -protocol [tcp  
| udp]  
                -publicremoteaccessport [public port number] -  
privateremoteaccessport [private  
port number]
```

Command Options

The following table describes the options available for the `DeployToAzure` command:

Table 15: DeployToAzure command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
<code>-protectedserver</code>	Protected machine with recovery points that you want to export.
<code>-volumes</code>	Optional. List of additional volume names for the deploy. If you use the value <code>all</code> or use no value, then all volumes deploy.
<code>-destinationcontainer</code>	The name of the Azure destination container you want to use for the deploy.
<code>-deploymentname</code>	The name of the deployment.
<code>-subscriptionid</code>	The Azure subscription ID.
<code>-cloudservicename</code>	The name of the Azure cloud service.
<code>-vmname</code>	The name of the virtual machine.
<code>-vmsize</code>	The size of the virtual machine; for example, <code>A0</code> , <code>Basic_A4</code> , or <code>Standard_G1</code> .
<code>-endpointname</code>	The Azure endpoint protocol used only for remote access <code>rdp</code> or <code>ssh</code> . The default value is <code>rdp</code> .
<code>-protocol</code>	The protocol used only for remote access <code>tcp</code> or <code>udp</code> . The default value is <code>tcp</code> .
<code>-publicremoteaccessport</code>	The public port for using remote access. The default value is 3389.
<code>-privateremoteaccessport</code>	The private port for using remote access. The default value is 3389.
<code>-privateagentport</code>	Optional. The Agent port. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-publicagentport</code>	Optional. The external Agent port. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-privatetransferport</code>	Optional. The TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.
<code>-publictransferport</code>	Optional. The external TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.

Example:

Deploy data to Azure:

```
>cmdutil /deploytoazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0
```

Deploy data to Azure using a specified endpoint:

```
>cmdutil /deploytoazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0 -endpointname ssh -protocol udp -publicremoteaccessport 1555 -privateremoteaccessport 22
```

Deploy data to Azure with specified Agent and transfer endpoint when the `-privateagentport` option has a user-defined value of 8006. The parameter for `-publicagentport` uses the special value 0, which is copied from `-privateagentport`. The parameter for `-privatetransferport` uses the special value 0, which is taken from the Agent configuration. The parameter for `-publictransferport` uses the special value 0, which is copied from `-privatetransferport`:

```
>cmdutil /deploytoazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0 -privateagentport 8006 -publicagentport 0 -privatetransferport 0 -publictransferport 0
```

Deploy data to Azure using all available disks:

```
>cmdutil /deploytoazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0 -privateagentport 8006 -publicagentport 0 -privatetransferport 0 -publictransferport 0 -Volumes all
```

Dismount

Use the `dismount` command to dismount a mounted recovery point specified by the `-path` option, dismount points for the selected agent by the `-protectedserver` parameter, or dismount all mounted recovery points—all.

Usage

The usage for the command is as follows:

```
/dis[mount] -core [host name] -user [user name] -password [password] [-all | -protectedserver [name | IP address] | -path [location]
```

Command Options

The following table describes the options available for the `dismount` command:

Table 16: Dismount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Dismount all mounted recovery points.
-protectedserver	Dismount all mounted recovery points for current agent.
-path	Dismount selected mount point.

Example:

Dismount a recovery point that was mounted to folder c:\mountedrecoverypoint:

```
>cmdutil /dismount -core 10.10.10.10 -user administrator -password 23WE@#sdd -path
c:\mountedRecoveryPoint
```

DismountArchiveRepository

After retrieving the information you want from a mounted archive, you should dismount the archive to avoid potential issues.

Usage

The usage for the command is as follows:

```
/dismountarchiverepository -core [host name] -user [user name] -password [password]
name] -name [archive repository name]
```

Command Options

The following table describes the options available for the `DismountArchiveRepository` command:

Table 17: DismountArchiveRepository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Required. The name of the archive repository.

Examples:

Dismount the repository named "NewArchive:"

```
>cmdutil /dismountarchiverepository -name NewArchive -core 10.10.10.10 -user administrator -password 23WE@#sdd -path d:\work\archive
```

DismountRemote

Use the `dismountremote` command to dismount a mounted recovery point mounted from a remote location.

Usage

The usage for the command is as follows:

```
/dismountremote -core [host name] -user [user name] -password [password] [-all | -protectedserver [name | IP address] | -protectedserver [name | IP address] - path [location]
```

Command Options

The following table describes the options available for the `dismountremote` command:

Table 18: DismountRemote command options

Option	Description
-?	Display this help message.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-all	Dismount all mounted recovery points.
-protectedserver	Dismount all mounted recovery points for current agent.
-path	Dismount selected mount point.

Example:

Dismount a remotely mounted recovery point by a specific path:

```
>cmdutil /dismountremote -core 10.10.10.10 -user administrator -password 23WE@#$sdd
-protectedserver "11.11.11.11" -path "C:\ProgramData\AppRecovery\MountPoints\LMU_
DESKTOP-IA8FI3J-2022-03-21T142354\F__\"
```

Dismount all remotely mounted recovery points for specified protected server:

```
>cmdutil /dismountremote -core 10.10.10.10 -user administrator -password 23WE@#$sdd
-protectedserver "11.11.11.11"
```

Dismount all remotely mounted recovery points for all protected servers:

```
>cmdutil /dismountremote -core 10.10.10.10 -user administrator -password
23WE@#$sdd -all
```

EditEsxServer

You can use the `editesxserver` command whenever you want to make changes to the number of VMware ESX (i) virtual machines that you want to protect agentlessly.

Usage

The usage for the command is as follows:

```
/editEsxServer -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -add | -remove -virtualMachines [virtual
machines collection | all] -autoprotect [object ID or name collection]
```

Command Options

The following table describes the options available for the `editesxserver` command:

Table 19: EditEsxServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to edit vCenter and ESX(i) objects for a specific protected machine.
-add	Use this option to add a specified vCenter or ESXi object.
-remove	Use this option to remove a specified vCenter or ESXi object.
-virtualmachines	Optional. This option lets you list the virtual machines that you want to protect.
-autoprotect	Optional. This option lets you list the new virtual machines that you want to automatically protect.

Examples:

Automatically protect specific vCenter or ESXi objects of a vCenter or ESXi server with the Core:

```
>cmdutil /editEsxServer -protectedserver 10.10.8.150 -add -autoprotect "Folder1"
"Folder2"
```

EditHyperVCluster

You can use the `edithypervcluster` command whenever you want to add or remove a Hyper-V cluster or virtual machine using agentless protection.

Usage


The usage for the command is as follows:

```
/edithypervcluster -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -add | -remove -virtualMachines [virtual
machines collection | all] -shareddisks [name/path collection | all]
```

Command Options

The following table describes the options available for the `edithypervcluster` command:

Table 20: EditHyperVCluster command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine.  NOTE: You must enclose the name in double quotes.
-protectedserver	The name of the protected cluster from which you want to add or remove virtual machines or shared virtual disks.
-add	Use this option to add virtual machines or shared virtual disks under protection.
-remove	Use this option to remove a virtual machine or shared virtual disks from protection.
-virtualmachines	Optional. This option lets you list the clusters or virtual machines that you want to protect. Separate the names by spaces and enclose the names of virtual machines in double quotes.
-deleterecoverypoints	Optional. This option can only be used with the "-remove" parameter. Use it to delete all recovery points for specified virtual machines.
-shareddisks	Optional. List the shared virtual disks that you want to protect or remove, separated by spaces. The name of the shared virtual disk must be enclosed double quotes.

Example:

Protect a specific Hyper-V cluster with the Core:

```
>cmdutil /edithypervcluster -protectedserver 10.10.8.150 -add -shareddisks  
C:\SharedDisks\Folder1
```

EditHyperVServer

You can use the `edithypervserver` command whenever you want to add or remove a Hyper-V server using agentless protection.

Usage

The usage for the command is as follows:

```
/edithypervserver -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -add | -remove -virtualmachines [virtual machines collection | all]
```

Command Options

The following table describes the options available for the `edithypervserver` command:

Table 21: EditHyperVServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to specify Hyper-V objects for a specific protected machine.
-add	Use this option to add specific Hyper-V objects under protection.
-remove	Use this option to remove specific Hyper-V objects from protection.
-virtualmachines	Optional. This option lets you list the virtual machines that you want to protect. Separate the names by spaces and enclose the names of virtual machines in double quotes.

Example:

Protect all of the virtual machines for a specific Hyper-V server:

```
>cmdutil /edithypervserver -protectedserver 10.10.8.150 -add -virtualmachines all
```

EditOracleDBVerifyNightlyJob

Use the command `editoracledbverifynightlyjob` to enable or disable this nightly job for specific Oracle machines that are under protection.

Usage

The usage for the command is as follows:

```
/editoracledbverifynightlyjob -core [host name] -user [user name] -password  
[password] -protectedserver [name | IP address] [-enable | -disable] [-global]
```

Command Options

The following table describes the options available for the `editoracledbverifynightlyjob` command:

Table 22: EditOracleDBVerifyNightlyJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle DBVerify nightly job.
-enable	Use this option to enable the DBVerify nightly job for the specified protected machine.
-disable	Use this option to disable the DBVerify nightly job for the specified protected machine.
-global	Use this option to apply the specified setting as the default for this Core.
-all	This option applies the specified changes for every protected machine that has at least one Oracle instance installed.

Example:

Enable the Oracle DBVerify nightly job for a protected server:

```
>cmdutil /editoracledbverifynightlyjob -core 10.10.127.42 -user admin -password  
676df#df -protectedserver 10.10.34.88 -enable
```

EditOracleLogTruncationNightlyJob

Use the command `editoraclelogtruncationnightlyjob` to enable or disable this nightly job for specific Oracle machines that are under protection and to set the deletion policy and retention duration for the logs.

Usage

The usage for the command is as follows:

```
/editoraclelogtruncationnightlyjob -core [host name] -user [user name] -password
[password] -protectedserver [name | IP address] [-enable | -disable] [-global] [-
usedefault] -deletionpolicy [automatic | keepnewest | keepspecificnumber] -
retentionduration [duration value] -retentionunit [day | week | month | year] -
numberoffiles [number of archive files to create]
```

Command Options

The following table describes the options available for the `editoraclelogtruncationnightlyjob` command:

Table 23: EditOracleLogTruncationNightlyJob command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-protectedserver</code>	Use this option to specify the protected machine for which you want to enable Oracle log truncation as a nightly job.
<code>-enable</code>	Use this option to enable log truncation for the specified protected machine. This is the default option and can be omitted.
<code>-disable</code>	Use this option to disable log truncation for the specified protected machine.
<code>-global</code>	Use this option to apply the specified setting as the default for this Core.
<code>-all</code>	This option applies the specified changes for every protected machine that has at least one Oracle instance installed.
<code>-usedefault</code>	Optional. Use this option to apply the default Core settings to the specified machine, which may also be set by using the <code>-global</code> option.
<code>-deletionpolicy</code>	Optional. This option must be represented by one of the following values: <ul style="list-style-type: none"> "automatic" "keepnewest" "keepspecificnumber"
<code>-retentionduration</code>	Optional. This value determines the length of time to keep a log before truncating and is constrained to positive integer values. If using the "keepnewest" value of the <code>-deletionpolicy</code> option, a retention duration value is required.
<code>-retentionunit</code>	Optional. This option identifies the time unit for the <code>-retentionduration</code> option. It must be represented by one of the following values: <ul style="list-style-type: none"> "day" "week"

Option	Description
	<ul style="list-style-type: none"> • "month" • "year"
-numberoffiles	Optional. This option sets the number of recent archive log files to keep. If using the "keepspecificnumber" value of the -deletionpolicy option, a number of files value is required.

Examples:

Enable the Oracle log truncation nightly job for a protected server:

```
>cmdutil /editoraclelogtruncationnightlyjob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -enable
```

Enable the Oracle log truncation nightly job (when -enable is the default option) for a protected server and configure the deletion policy as "keepnewest" with the logs kept for 10 days:

```
>cmdutil /editoraclelogtruncationnightlyjob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -deletionpolicy keepnewest -retentionduration 10 -retentionunit day
```

EnableOracleArchiveLogMode

Use the command `enableoraclearchivelogmode` to enable or disable this mode for specific Oracle machines that are under protection.

Usage

The usage for the command is as follows:

```
/enableoraclearchivelogmode -core [host name] -user [user name] -password [password] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `enableoraclearchivelogmode` command:

Table 24: EnableOracleArchiveLogMode command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle archive log mode.

Example:

Enable the Oracle archive log mode for a protected server:

```
>cmdutil /enableoraclearchivelogmode -core 10.10.127.42 -user admin -password
676df#df -protectedserver 10.10.34.88
```

FileSearch

The `filesearch` command lets you search for a specific file among the recovery points in a repository, which helps you determine which recovery point you need to mount for a restore.

Usage

The usage for the command is as follows:

```
/filesearch -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -startdate [start date] -enddate [end date]
-filemasks [file masks] -paths [paths] -subdiroff -ntfsfastoff -limitsearch
[limit search]
```

Command Options

The following table describes the options available for the `filesearch` command:

Table 25: FileSearch command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the

Option	Description
	Oracle archive log mode.
-startdate	The earliest date of a period within you want to conduct your search. Use the date pattern "MM/DD/YYYY HH:mm:ss AM."
-enddate	The latest date of a period within you want to conduct your search. Use the date pattern "MM/DD/YYYY HH:mm:ss AM."
-filemasks	A combination of fixed and wildcard characters to search for the file. It can be one string or an array of strings. All masks should be separated by a space; for example: -filemasks "first" "second."
-paths	Optional. If there are specific directories in which you want to search, use this option to list the paths. It can be one string or an array of strings. All directories should be separated by a space; for example: -paths "E:\" "C:\Program Files."
-subdiroff	Optional. By default, the file search is performed in subdirectories. Use this option if you want to turn this feature off and not search in subdirectories.
-ntfsfastoff	Optional. By default, the file search is performed using the NTFS fast algorithm. If you want to perform the search without this feature, specify this option.
-limitsearch	Optional. Use this option to limit the number of search results. The default value is 1000.

Examples:

Perform a file search with one file mask:

```
>cmdutil /filesearch -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver 10.10.10.10 -filemasks "sample"
```

Perform a file search with multiple file masks in specified directories and without the NTFS fast algorithm:

```
>cmdutil /filesearch -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver 10.10.10.10 -filemasks "sample" "second" -paths "C:\dir" -
ntfsfastoff
```

Force

The `force` command forces a snapshot of a specified protected server. Forcing a snapshot lets you force a data transfer for the current protected machine. When you force a snapshot, the transfer will start immediately or will be added to the queue. Only the data that has changed from a previous recovery point will be transferred. If there is no previous recovery point, all data on the protected volumes will be transferred.

Usage

The usage for the command is as follows:

```
/force [snapshot | base] -core [host name] -user [login] -password [password] -all |
-protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `force` command:

Table 26: Force command options

Option	Description
<code>-?</code>	Display this help message.
<code>-force</code>	Optional. Type of snapshot to create. Available values: 'snapshot' (incremental snapshot) and 'base' (base image snapshot). By default, an incremental snapshot is performed.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-all</code>	Force snapshots for all machines on the core.
<code>-protectedserver</code>	Force a snapshot for a specific protected machine.
<code>-synthetic</code>	Force a synthetic snapshot.

Example:

Force a snapshot for all machines on the Core:

```
>cmdutil /force snapshot -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -all
```

ForceAttach

The `forceattach` command lets you force a SQL database files attachability check. When you force an attachability check, the check begins immediately.

Usage

The usage for the command is as follows:

```
/forceattach -core [host name] -user [user name] -password [password] -  
protectedserver [name | IP address] -rpn [number | numbers] | -time [time string]
```

Command Options

The following table describes the options available for the `forceattach` command:

Table 27: ForceAttach command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine against which to perform the attachability check.
-rpn	The sequential number of a recovery point against which to perform checks (run command /list rps to obtain the numbers). To perform checks against multiple recovery points with a single command, you can specify several numbers separated by spaces.
-time	Select a recovery point by its creation time. You must specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify the date and time values of the time zone set on your PC.

Example:

Perform attachability checks for recovery points with numbers 5 and 7:

```
>cmdutil /forceattach -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver 10.10.5.22 -rpn 5 7
```

ForceChecksum

The `forcechecksum` command lets you force an integrity check of any Exchange Message Databases (MDBs) present on the specified recovery point or points. When you force a checksum check, the command begins immediately.

Usage

The usage for the command is as follows:

```
/forcechecksum -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -rpn [number | numbers] -time [time string]
```

Command Options

The following table describes the options available for the `forcechecksum` command:

Table 28: ForceChecksum command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine against which to perform the checksum check.
-rpn	The sequential number of a recovery point against which to perform checks (run command /list rps to obtain the numbers). To perform checks against multiple recovery points with a single command, you can specify several numbers separated by spaces.
-time	Select a recovery point by its creation time. You must specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify the date and time values of the time zone set on your PC.

Example:

Perform a checksum check for recovery points with numbers 5 and 7:

```
>cmdutil /forcechecksum -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -rpn 5 7
```

ForceLogTruncation

Forcing log truncation lets you perform this job one time, on-demand. It immediately truncates the logs for the specified SQL Server agent machine.

Usage

The usage for the command is as follows:

```
/[forcelogtruncation | flt] -core [host name] -user [user name] -password [password] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `forcelogtruncation` command:

Table 29: ForceLogTruncation command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine against which to perform log file truncation.

Example:

Force log truncation for a protected server:

```
>cmdutil /forcelogtruncation -core 10.10.10.10 -user administrator -password
23WE@#$sdd -protectedserver 10.10.20.20
```

ForceMount

Use the `forcemount` command to conduct an one-time recovery point mountability check. This determines whether or not the specified recovery point or recovery points can be mounted and used to restore backed up data. You must list either one or more specific recovery points on which to conduct the check, or a time range during which the recovery points were created.

Usage

The usage for the command is as follows:

```
/forcemount -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -rpn [number | numbers] | -time [time string]
```

Command Options

The following table describes the options available for the `forcemount` command:

Table 30: ForceMount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine against which to perform a mountability check.
-rpn	The sequential number of a recovery point against which to perform checks (run command /list rps to obtain the numbers). To perform checks against multiple recovery points with a single command, you can specify several numbers separated by spaces.
-time	Select a recovery point by its creation time. You must specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify the date and time values of the time zone set on your PC.

Example:

Perform mountability checks for recovery points with numbers 5 and 7:

```
>cmdutil /forcemount -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.20.20 -rpn 5 7
```

ForceOptimizationJob

The `forceoptimizationjob` command lets you perform optimize a repository on demand.

Usage

The usage for the command is as follows:

```
/forceoptimizationjob -repository [repository name] | -all -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `forceoptimizationjob` command:

Table 31: ForceOptimizationJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user

Option	Description
	are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	The name of the repository that you want to optimize.
-all	Use this option to perform the optimization job on all repositories for this Core.

Example:

Force a repository optimization job:

```
>cmdutil /forceoptimizationjob -repository "Repository 1" -core 10.10.10.10 -user administrator -password 23WE@#sdd
```

ForceReplication

Use the `forcereplication` command to force a one-time transfer of replicated data from the source core to the target core. You can replicate one specific protected server or replicate all protected servers. The protected servers must be already configured for replication.

Usage

The usage for the command is as follows:

```
/[forcereplication |frep] -core [host name] -user [user name] -password [password] -targetcore [host name] -all | -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `forcereplication` command:

Table 32: ForceReplication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used

Option	Description
-targetcore	Host name of the target core against which replication should be forced.
-protectedserver	The protected machine you want to replicate.
-all	Force replication for all machines being replicated to the target core.

Example:

Force replication for a protected server on a specific target core:

```
>cmdutil /forcereplication -target core 10.10.10.10 -protectedserver 10.20.30.40
```

ForceRollup

Use the `forcerollup` command to force the rollup of recovery points on a protected machine.

Usage

The usage for the command is as follows:

```
/[forcerollup | fro] -core [host name] -user [user name] -password [password] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `forcerollup` command:

Table 33: ForceRollup command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Optional. Protected machine against which to perform rollup.

Example:

Force rollup for agent 10.10.10.1 on the Core:

```
>cmdutil /forcerollup -core 10.10.10.10 - user administrator -password 23WE@#sdd -  
protectedserver 10.10.10.1
```

ForceScheduledArchive

The `forcescheduledarchive` command lets you force an archive to occur outside of its regularly scheduled time.

Usage

The usage for the command is as follows:

```
/forcescheduledarchive -core [host name] -user [user name] -password [password] -all  
-ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `forcescheduledarchive` command:

Table 34: ForceScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Use this option to force all scheduled archives.
-ids	The identifier (ID) or IDs separated by spaces of the scheduled archives that you want to force.

Examples:

Force all scheduled archives:

```
>cmdutil /forcescheduledarchive -all
```

Force one scheduled archive:

```
>cmdutil /forcescheduledarchive -ids 6c123c39-5058-4586-bd0c-7c375e72017b
```

ForceVirtualStandby

Exporting data from a protected machine to a virtual machine creates a virtual standby machine. If you have continuous virtual export set up, you can use this command to force Rapid Recovery to export data on demand, regardless of the predetermined schedule.

Usage

The usage for the command is as follows:

```
/forcevirtualstandby -core [host name] -user [user name] -password [password login]
-protectedserver [name] | -all
```

Command Options

The following table describes the options available for the `ForceVirtualStandby` command:

Table 35: ForceVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or space-separated names of virtualized machines.
-all	This command specifies whether to force all scheduled virtual exports.

Examples:

Force all virtual standby exports:

```
>cmdutil /forcevirtualstandby -all
```

Force virtual standby for two machines:

```
>cmdutil /forcevirtualstandby -protectedserver 10.10.35.48 10.10.35.69
```

GetOracleInstanceMetadata

The `getoracleinstancemetadata` command lets you retrieve the detailed metadata for a specified Oracle instance.

Usage

The usage for the command is as follows:

```
/getoracleinstancemetadadata -core [host name] -user [user name] -password [password]
-protectedserver [name | IP address] -instancename [Oracle instance SID]
```

Command Options

The following table describes the options available for the `getoracleinstancemetadadata` command:

Table 36: GetOracleInstanceMetadata command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.
-instancename	The Oracle SID from which you want to fetch metadata.

Example:

Get detailed metadata for the named Oracle instance. If no metadata credentials are set, then only summary metadata displays:

```
>cmdutil /getoracleinstancemetadadata -core 10.10.127.42 -user admin -password -
676df#df -protectedserver 10.10.34.88 -instancename ORCL
```

Help

The `help` command displays a list of the available commands and their definitions. It also provides copyright and version details.

Usage

The usage for the command is as follows:

```
/help
```

Example:

Request Command Line help:

```
>cmdutil /help
```

List

The `list` command returns information about all recovery points, active jobs, completed jobs, failed jobs, invalid (failed) recovery points, valid (passed) recovery points, mounts, protected servers, volumes, virtualized servers, unprotected volumes, clusters, protection groups, SQL databases, Exchange databases, replicated servers, and repositories for the specified agent or list of servers currently protected by the Core. The most recent records return by default. You can list all records or specify how many records display by using a number parameter. This parameter should contain the letter "l" for the latest recovery points and "f" for the first recovery point. Each recovery point has its own number, which the administrator can use for mounting.

Usage

The usage for the command is as follows:

```
/list [rps | passed | failed | mounts | volumes | protectedservers | activejobs |  
completed jobs | failedjobs | virtualizedservers | unprotectedvolumes | clusters |  
protectiongroups | sqldatabases | exchangemailstores | replicatedservers |  
repositories] -protectedserver [name | IP address] -core [host name] -user [user  
name] -password [password] -number [all | l<number> | f<number> | <number>] -jobtype
```

Command Options

The following table describes the options available for the `list` command:

Table 37: List command options

Option	Description
-?	Display this help message.
-list	Select one of the following options: <ul style="list-style-type: none">all recovery points ('rps')valid recovery points ('passed')invalid recovery points ('failed')mounts ('mounts')protected volumes ('volumes')unprotected volumes ('unprotectedvolumes')protected machines ('protectedservers')active jobs ('activejobs')failed jobs ('failedjobs')

Option	Description
	<ul style="list-style-type: none"> completed jobs ('completedjobs') virtualized servers ('virtualizedservers') clusters ('clusters') protection groups ('protectiongroups') SQL Server databases ('sqldatabases') MS Exchange databases ('exchangemailstores') replicated servers ('replicatedservers') repositories ('repositories')
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	For show jobs only. Display all events of a specific type (active/failed/completed) on the core server.
-protectedserver	Protected machine with recovery points to display.
-number	<p>Optional. Number of data items to display. Use only with the following specifiers: 'rps', 'activejobs', 'completedjobs', 'failedjobs'. Available values are:</p> <ul style="list-style-type: none"> all (fetch all data items) l[number] or [number] (fetches top ## data items) f[number] (fetches first ## data items) <p>Only takes effect when displaying recovery points and jobs.</p>
-jobtype	<p>Optional. Filter output by job type. Available values include:</p> <ul style="list-style-type: none"> 'transfer' (data transfer) 'repository' (repository maintenance) 'replication' (local and remote replications) 'backup' (backup and restore) 'bootcdbuilder' (create boot CDs) 'diagnostics' (upload logs) 'exchange' (Exchange Server files check) 'export' (recovery point export) 'pushinstall' (deploy agents) 'restore' (recovery point restores)

Option	Description
	<ul style="list-style-type: none"> • 'rollup' (protected machine rollups) • 'sqlattach' (agent attachability checks) • 'mount' (mount repository)

Examples:

List the 30 most recent recovery points:

```
>cmdutil /list rps -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -number 130
```

View all failed data transfer jobs performed by a protected machine:

```
>cmdutil /list failed jobs -core 10.10.10.10 -user administrator -password
23WE@#sdd -protectedserver 10.10.5.22 -number all -jobtype transfer
```

ListAzureVMSizes

Use the `listazurevmsizes` command to determine the size of a virtual machine (VM) that has been deployed to a Microsoft Azure cloud account.

Usage

The usage for the command is as follows:

```
/listazurevmsizes -storageaccountname [Azure storage account name] -core [host
name] -user [user name] -password [password] -protectedserver [name | IP
address] or [IP]
```

Command Options

The following table describes the options available for the `listazurevmsizes` command:

Table 38: ListAzureVMSizes command options

Option	Description
-?	Display this help message.
-cloudaccountname	Optional when specifying -storageaccountname. Specify the name of the Azure cloud account.
-storageaccountname	Optional when specifying -cloudaccountname. Specify the name of the Azure storage account.
-subscriptionid	The Azure subscription ID.

Option	Description
-cloudservicename	The name of the Azure cloud service.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Examples:

View a list of the available virtual machine sizes for the cloud account Account1:

```
>cmdutil /listazurevm sizes -cloudaccountname Account1 -cloudservicename Service
```

View a list of the available virtual machine sizes for the storage account named "teststorage:"

```
>cmdutil /listazurevm sizes -storageaccountname teststorage -cloudservicename Service
```

ListOracleInstances

The `listoracleinstances` command lets you retrieve a list of all Oracle instances running on a specified protected machine.

Usage

The usage for the command is as follows:

```
/listoracleinstances -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `listoraclesinstances` command:

Table 39: ListOracleInstances command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.

Example:

List the Oracle instances running on the specified protected server:

```
>cmdutil /listoracleinstances -core 10.10.127.42 -user admin -password -676df#df -protectedserver 10.10.34.88
```

ManagementCertificates

Use the `managementcertificates` command to view a list of the Microsoft Azure management certificates.

Usage

The usage for the command is as follows:

```
/managementcertificates -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -list [list certificates] -upload [publish setting file path] -delete [subscription IID]
```

Command Options

The following table describes the options available for the `managementcertificates` command:

Table 40: ManagementCertificates command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of a protected machine.
-list	Optional. List of Azure management certificates.

Option	Description
-upload	Optional. The location of the publish settings file from which you want to upload Azure management certificates.
-delete	Use this option to delete an Azure management certificate by using the subscription ID.

Examples:

View a list of the Azure management certificates previously added on the Core:

```
>cmdutil /managementcertificates
>cmdutil /managementcertificates -list
```

Upload Azure management certificates from a publish settings file:

```
>cmdutil /managementcertificates -upload "c:\file.publishsettings"
```

Delete an Azure management certificate using the subscription ID:

```
>cmdutil /managementcertificates -delete "111111-22222-33333-4444-555555"
```

Mount

The `mount` command mounts a snapshot of one or more drives. You can specify whether the mount should be read, write, or read-only with previous writes. The default selection is read-only.

Usage

The usage for the command is as follows:

```
/mount -core [host name] -user [user name] -password [password] -protectedserver
[name | IP address] -mounttype [read | write | readOnlyWithPreviousWrites] -drives
[drive names] -volumes [volume names] -path [location] -rpn [number | numbers] | -
time [time string]
```

Command Options

The following table describes the options available for the `mount` command:

Table 41: Mount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with a recovery point or points to be mounted.
-mounttype	Optional. Specifies a mount mode. Available values are 'read' (read-only), 'readOnlyWithPreviousWrites' (read-only with previous writes), 'write' (writable). The default mode is read-only.
-volumes	Optional. List of volume names to mount. If not specified, all volumes are mounted. Values must be enclosed in double quotes and separated by spaces; for example: "c:" "d:". Do not use trailing slashes in volume names.
-path	Path to a folder on the core server to which the recovery point should be mounted. If one does not exist, a folder is automatically created.
-rpn	Optional. The sequential number of a recovery point to mount (use /list rps command to get the numbers). Specify several space-separated numbers to mount multiple recovery points with a single command. In this case data from each recovery point will be stored in a separate child folder. Note: if neither option -time nor -rpn is specified then the most recent recovery point that successfully passed integrity check will be mounted.
-time	Optional. Determines recovery point or points to be selected for mount. Available values include: 'latest', 'passed', exact time in the format "mm/dd/yyyy hh:mm tt" (for instance, "2/24/2012 09:00 AM"). Keep in mind to specify date time values of the time zone set on your PC. If neither the -time option nor the -rpn option is specified, then the most recent recovery point that successfully passed an integrity check is mounted.
-localdrive	Optional. Perform mount to user disk on local PC.

Examples:

Mount the most recent recovery points containing volumes "c:\" and "d:\" in the read-only mode:

```
>cmdutil /mount -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver 10.10.5.22 -path c:\mountedrecoverypoint -mounttype read -
volumes "c:" "d:"
```

Mount recovery points with numbers 2 and 7:

```
>cmdutil /mount -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver 10.10.5.22 -path c:\mountedrecoverypoint -rpn 2 7
```

MountArchiveRepository

To restore data from an archive in Rapid Recovery, you must first mount it.

Usage

The usage for the command is as follows:

```
/mountarchiverepository -core [host name] -user [user name] -password [password] -name [archive repository name]
```

Command Options

The following table describes the options available for the `mountarchiverepository` command:

Table 42: MountArchiveRepository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Required. The name of the archive repository.

Examples:

Mount the repository named "NewArchive:"

```
>cmdutil /mountarchiverepository -name NewArchive
```

NewCloudAccount

Use the `NewCloudAccount` command to add an account for a cloud provider to the Rapid Recovery Core. You can then use the account to store archives for retention or replication.

Usage

The usage for the command is as follows:

```
/newcloudaccount -core [host name] -user [user name] -password [password] -displayname [name for the account] -type [cloud account provider] -username [user name for the account] -key [secret key] -region [region for account] tenanatid [tenant ID] -authurl [authorization URL]
```

Command Options

The following table describes the options available for the `NewCloudAccount` command:

Table 43: NewCloudAccount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-displayname	The name you want to use for the cloud account.
-type	The type of cloud account. Supported values include: <ul style="list-style-type: none"> • amazon • openstack • rackspace • windowsazure • "windows azure" • azure
-username	The user name for the cloud account you want to add. This is the credential you use in the authentication process. The property has the following variations based on the cloud type: <ul style="list-style-type: none"> • Amazon - Access Key • OpenStack - User Name • Rackspace - User Name • Windows Azure - Storage Account Name
-key	The authentication key for the cloud account you want to add. This is the credential you use in the authentication process. The property has the following variations based on the cloud type: <ul style="list-style-type: none"> • Amazon - Secret Key • OpenStack - API Key • Rackspace - API Key • Windows Azure - Access Key
-region	The region of the cloud account you want to add. This option is required only for OpenStack and Rackspace accounts.
-tenantid	The ID you use to authenticate an OpenStack cloud account. This option is required only for OpenStack accounts.
-authurl	The URL you use to authenticate an OpenStack cloud account. This option is required only for OpenStack accounts.

Examples:

Add a new cloud account with the name "Amazon S3 Account" with the access key "akey" and the secret key "skey:"

```
>cmdutil /newcloudaccount -displayname "Amazon S3 Account" -type amazon -username  
akey -key skey
```

OpenDvmRepository

Use this command to open an existing DVM repository created in AppAssure Core or Rapid Recovery Core.

Usage

The usage for the command is as follows:

```
/opendvmrepository -localpath [local path] -sharepath [network share path] -  
shareusername [user name for network share] -sharepassword [network share password]
```

Command Options

The following table describes the options available for the `OpenDvmRepository` command:

Table 44: OpenDvmRepository command options

Option	Description
-?	Display this help message.
-localpath	The path to the folder with a DVM repository on the local Core.
-sharepath	The path to the folder with the DVM repository on a CIFS share.
-shareusername	The user name you use to log in to the shared folder.
-sharepassword	The password you use to log in to the shared folder.

Example:

Open an existing DVM repository on the local machine:

```
>cmdutil /opendvmrepository -localpath E:\Repository
```

Pause

An administrator can pause snapshots, export to virtual machines, or replicate a Core. The `pause` command accepts three parameters: `snapshot`, `vmexport`, and `replication`. Only one parameter can be specified. A snapshot can be paused until a certain time, if a time parameter is specified.

A user can pause replication in three ways:

- On a source Core for all protected machines.(-[outgoing]).
The administrator must specify the remote machine name with the outgoing replication pairing to pause outgoing replication on the source Core:


```
>cmdutil /pause replication /o 10.10.12.10
```
- On the source Core for a single protected machine.(-protectedserver):


```
>cmdutil /pause replication /protectedserver 10.10.12.97
```
- On target Core (-incoming).
If the local Core is a target Core, the administrator can pause replication by specifying the source Core using the incoming parameter:


```
>cmdutil /pause replication /i 10.10.12.25
```

Usage

The usage for the command is as follows:

```
/pause [snapshot | vmexport | replication] -core [host name] -user [user name] -password [password] -all | -protectedserver [name | IP address] -incoming [host name] | outgoing [host name] -time [time string]
```

Command Options

The following table describes the options available for the `pause` command:

Table 45: Pause command options

Option	Description
-?	Display this help message.
-pause	[snapshots], [replication] or [vmexport]. Optional.
-core	Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you

Option	Description
	must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Optional. Pause all agents on the selected Core.
-protectedserver	Optional. Pause current protected server.
-incoming	Optional. Host name of the remote core that replicates to the core machine.
-outgoing	Optional. Host name of the remote target core to which data is replicated.
-time	Optional. The time in the format 'Day-Hours-Minutes' when the snapshots will be resumed (only for snapshots pause).

Examples:

Pause creating snapshots for a specific protected server:

```
>cmdutil /pause snapshot -core 10.10.10.10 -user administrator -password 23WE@#$sdd  
-protectedserver 10.10.10.4
```

Pause creating snapshots for a protected machine and resume it after three days, 20 hours, and 50 minutes:

```
>cmdutil /pause snapshot -core 10.10.10.10 -user administrator -password 23WE@#$sdd  
-protectedserver 10.10.10.4 -time 3-20-50
```

Pause export to virtual machine for all protected machines on the core:

```
>cmdutil /pause vmexport -core 10.10.10.10 /user administrator -password  
23WE@#$sdd -all
```

Pause outgoing replication on the core for a specific protected machine:

```
>cmdutil /pause replication -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -protectedserver 10.10.1.76
```

Pause outgoing replication for all protected machines on the target core:

```
>cmdutil /pause replication -core 10.10.10.10 -user administrator -password -  
23WE@#$sdd -outgoing 10.10.1.63
```

Pause incoming replication for all machines on the target core:

```
>cmdutil /pause replication -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -incoming 10.10.1.82
```

Protect

The `protect` command adds a server under protection by a core.

Usage

The usage for the command is as follows:

```
/protect -core [host name] -user [user name] -password [password] -repository [name]  
-agentname [name | IP address] -agentusername [user name] -agentpassword [password]  
-agentport [port] -volumes [volume names]
```

Command Options

The following table describes the options available for the `protect` command:

Table 46: Protect command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-agentname	Name or IP address of the server you want to protect.
-agentusername	User name for the server to be protected.
-agentpassword	Password for the server to be protected.
-agentport	Protected server port number.
-volumes	List of volumes to protect. Values must be enclosed in double quotes and separated by a space. Do not use trailing slashes in volume names; for example: "c:" "d:".

Example:

Protect specific volumes of a server with the Core:

```
>cmdutil /protect -core 10.10.10.10 -username administrator -password 23WE@#$sdd -
repository "Repository 1" -agentname 10.10.9.120 -agentport 5002 -agentusername
administrator agentpassword 12345 -volumes "c:" "d:"
```

ProtectCluster

The `protectcluster` command adds a cluster under protection by a core.

Usage

The usage for the command is as follows:

```
/protectcluster -core [host name] -user [user name] -password [password] -repository
[name] -clustername [name | IP address] -clusterusername [user name] -
clusterpassword [password] -clusterport [port] -clustervolumes [volume names] -
clusternodes [cluster nodes collection]
```

Command Options

The following table describes the options available for the `protectcluster` command:

Table 47: ProtectCluster command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-clustername	Name or IP address of the cluster you want to protect.
-clusterusername	User name for the cluster to be protected.
-clusterpassword	Password for the cluster to be protected.
-clusterport	Protected cluster server port number.
-clustervolumes	List of volumes to protect. Values must be enclosed in double quotes and separated by a space. Do not use trailing slashes in volume names; for example: "c:" "d:".
-clusternodes	List of the cluster nodes and the volumes you want to protect on each node.

Example:

Protect specific volumes of a cluster server with the Core:

```
>cmdutil /protectcluster -core 10.10.10.10 -username administrator -password
23WE@#$sdd -repository "Repository 1" -clustername 10.10.8.150 -clusterport 8006 -
clusterusername clusterAdmin clusterpassword password -volumes
"C:\ClusterStorage\Volume1" -clusternodes nodeName 10.10.8.150 volumes "c:" nodeName
10.10.8.151 volumes "c:"
```

ProtectEsxServer

You can use the `protectesxserver` command whenever you want to add a VMware ESX(i) virtual machine to protection.

Usage

The usage for the command is as follows:

```
/protectesxserver -core [host name] -user [user name] -password [password] -
repository [repository name] -server [name | IP address] -serverusername [user name]
-serverpassword [password for server login] -serverport [port] -virtualMachines
[virtual machines collection | all] -autoProtect [object ID or name collection]
```

Command Options

The following table describes the options available for the `protectesxserver` command:

Table 48: ProtectEsxServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-server	The name or IP address for the vCenter or ESXi server you want to protect.
-serverusername	The user name for logging in to the vCenter or ESXi server that you want to protect.
-serverpassword	The password for logging in to the vCenter or ESXi server that you want to protect.
-serverport	Optional. The port number for the vCenter or ESXi server that you want to protect.
-virtualmachines	Optional. This option lets you list the virtual machines that you want to protect.
-autoprotect	Optional. This option lets you list new virtual machines that you want to automatically protect.

Example:

Protect specific virtual machines from a vCenter or ESXi server with the Core:

```
>cmdutil /protectesxserver -core 10.10.10.10 -user admin -password password -  
repository "Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root -  
serverpassword password -virtualmachines "VM1" "VM2" -autoprotect "Folder1"
```

ProtectHyperVCluster

The `protecthypervcluster` command adds a Hyper-V cluster under protection by a Core using agentless protection.

Usage

The usage for the command is as follows:

```
/protecthypervcluster -core [host name] -user [user name] -password [password] -
repository [name] -server [name | IP address] -serverusername [user name] -
serverpassword [password] -serverport [port] -virtualmachines [virtual machines
collection | all] -isagentprotection
```

Command Options

The following table describes the options available for the `protecthypervcluster` command:

Table 49: ProtectHyperVCluster command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-server	Name or IP address of the Hyper-V server that you want to protect.
-serverusername	User name for the Hyper-V server to be protected.
-serverpassword	Password for the Hyper-V server to be protected.
-serverport	Optional. Protected Hyper-V server port number.
-virtualmachines	Optional. List of virtual machines to protect. Values must be enclosed in double quotes and separated by a space. If you exclude this parameter, only the Hyper-V cluster container is protected.
-isagentprotection	Optional. Use this option to protect a cluster with an Agent in each guest virtual machine, which is false by default.
-autoprotect	Optional. This option enables the autoprotect feature for the Hyper-V server. It is not compatible with the <code>-isagentprotection</code> option.

Example:

Protect specific virtual machines of a Hyper-V cluster:

```
>cmdutil /protecthypervcluster -core 10.10.10.10 -username admin -password password
-repository "Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root
clusterpassword password -virtualmachines "VM1" "VM2" -autoprotect
```

ProtectHyperVServer

The `protecthypervserver` command adds a Hyper-V server under protection by a Core using agentless protection.

Usage

The usage for the command is as follows:

```
/protecthypervserver -core [host name] -user [user name] -password [password] -  
repository [name] -server [name | IP address] -serverusername [user name] -  
serverpassword [password] -serverport [port] -virtualmachines [virtual machines  
collection | all] -isagentprotection
```

Command Options

The following table describes the options available for the `protecthypervserver` command:

Table 50: ProtectHyperVServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-server	Name or IP address of the Hyper-V server that you want to protect.
-serverusername	User name for the Hyper-V server to be protected.
-serverpassword	Password for the Hyper-V server to be protected.
-serverport	Optional. Protected Hyper-V server port number.
-virtualmachines	Optional. List of virtual machines to protect. Values must be enclosed in double quotes and separated by a space. If you exclude this parameter, only the Hyper-V cluster container is protected.

Example:

Protect specific virtual machines of a Hyper-V server:

```
>cmdutil /protecthypervserver -core 10.10.10.10 -username admin -password password -
repository "Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root
clusterpassword password -virtualmachines "VM1" "VM2"
```

RemoveAgent

The `RemoveAgent` command lets you remove a protected machine from the protection of a Core and optionally delete the recovery points of the removed machine. If you do not delete the recovery points, Rapid Recovery retains and labels them as a recovery points only machine.

Usage

The usage for the command is as follows:

```
/removeagent -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -deleterecoverypoints
```

Command Options

The following table describes the options available for the `RemoveAgent` command:

Table 51: RemoveAgent command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the server you want to remove from protection.
-deleterecoverypoints	Optional. Deletes all recovery points for the machine you want to remove.

Example:

Remove a machine from protection and delete the associated recovery points:

```
>cmdutil /removeagent -protectedserver 10.10.1.1 -deleterecoverypoints
```

RemoveArchiveRepository

You can use the `removearchiverepository` command to delete a repository from the Rapid Recovery Core.

Usage

The usage for the command is as follows:

```
/removearchiverepository -core [host name] -user [user name] -password [password]
name] -name [archive repository name]
```

Command Options

The following table describes the options available for the `removearchiverepository` command:

Table 52: RemoveArchiveRepository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-name	Required. The name of the archive repository.

Examples:

Remove the repository named "NewArchive" from the local Core:

```
>cmdutil /removearchiverepository -name NewArchive
```

RemovePoints

The `removepoints` command lets you delete specific recovery points of a protected machine.

Usage

The usage for the command is as follows:

```
/removepoints -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -rpn [number | numbers] | -time [time string]
```

Command Options

The following table describes the options available for the `removepoints` command:

Table 53: RemovePoints command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the server for which you want to delete recovery points
-rpn	Optional. The sequential number of a recovery point to be deleted (use <code>/list rps</code> command to get the numbers). Specify several space-separated numbers to delete multiple recovery points with a single command.
-time	Optional. Determines which recovery point or points to delete by creation time. Specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify the date time values of the time zone set on your PC.

Example:

Delete the recovery points with number 5 and 7:

```
>cmdutil /removepoints -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -rpn 5 7
```

RemoveScheduledArchive

Use this command to discontinue an existing Rapid Recovery scheduled continuous archive.

Usage

The usage for the command is as follows:

```
/removescheduledarchive -core [host name] -user [user name] -password [password] name] -all -ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `removescheduledarchive` command:

Table 54: RemoveScheduledArchive command options

Option	Description
-?	Display this help message.

Option	Description
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-all</code>	This option specifies whether to remove all scheduled archives associated with this Core.
<code>-ids</code>	Use this option to list the ID or IDs for each scheduled archive you want to remove. Separate multiples IDs with spaces.

Examples:

Remove all scheduled archives:

```
>cmdutil /removescheduledarchive -all
```

Remove one scheduled archive:

```
>cmdutil /removescheduledarchive -ids 6c123c39-5058-4586-bd0c-7c375e72017b
```

RemoveVirtualStandby

Use this command to discontinue the continuous export of data to a virtual machine in the Rapid Recovery command utility.

Usage

The usage for the command is as follows:

```
/removevirtualstandby -core [host name] -user [user name] -password [password login]
-protectedserver [name] | -all
```

Command Options

The following table describes the options available for the `removevirtualstandby` command:

Table 55: RemoveVirtualStandby command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or space-separated names of virtualized machines.
-all	This command specifies whether to remove all scheduled virtual exports.

Examples:

Remove all virtual standby exports:

```
>cmdutil /removevirtualstandby -all
```

Remove virtual standby export for two machines:

```
>cmdutil /removevirtualstandby -protectedserver 10.10.35.48 10.10.35.69
```

Replicate

Use the `Replicate` command to set up replication between two Rapid Recovery Cores.

Usage

The usage for the command is as follows:

```
/replicate -request [email | email customer ID] -targetserver [host name | hostname port | hostname user name password | hostname port user name password] -replicationname [name] -seeddrive [localpath | network path username password] [comment] -protectedserver [name | name repository]
```

Command Options

The following table describes the options available for the `Replicate` command:

Table 56: Replicate command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.

Option	Description
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used
<code>-request</code>	Optional. Specify this option if you want to use a subscription to a third-party provider of off-site backup and disaster recovery services.
<code>-targetserver</code>	The name of the server where you want to establish replication. It includes the following parameters: <ul style="list-style-type: none"> port user name password The port parameter is optional, with a default of 8006. If you used the <code>request</code> option, you should also use the user name and password for the target server.
<code>-replicationname</code>	Optional. Use the name of the replication job if you do not use the <code>request</code> option.
<code>-seeddrive</code>	Optional. Use this option to specify a seed drive for the initial data transfer. The comment parameter is optional.
<code>-protectedserver</code>	The list of protected machines you want to replicate. If you use the <code>request</code> option, list only the names or IP addresses of protected machines. Otherwise, list both protected machines and the corresponding remote repository name.

Example:

Replicate two protected machines to the remote Core using a seed drive from a network share:

```
>cmdutil /replicate -targetserver 10.10.1.100 Administrator 123Q -replicationname
ReplicationName -seeddrive Network \\10.10.1.100\seeddrive Administrator 123Q -
protectedserver 10.10.1.1 Repository1 10.10.1.2 Repository2
```

Replication

Use the `replication` command to control existing replication between two Rapid Recovery Cores and manage pending replication requests.

i NOTE: This command succeeds the `Replicate` command, which establishes the connection—called pairing—between the Cores and uses a seed drive for the initial data transfer. For more information about this command, see [Replicate](#).

Usage

The usage for the command is as follows:

```
/replication [-list [incoming | outgoing | pending] -accept | -deny | -ignore | -
delete | -edit] -id [replication ID] -protectedserver [name | name repository] -
responsecomment [comment] -deleterecoverypoints -scheduletype [type] -dailystarttime
[time] -dailyendtime [time] -weekdaystarttime [time] -weekdayendtime [time] -
weekendstarttime [time] -weekendendtime [time]
```

Command Options

The following table describes the options available for the `replication` command:

Table 57: Replication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-list	The list of incoming or outgoing replication jobs or pending replication requests.
-accept	Accepts the replication request.
-deny	Denies the replication request.
-ignore	Ignores the replication request.
-delete	Use this option to delete an existing replication job or a machine from the replication job. Specify only the <code>-id</code> parameter to delete an entire replication relationship, or specify both the <code>-id</code> and <code>-protectedserver</code> parameters to delete only specific machines from replication.
-edit	Edits the schedule of existing replication jobs.
-id	The identifier for the replication job or pending replication request. It can be a remote Core ID, host name, customer ID, email address, or pending replication request ID.
-protectedserver	When responding to a replication request, use this option to apply your response to list of protected servers with a repository name or ID. Use the parameter "all" to apply response to all requested machines.
-responsecomment	The comment you provide with the response to a pending replication request.
-deleterecoverypoints	Use this option if specific recovery points from a deleted replicated machine should also be removed.
-schoeduletype	If you use the <code>-edit</code> option, this option specifies the type of replication schedule. Include one of the following four values: <ul style="list-style-type: none">• <code>atalltimes</code> - Automatically replicate at any time.• <code>daily</code> - Replicate daily. Specify the <code>-dailystarttime</code> and <code>-dailyendtime</code> parameters.• <code>custom</code> - When using daily replication, use this value to schedule replication on weekdays or weekends. Specify the <code>-weekdaystarttime</code>, <code>-weekdayendtime</code>, <code>-weekendstarttime</code>, and <code>-weekendendtime</code> parameters.
-dailystarttime	Use only for the daily value of the <code>-schoeduletype</code> option. It is used to

Option	Description
	establish a window of time for when replication should occur. Use this option to specify the earliest time of day when you want replication to start. Confirm with Dev.
-dailyendtime	Use only for the daily value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of day when you want replication to start. Confirm with Dev.
-weekdaystarttime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the earliest time of a weekday when you want replication to start. Confirm with Dev.
-weekdayendtime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of a weekday when you want replication to start. Confirm with Dev.
-weekendstarttime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the earliest time of the weekend when you want replication to start. Confirm with Dev.
-weekendendtime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of the weekend when you want replication to start. Confirm with Dev.

Examples:

List all incoming replication:

```
>cmdutil /replication -list incoming
```

Accept pending replication requests for two protected machines:

```
>cmdutil /replication -accept -id customer@email.address -protectedserver 10.10.1.1
Repository1 10.10.1.2 Repository2 -responsecomment A response comment
```

Deny a pending replication request:

```
>cmdutil /replication -deny -id customer@email.address
```

Delete existing replication with replicated recovery points:

```
>cmdutil /replication -delete -id RemoteServerHostname -deleterecoverypoints
```

Remove two machines from existing replication:

```
>cmdutil /replication -delete -id "156d7a46-8e44-43f4-9ed8-60d998e582bf" -
protectedserver 10.10.1.1 10.10.1.2
```

Edit schedule of replication with specified weekday and weekend times:

```
>cmdutil /replication -edit -id RemoteServerHostName -scheduletype custom -  
weekdaystarttime "9:00 AM" -weekdayendtime "6:00 PM" -weekendstarttime "9:00 AM" -  
weekendendtime "6:00 PM"
```

ResizeDedupeCache

Use the `resizededupecache` command to change the size of the deduplication cache location for the Azure repository.

Usage

The usage for the command when resizing the deduplication cache location for an Azure repository is as follows:

```
/resizededupecache -core [host name] -user [login] -password [password] -repository  
[repository id] -dedupe cachesize [cache size]
```

Command Options

The following table describes the options available for the `resizededupecache` command:

Table 58: ResizeDedupeCache command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	ID of the Azure repository.
-dedupe cachesize	Optional. Amount of memory to be allocated for deduplication cache. Available units are B, KB, MB, and GB. The default value is 1.5 GB.

Examples:

Resize the deduplication cache for an Azure repository:

```
>cmdutil /resizededupecache -repository AzureStorageID -dedupe cachesize 200 Gb -core  
10.10.10.10:8006 -user administrator -password 23WE@#$$sdd
```

RestartCoreService

If the Core service on the Core machine is stopped, use the `restartcoreservice` command to start it again.

Usage

The usage for the command is as follows:

```
/restartcoreservice -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false] -wait [time in seconds]
```

Command Options

The following table describes the options available for the `restartcoreservice` command:

Table 59: RestartCoreService command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."
-wait	Optional. This option indicates that the command should wait until the Core service is fully restarted for the specified period of time in seconds before canceling active jobs.

Example:

Restart the Core service:

```
>cmdutil /restartcoreservice -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true -wait 600
```

RestoreAgent

The `restoreagent` command lets you restore a protected machine or volume from a specific Rapid Recovery recovery point.

Usage

The usage for the command is as follows:

```
/restoreagent -protectedserver [name | IP address] -rpn [recovery point number] -volumes [IDs | names | all] -targetmachine [name] -targetvolume [volume name] -forcedismount -autorestart
```

Command Options

The following table describes the options available for the `restoreagent` command:

Table 60: RestoreAgent command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-protectedserver</code>	The name or IP address of the server you want to restore.
<code>-rpn</code>	The identification number of the recovery point you want to use to restore the machine. To find the correct number, use the command <code>/list rps</code> .
<code>-volumes</code>	The IDs or names of the volumes you want to restore. To restore all protected volumes, use <code>-volumes all</code> .
<code>-targetmachine</code>	The name of the machine to which you want to restore the protected machine.
<code>-targetvolume</code>	The name or ID of the volume to which you want to restore the machine.
<code>-forcedismount</code>	Optional. Use this option to force the dismount of the database on demand.
<code>-autorestart</code>	Optional. Use this command if restarting an Exchange Server machine is necessary.

Example:

Restore a machine to a protected machine with the IP address 192.168.20.130, including the force database dismount option:

```
>cmdutil /restoreagent -protectedserver 192.168.20.130 -rpn 259 -volumes "F:" "E:"  
"C:" -targetmachine 192.168.20.174 -targetvolume "E:" "G:" "F:" -forcedismount
```

RestoreArchive

This command restores an archive from a local archive or share and places the restored data in a specified repository.

Usage

The usage for the command is as follows:

```
/restorearchive -core [host name] -user [user name] -password [password] -all | -
protectedserver [name | IP address] -repository [name] -archiveusername [name] -
archivepassword [password] -path [location]
```

Command Options

The following table describes the options available for the `restorearchive` command:

Table 61: RestoreArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Restore data for all protected machines from the archive files.
-protectedserver	Protected machine with recovery points to restore. You can specify several machine names enclosed in double quotes and separated by spaces.
-repository	Name of a repository on the Core to which the restored recovery points should be placed. The name must be enclosed in double quotes.
-archiveusername	Optional. User name for the remote machine. Required for network path only.
-archivepassword	Optional. Password to the remote machine. Required for network path only.
-path	Location of the archived data to be restored; for example: d:\work\archive or network path \\servername\sharename.

Examples:

Restore archived data for all protected servers:

```
>cmdutil /restorearchive -core 10.10.10.10 -username administrator -password
23WE@#$sdd -all -repository repository1 -path d:\work\archive
```

Restore archived data for specific protected servers:

```
>cmdutil /restorearchive -core 10.10.10.10 -username administrator -password
23WE@#$sdd -protectedserver "10.10.20.30" "20.10.10.5" -repository repository1 -path
d:\work\archive
```

RestoreUrc

The `restoreurc` command lets you restore a protected machine or volume from a specific Rapid Recovery recovery point to a bare-metal machine using the Universal Recovery Console (URC).

Usage

The usage for the command is as follows:

```
/restoreurc -protectedserver [name | IP address] -rpn [recovery point number] -  
volumes [IDs | names | all] -targetmachine [IP address] -urcpassword [password from  
the URC] -targetdisk [disk number | all]
```

Command Options

The following table describes the options available for the `restoreurc` command:

Table 62: RestoreUrc command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the server you want to which you want to restore the URC.
-rpn	The identification number of the recovery point you want to use to restore the machine. To find the correct number, use the command <code>/list rps</code> .
-volumes	The IDs or names of the volumes you want to restore. To restore all protected volumes, use <code>-volumes all</code> .
-targetmachine	The name of the machine to which you want to restore the protected machine.
-urcpassword	The authentication key from the URC.
-targetdisk	The numbers of the disks on which you want to restore the machine. To select all disks from the machine using the URC, use <code>-targetdisk all</code> .

Example:

Restore a machine to disks 0 and 1 of the machine using the URC, when the IP address for the URC machine is 192.168.20.175:

```
>cmdutil /restoreurc -protectedserver 192.168.20.130 -rpn 259 -volumes "C:" "E:" -  
targetmachine 192.168.20.175 -urcpassword ***** -targetdisk 0 1
```

Resume

The administrator can use this command to resume snapshots, export to a virtual machine, and replicate. You must specify your need to resume by a parameter. The following parameters are valid: `snapshot`, `vmexport`, and

replication. See [Pause](#) for more details.

Usage

The usage for the command is as follows:

```
/resume [snapshot | vmexport | replication] -core [host name] -user [user name] -password [password] -all | -protectedserver [name | IP address] -incoming [host name] | outgoing [host name] -time [time string]
```

Command Options

The following table describes the options available for the `resume` command:

Table 63: Resume command options

Option	Description
-?	Display this help message.
-restore	[snapshots], [replication] or [vmexport].
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Resume all agents on the selected Core.
-protectedserver	Resume current protected server.
-incoming	Host name of the remote core that replicates to the core machine.
-outgoing	Host name of the remote target core to which data is replicated.

Examples:

Resume snapshots for specific protected server:

```
>cmdutil /resume snapshot -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.10.4
```

Resume export to a virtual machine for all protected machines on the core:

```
>cmdutil /resume vmexport -core 10.10.10.10 -user administrator -password 23WE@#$sdd -all
```

Resume outgoing replication on the core for a specific protected machine:

```
>cmdutil /resume replication -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -protectedserver 10.10.1.76
```

Resume outgoing replication for all protected machines on the target core:

```
>cmdutil /resume replication -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -outgoing 10.10.1.63
```

Resume incoming replication for all machines on the target core:

```
>cmdutil /resume replication -core 10.10.10.10 -user administrator -password  
23WE@#$sdd -incoming 10.10.1.82
```

ResumeScheduler

This command lets you resume the task scheduler it has been paused.

Usage

The usage for the command is as follows:

```
/resumescheduler -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `resumescheduler` command:

Table 64: ResumeScheduler command options

Option	Description
-?	Display this help message.
-restore	[snapshots], [replication] or [vmexport].
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Example:

Resume snapshots for specific protected server:

```
>cmdutil /resumescheduler -core 10.10.127.42 -user admin -password 676df#df
```

SeedDrive

You can use a seed drive for the initial data transfer when you establish Rapid Recovery replication.

Usage

The usage for the command is as follows:

```
/seeddrive [-list | -startcopy | -startconsume | -abandon] -path [local | network  
path] -seeddriveusername [user name] -seeddrivepassword [password] -remotecore  
[name] [-targetcore [name or IP] | -protectedserver [name] | -all] -  
usecompatibleformat
```

Command Options

The following table describes the options available for the `seeddrive` command:

Table 65: SeedDrive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-list	The list of outstanding seed drives with extended information.
-startcopy	Start copying data to the seed drive.
-startconsume	Start consuming the seed drive.
-abandon	Abandon the outstanding seed drive request.
-path	The local or network path of the seed drive.
-seeddriveusername	Optional. The user name for the network location of the seed drive.
-seeddrivepassword	Optional. The password for the network location of the seed drive.
-targetcore	Optional. Use only with the <code>-copy</code> option. It is the name or IP address of the remote Core. All protected machines replicating to this Core receive seed drive recovery points.
-remotecore	Use only with the <code>-consume</code> option. It is the name of the remote Core from which the seed drive recovery points are created or consumed.
-protectedserver	The name or IP address of the protected machine you are using to create or consume the seed drive of recovery points. For example: <code>-protectedserver "10.10.60.48" "10.10.12.101."</code>

Option	Description
-all	This option specifies whether to consume or copy all of the available protected machines.
-usecompatibleformat	The new archiving format offers improved performance, however it is not compatible with older Cores. Use this option when working with a legacy AppAssure Core. Confirm with dev.

Examples:

List outstanding seed drives:

```
>cmdutil /seeddrive -list
```

Copy two protected machines to the seed drive on the network share:

```
>cmdutil /seeddrive -startcopy -remotecore TargetCoreName -path \\10.10.1.1\Share\Seed\ -seeddriveusername Administrator -seeddrivepassword 12345 -usecompatibleformat
```

Starting consuming the seed drive:

```
>cmdutil /seeddrive -startconsume -path \\10.10.1.1\Share\Seed\ -seeddriveusername Adminsitrator -seeddrivepassword 12345 -remotecore RemoteCoreName
```

Abandon an outstanding seed drive request:

```
>cmdutil /seeddrive -abandon RemoteCoreHostName
```

SetAgentMetadataCredentials

The `setagentmetadatacredentials` command sets the metadata credentials for a specified protected machine.

Usage

The usage for the command is as follows:

```
/setagentmetadatacredentials -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -target [default | SQL | Exchange] -metadatausername [user name] -metadatapassword [password] -sqlinstancename [SQL instance name] -usewindowsauthentication
```

Command Options

The following table describes the options available for the `setagentmetadatacredentials` command:

Table 66: SetAgentMetadataCredentials command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.
-target	Optional. The type of metadata, such as SQL, Exchange, or default.
-metadatausername	Optional. The metadata-related login.
-metadatapassword	Optional. The metadata-related password.
-sqlinstancename	Optional. The specific SQL instance name. Use this option in conjunction with the -target "sql."
-usewindowsauthentication	Optional. Use this option if your SQL credentials are also used for Windows authentication.

Example:

Set credentials for Exchange metadata:

```
>cmdutil /setagentmetadatacredentials -core 10.10.10.10 -user administrator -
password -23WE@#$sdd -protectedserver 10.10.20.20 -target exchange -metadatausername
administrator -metadatapassword 123#
```

SetOracleMetadataCredentials

The `setoraclemetadatacredentials` command lets you set the metadata credentials for a specified Oracle instance.

Usage

The usage for the command is as follows:

```
/setoraclemetadatacredentials -core [host name] -user [user name] -password
[password] -protectedserver [name | IP address] -instancename [Oracle instance
SID] -connectiontype [-basic | TNS] -hostname [host name | IP address] -port
[port number] [-usesid] -instanceservicename [service name] -tnsnetworkalias [TNS
alias] [-usewindowsauthentication] -oracleusername [user name] -oraclepassword
[password] [-edit]
```

Command Options

The following table describes the options available for the `setoraclemetadatacredentials` command:

Table 67: SetOracleMetadataCredentials command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.
-instancename	The Oracle SID from which you want to fetch metadata.
-connectiontype	Use this option to identify the connection type. It must be represented by either <code>basic</code> or <code>TNS</code> .
-hostname	Optional. The name of the Oracle host. Use it for the <code>basic</code> connection type.
-port	Optional. A port number. Use it for the <code>basic</code> connection type.
-usesid	Optional. This option uses the <code>-instancename</code> to identify the Oracle instance. Use it for the <code>basic</code> connection type.
-instanceservicename	Optional. The Oracle instance service name. Use it when the <code>-usesid</code> is not specified and for the <code>basic</code> connection type.
-tnsnetworkalias	Optional. Use this option to identify the TNS network alias when using the <code>TNS</code> connection type.
-usewindowsauthentication	Optional. This option lets you authenticate with your Windows credentials.
-oracleusername	Optional. The user name for the Oracle instance.
-oraclepassword	Optional. The password for the Oracle instance.
-edit	Optional. This option lets you omit any number of options.

Examples:

Set the metadata credentials for the ORCL instance on a protected server using the `basic` connection type:

```
>cmdutil /setoraclemetadatacredentials -core 10.10.127.42 -user admin -password  
-676df#df -protectedserver 10.10.34.88 -instancename ORCL -connectiontype basic  
-hostname localhost -port 1521 -usesid -oracleusername User-ORA -oraclepassword  
676df#df
```

Set the metadata credentials for the ORCL instance on a protected server using the `TNS` connection type and Windows authentication:

```
>cmdutil /setoraclemetadatacredentials -core 10.10.127.42 -user admin -password -  
676df#df -protectedserver 10.10.34.88 -instancename ORCL -connectiontype TNS -  
tnsnetworkalias ORCL_ALIAS -usewindowsauthentication
```

StartExport

The `startexport` command forces a one-time export of data from a protected machine to a virtual server. You can export to an ESXi, VMware Workstation, Hyper-V, or VirtualBox virtual machine. If exporting to ESXi, you must specify thick or thin disk provisioning.

Usage

The usage for the command is as follows:

```
/startexport -exporttype [esxi | vm | hyperv | vb] -core [host name] -user [user  
name] -password [password] -protectedserver [name | IP address] -volumes [volume  
names] -rpn [recovery point number | numbers] | -time [time string] -vmname [virtual  
machine name] -hostname [virtual host name] -hostport [virtual hostport number] -  
hostusername [virtual host user name] -hostpassword [virtual host password] [-ram  
[total megabytes] | -usesourceram] -diskprovisioning [thin | thick] -diskmapping  
[automatic | manual | withvm] -targetpath [location] -pathusername [user name] -  
pathpassword [password] [-uselocalmachine]
```

Command Options

The following table describes the options available for the `startexport` command:

Table 68: StartExport command options

Option	Description
-?	Display this help message.
-exporttype	Perform export of data from protected server to an ESXi server ('esxi'), VMware Workstation server ('vm'), Hyper-V server ('hyperv'), or VirtualBox server ('vb').
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points to be exported.
-volumes	Optional. List of volume names to be exported. If not specified, all volumes will be

Option	Description
	exported. Values must be enclosed in double quotes and separated with spaces; for example: "c:" "d:". Do not use trailing slashes in volume names.
-rpn	Optional. The sequential number of a recovery point to be exported (use Get-RecoveryPoints command to get the numbers). If neither the 'time' nor the 'rpn' option is specified, then the most recent recovery point is exported.
-time	Optional. Determines the recovery point or points to be selected for export. You need to specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Be sure to specify the date time values of the time zone set on your PC. Note: if neither the 'time' nor the 'rpn' option is specified, then the most recent recovery point is exported.
-vmname	The Windows name of the virtual machine.
-hostname	For ESXi and Hyper-V virtual exports only. The virtual server host name.
-linuxhostname	For VirtualBox exports only. The virtual server host name.
-hostport	For ESXi and Hyper-V virtual exports only. The virtual server port number.
-hostusername	For ESXi and Hyper-V virtual exports only. The user name for the virtual server host.
-hostpassword	For ESXi and Hyper-V virtual exports only. The password for the virtual server host.
-ram	Use this option to allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Use this option to allocate the same amount of RAM on the virtual server that the source machine contains.
-diskprovisioning	<p>Use this option for ESXi exports only. Optional. The amount of disk space that you want to allocate on the virtual machine. Use one of the two following specifications:</p> <ul style="list-style-type: none"> • Thick - This specification makes the virtual disk as large as the original drive on the protected machine. • Thin - This specification allocates the amount of actual disk space occupied on the original drive with a few additional megabytes. <p>The default specification is "thin."</p>
-diskmapping	<p>Use this option for ESXi exports only. Optional. This option determines how to map the disks from the protected machine to the virtual machine. Use one of the following values:</p> <ul style="list-style-type: none"> • auto - This value automatically maps the disks. • manual - This value lets you map the disks manually. • withvm - This value stores the virtual disks in a datastore that you select. <p>The default value is "auto."</p>
-targetpath	For VMware Workstation and VirtualBox exports only. This option specifies the local or network path—or Linux path, for VirtualBox only—to the folder where you want to store the virtual machine files
-pathusername	For VMware Workstation exports only. It is the user name for the network machine. It is only required when you specify a network path in the -targetpath option.
-pathpassword	For VMware Workstation exports only. It is the password for the network machine. It is only required when you specify a network path in the -targetpath option.

Option	Description
-uselocalmachine	For Hyper-V exports only. Optional. Use this command to connect to the local Hyper-V server. This option ignores the -hostname, -hostport, -hostusername, and -hostpassword options.

Examples:

Export data to an ESXi virtual machine with a specific name and the same amount of RAM and disk size as the source protected server:

```
>cmdutil /startexport -exporttype esxi -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -vmname Win2008-Smith -hostname 10.10.10.23 -hostport 443 -hostusername root -hostpassword 12QWsdxc@# -usesourceram -diskprovisioning thick
```

Create a VMware Workstation machine file on the local drive with protected data from recovery point #4:

```
>cmdutil /startexport -exporttype vmstation -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -rpn 4 -vmname Win2008-Smith -targetpath c:\virtualmachines -ram 4096
```

Create a Hyper-V machine files to be stored on a remote machine:

```
>cmdutil /startexport -exporttype hyperv -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -vmlocation \\WIN7-Bobby\virtualmachines -hostname 10.10.10.23 -hostport 443 -hostusername root -hostpassword 12QWsdxc@# -ram 4096
```

StartExportAzure

You can use the `startexportazure` command to force the export of data from a protected machine to a Microsoft Azure virtual server.

Usage

The usage for the command is as follows:

```
/startexportazure -core [host name] -user [user name for Core] -password [password for Core] -protectedserver [name | IP address] -volumes [volume names | all] -rpn [number | numbers] -time [time string] -cloudaccountname [Azure account name] -storageaccountname [storage account name] -containername [container name] -foldername [folder name] -deploymentname [deployment name] -destinationcontainer [Azure destination container] -subscriptionid [Azure subscription ID] -cloudservicename [cloud service name] -vmname [virtual machine name] -vmsize [virtual machine size] -endpointname [rdp | ssh] -protocol [tcp | udp] -publicremoteaccessport [public remote access port number] -privateremoteaccessport [private port number]
```

Command Options

The following table describes the options available for the `startexportzure` command:

Table 69: StartExportAzure command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points that you want to export.
-volumes	Optional. List of additional volume names for the deploy. If you use the value <code>all</code> or use no value, the all volumes deploy.
-rpn	Optional. The sequential number of a recovery point that you want to export (use the <code>/list rps</code> command to get the numbers). If neither <code>-time</code> nor <code>-rpn</code> is specified, then the most recent recovery point is exported.
-time	Optional. This option determines the recovery points to select for export. Specify the exact time in the format <code>mm/dd/yyyy hh:mm tt</code> ; for example, <code>2/24/2012 09:00 AM</code> . Keep in mind to specify the date time value of the time zone set on your PC. If neither <code>-time</code> nor <code>-rpn</code> is specified, then the most recent recovery point is exported.
-cloudaccountname	Optional, if the <code>-storageaccountname</code> is specified. Specify the Azure cloud account name.
-storageaccountname	Optional, if the <code>-cloudaccountname</code> is specified. Specify the Azure storage account name.
-containername	The name of the Azure container.
-foldername	Optional. The name of the Azure folder.
-deploymentname	Use this option to specify the name of the deployment. It is required for a deploy after export only.
-destinationcontainer	The name of the Azure destination container you want to use for the deploy.
-subscriptionid	The Azure subscription ID. It is required for a deploy after export only.
-cloudservicename	The name of the Azure cloud service. It is required for a deploy after export only.
-vmname	The name of the virtual machine. It is required for a deploy after export only.
-vmsize	The size of the virtual machine; for example, <code>A0</code> , <code>Basic_A4</code> , or <code>Standard_G1</code> .
-endpointname	The Azure endpoint protocol used only for remote access <code>rdp</code> or <code>ssh</code> . The

Option	Description
	default value is <code>rdp</code> . It is required for a deploy after export only.
<code>-protocol</code>	The protocol used only for remote access <code>tcp</code> or <code>udp</code> . It is required for a deploy after export only. The default value is <code>tcp</code> .
<code>-publicremoteaccessport</code>	The public port for using remote access. The default value is 3389.
<code>-privateremoteaccessport</code>	The private port for using remote access. The default value is 3389.
<code>-privateagentport</code>	Optional. The Agent port. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-publicagentport</code>	Optional. The external Agent port. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-privatetransferport</code>	Optional. The TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.
<code>-publictransferport</code>	Optional. The external TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.

Examples:

Export data to Azure:

```
>cmdutil /startexportazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -cloudaccountname "Cloud Account 1" -containername "mycontainer" -foldername "folder" -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0
```

Export data to Azure using a specified endpoint:

```
>cmdutil /startexportazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -cloudaccountname "Cloud Account 1" -containername "mycontainer" -foldername "folder" -deploymentname Deploy1 -destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname VirtualMachine -vmsize A0 -endpointname ssh -protocol udp -publicremoteaccessport 1555 -privateremoteaccessport 22
```

Export data to Azure with a specified Agent endpoint when the `-privateagentport` option uses the special value 0, which is taken from the Agent configuration. The `-publicagentport` option has the user-defined value of 1888:

```
>cmdutil /startexportazure -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -cloudaccountname "Cloud Account 1" -
```

```
containername "mycontainer" -deploymentname Deploy1 -destinationcontainer container1
-subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname
VirtualMachine -vmsize A0 -privateagentport 0 -publicagentport 1888
```

Export data to Azure with specified Agent and transfer endpoints. The `-privateagentport` option has the user-defined value of 8006. The parameter for `-publicagentport` uses the special value of 0, which is copied from the `-privateagentport` option. The parameter for `-privatetransferport` uses the special value of 0, which is taken from the Agent configuration. The parameter for `-publictransferport` uses the special value 0, which is copied from the `-privatetransferport` option.:

```
>cmdutil /startexportazure -core 10.10.10.10 -user administrator -password
23WE@#$sdd -protectedserver 10.10.5.22 -cloudaccountname "Cloud Account 1" -
containername "mycontainer" -foldername "folder" -deploymentname Deploy1 -
destinationcontainer container1 -subscriptionid "111111-22222-33333-4444-555555" -
cloudservicename Service1 -vmname VirtualMachine -vmsize A0 -privateagentport 8006 -
publicagentport 0 -privatetransferport 0 -publictransferport 0
```

StartOracleDBVerifyJob

Use the command `startoracledbverifyjob` to start the DBVerify job for one or more specified recovery points on a protected server.

Usage

The usage for the command is as follows:

```
/startoracledbverifyjob -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -recoverypointnumber [number | numbers]
```

Command Options

The following table describes the options available for the `startoracledbverifyjob` command:

Table 70: StartOracleDBVerifyJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle DBVerify nightly job.

Option	Description
<code>-recoverypointnumber</code>	The sequential number of a recovery point that you want to export (use the <code>/list rps</code> command to get the numbers). To start the job on multiple recovery points with one command, separate each recovery point number with a space.

Example:

Start the Oracle DBVerify job for the recovery points on the specified protected server:

```
>cmdutil /startoracledbverifyjob -core 10.10.127.42 -user admin -password 676df#df -
protectedserver 10.10.34.88 -recoverypointnumber 1 2
```

StartOracleLogTruncationJob

The command `startoraclelogtruncationjob` lets you start a log truncation job for a specified Oracle instance on a protected server.

Usage

The usage for the command is as follows:

```
/startaclelogtruncationjob -core [host name] -user [user name] -password
[password] -protectedserver [name | IP address] -instancename [instance SID] -
deletionpolicy [automatic | keepnewest | keepspecificnumber] -retentionduration
[duration value] -retentionunit [day | week | month | year] -numberoffiles [number
of archive files to create]
```

Command Options

The following table describes the options available for the `startoraclelogtruncationjob` command:

Table 71: StartOracleLogTruncationJob command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-protectedserver</code>	Use this option to specify the protected machine for which you want to enable Oracle log truncation as a nightly job.

Option	Description
-instancename	The name of the Oracle instance for which you want to start log truncation.
-deletionpolicy	Optional. This option must be represented by one of the following values: <ul style="list-style-type: none"> "automatic" "keepnewest" "keepspecificnumber"
-retentionduration	Optional. This value determines the length of time to keep a log before truncating and is constrained to positive integer values. If using the "keepnewest" value of the -deletionpolicy option, a retention duration value is required.
-retentionunit	Optional. This option identifies the time unit for the -retentionduration option. It must be represented by one of the following values: <ul style="list-style-type: none"> "day" "week" "month" "year"
-numberoffiles	Optional. This option sets the number of recent archive log files to keep. If using the "keepspecificnumber" value of the -deletionpolicy option, a number of files value is required.

Examples:

Start the Oracle log truncation job for the ORCL instance on a specified protected server:

```
>cmdutil /startoraclelogtruncationjob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -instancename ORCL
```

Start the Oracle log truncation job for the ORCL instance on a specified protected server and configure the deletion policy as "keepnewest" with the logs kept for 10 days:

```
>cmdutil /startoraclelogtruncationjob -protectedserver 10.10.34.88 -instancename ORCL -deletionpolicy keepnewest -retentionduration 10 -retentionunit day
```

StopCoreService

Use this command to stop the Core service on a Core machine.

Usage

The usage for the command is as follows:

```
/stopcoreservice -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false] -wait [time in seconds]
```

Command Options

The following table describes the options available for the `stopcoreservice` command:

Table 72: StopCoreService command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."
-wait	Optional. This option indicates that the command should wait until the Core service is fully stopped for the specified period of time in seconds before canceling active jobs.

Example:

Stop the Core service:

```
>cmdutil /stopcoreservice -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true -wait 600
```

SuspendScheduler

This command lets you suspend or pause the task scheduler it has been paused.

Usage

The usage for the command is as follows:

```
/suspendscheduler -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false]
```

Command Options

The following table describes the options available for the `suspendscheduler` command:

Table 73: SuspendScheduler command options

Option	Description
-?	Display this help message.
-restore	[snapshots], [replication] or [vmexport].
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."

Example:

Pause the task scheduler:

```
>cmdutil /suspendscheduler -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true
```

UpdateRepository

The `updaterepository` command adds a new storage location to an existing DVM repository.

i NOTE: This command is deprecated.

Usage

The usage for the command is as follows:

```
/updaterepository -name [repository name] -size [size of the repository] [-datapath [data path] -metadatapath [metadata path] | [-uncpath [UNC path] -shareusername [share user name] -sharepassword [share password] -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `updaterepository` command:

Table 74: UpdateRepository command options

Option	Description
-?	Display this help message.
-name	Repository name.
-size	Size of repository storage location. Available units are b, Kb, Mb, Gb, Tb, and Pb.
-datapath	For local location only. Determines data path of repository storage location.
-metadatapath	For local location only. Determines metadata path of repository storage location.
-uncpath	For share location only. Determines data and metadata paths of repository storage location.
-shareusername	For share location only. Determines user name to share location.
-sharepassword	For share location only. Determines password to share location.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Examples:

Create a new storage location in a local DVM repository:

```
>cmdutil /updaterepository -name "Repository 1" -size 200Gb -datapath d:\repository
-metadatapath d:\repository -core 10.10.10.10:8006 -username administrator -
password 23WE@#sdd
```

Create a storage location for a DVM repository at a shared location:

```
>cmdutil /updaterepository -name "Repository 1" -size 200Gb -uncpath
\\share\repository -shareusername login -sharepassword 23WE@#sdd -core
10.10.10.10:8006 -username administrator -password 23WE@#sdd
```

Version

The `version` command displays information about the version of the Rapid Recovery software installed on the specified server. If you do not specify a core or protected server, the information returned applies to the Core on which you are currently working.

Usage

The usage for the command is as follows:

```
/[version | ver] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `version` command:

Table 75: Version command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Optional. The protected machine for which you want to view version information. If you do not specify a protect machine, the return is information about the Core machine on which you are working.

Example:

Display information about the version of Rapid Recovery installed on the current Rapid Recovery Core:

```
>cmdutil /version
```

VirtualStandby

You can use the `virtualstandby` command to export data from a Rapid Recovery protected machine to a compatible virtual machine.

Usage

The usage for the command is as follows:

```
/virtualstandby -edit -exporttype [esxi | vm | hyperv | vb] -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -volumes [volume names] -vmname [virtualmachine name] -gen2 -hostname [virtual host name] -hostport [virtual host port number] -hostusername [virtual host user name] -hostpassword [virtual host password] [-ram [total megabytes] | -usesourceram] -diskprovisioning [thin | thick] -diskmapping [automatic | manual | withvm] -targetpath [location] -pathusername [user name] -pathpassword [password] [-uselocal machine] -initialexport
```

Command Options

The following table describes the options available for the `virtualstandby` command:

Table 76: VirtualStandby command options

Option	Description
-?	Display this help message.
-exporttype	<p>This option exports data from a protected machine to one of the following specified virtual servers:</p> <ul style="list-style-type: none"> • esxi (ESXi) • vm (VMware Workstation) • hyperv (Hyper-V) • vb (VirtualBox)
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine whose recovery points you want to export.
-volumes	Optional. Use this option to list the names of the volumes that you want to export. If you do not specify volumes, then all volumes in the recovery point will export. Enclose values in double quotes and separate them with a space; for example: "c:" "d:". Do not use trailing slashes in volumes names.
-ram	Use this option to allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Use this option to allocate the same amount of RAM on the virtual server that the source machine contains.
-vmname	The Windows name of the virtual machine.
-gen2	<p>Optional. This option specifies Generation 2 of the VM server. If you do not specify the generation, the command uses Generation 1. The following operating systems support Generation 2:</p> <ul style="list-style-type: none"> • Windows <ul style="list-style-type: none"> • Windows Server 2012 R2 • Windows 8.1 • Ubuntu Linux <ul style="list-style-type: none"> • CentOS • RHEL • Oracle Linux 7
-hostname	For ESXi and Hyper-V virtual exports only. The virtual server host name.
-linuxhostname	For VirtualBox exports only. The virtual server host name.

Option	Description
-hostport	For ESXi and Hyper-V virtual exports only. The virtual server port number.
-hostusername	For ESXi and Hyper-V virtual exports only. The user name for the virtual server host.
-hostpassword	For ESXi and Hyper-V virtual exports only. The password for the virtual server host.
-diskprovisioning	<p>For ESXi exports only. Optional. The amount of disk space that you want to allocate on the virtual machine. Use one of the two following specifications:</p> <ul style="list-style-type: none"> Thick - This specification makes the virtual disk as large as the original drive on the protected machine. Thin - This specification allocates the amount of actual disk space occupied on the original drive with a few additional megabytes. <p>The default specification is "thin."</p>
-diskmapping	<p>For ESXi exports only. Optional. This option determines how to map the disks from the protected machine to the virtual machine. Use one of the following values:</p> <ul style="list-style-type: none"> auto - This value automatically maps the disks. manual - This value lets you map the disks manually. withvm - This value stores the virtual disks in a datastore that you select. <p>The default value is "auto."</p>
-targetpath	For VMware Workstation and VirtualBox exports only. This option specifies the local or network path—or Linux path, for VirtualBox only—to the folder where you want to store the virtual machine files.
-pathusername	For VMware Workstation exports only. It is the user name for the network machine. It is only required when you specify a network path in the -targetpath option.
-pathpassword	For VMware Workstation exports only. It is the password for the network machine. It is only required when you specify a network path in the -targetpath option.
-uselocalmachine	For Hyper-V exports only. Optional. Use this command to connect to the local Hyper-V server. This option ignores the -hostname, -hostport, -hostusername, and -hostpassword options.
-edit	Optional. This option lets you edit existing virtual machines. It ignores the -exporttype and -initialexport options.
-initialexport	Optional. This option specifies whether to start an initial on-demand virtual machine export after you configure a continuous virtual standby.

Examples:

Set up a virtual standby export to an ESXi virtual machine with the name, amount of RAM, and disk size of the source protected server:

```
>cmdutil /virtualstandby -exporttype esxi -core 10.10.10.10 -user administrator -
password 23WE@#$sdd -protectedserver 10.10.5.22 -vmname Win2008-Smith -hostname
10.10.10.23 -hostport 443 -hostusername root -hostpassword 12QWsdxc@# -usesourceram
-diskprovisioning thick
```

Set up a virtual standby export to a VMware Workstation machine file on the local drive:

```
>cmdutil /virtualstandby -exporttype vm -core 10.10.10.10 -user administrator -  
password 23WE@#$sdd -protectedserver 10.10.5.22 -vmname Win2008-Smith -targetpath  
c:\virtualmachines -ram 4096
```

Set up a virtual standby export to a Hyper-V machine files and store them on a remote machine:

```
>cmdutil /virtualstandby -exporttype hyperv -core 10.10.10.10 -user adminstrator -  
password 23WE@#$sdd -protectedserver 10.10.5.22 -vmname Win20008-Smith -vmlocation  
\\WIN7-Bobby\virtualmachines -hostname 10.10.10.23 -hostport 443 -hostusername root  
-hostpassword 12QWsdxc@# -ram 4096
```

Localization

When running on the same machine on which Rapid Recovery Core is installed, the Rapid Recovery Command Line Management utility bases its display language on the language set for the Rapid Recovery Core. In this release, supported languages include English, Chinese (Simplified), French, Korean, German, Japanese, Portuguese (Brazil), and Spanish.


If the Rapid Recovery Command Line Management utility is installed on a separate machine, English is the only language supported.

PowerShell module

Rapid Recovery consists of several software components. Key components relevant to this topic include the following:

- The Rapid Recovery manages authentication for protected machines, schedules for transferring data for backup and replication, export to virtual machines, reporting, and bare metal restore (BMR) to similar or dissimilar hardware.
- The Rapid Recovery Agent is responsible for taking volume snapshots and for fast transfer of the data to the repository managed by the Core.
- The Rapid Recovery PowerShell Module is a Windows utility that lets users interact with the Core server by using Windows PowerShell® scripts. This module offers some of the same functionality that the Rapid Recovery Core Console graphic user interface (GUI) provides. For example, the Rapid Recovery PowerShell Module can mount Rapid Recovery recovery points or force a snapshot of a protected machine.

The PowerShell module interacts with the Rapid Recovery Core



PowerShell is a Microsoft .NET Framework-connected environment designed for administrative automation. This section describes the Rapid Recovery PowerShell module and the cmdlets administrators can use to script certain functions without interaction with the Rapid Recovery Core GUI.

NOTE: You can also run PowerShell scripts as pre and post scripts. For more information and sample scripts, see [Scripting](#).

The Rapid Recovery PowerShell Module is automatically installed and registered when you install the Rapid Recovery Core. The module is installed in your Windows system directory in the path: [Environment.SystemDirectory]\WindowsPowerShell\v1.0\Modules\RapidRecoveryPowerShellModule. For example, for x86 or 32-bit OS, it is installed in C:\Windows\System32\WindowsPowerShell\v1.0\Modules\RapidRecoveryPowerShellModule. When using the module, run PowerShell as an Administrator, and then change the directory to the location of the module.

Prerequisites for using PowerShell

Before using the Rapid Recovery PowerShell module, you must have Windows PowerShell 2.0 or later installed. Due to new features introduced in PowerShell 3.0, including easier access to object properties, PowerShell Web access, and support for REST calls, Quest recommends using PowerShell 3.0 or later.

Note: Make sure to place the powershell.exe.config file in the PowerShell home directory; for example, C:\WindowsPowerShell\powershell.exe.config.

powershell.exe.config

```
<?xml version="1.0"?>
<configuration>
  <startup useLegacyV2RuntimeActivationPolicy="true">
    <supportedRuntime version="v4.0.30319"/>
    <supportedRuntime version="v2.0.50727"/>
  </startup>
</configuration>
```

Working with commands and cmdlets

Cmdlets are specialized commands in a Windows PowerShell script that perform a single function. A cmdlet is typically expressed as a verb-noun pair. The result returned by a cmdlet is an object.

You can pipeline PowerShell commands, which enables the output of one cmdlet to be piped as input to another cmdlet. As a simple example, you can request the list of commands in the Rapid Recovery PowerShell module, and sort that list by name. The example script for this is:

```
Get-Command -module rapidrecoverypowershellmodule | sort-object name
```

Getting cmdlet help and examples

After you open PowerShell and import the Rapid Recovery PowerShell module, you can request additional information at any time by using the Get-Help <command_name> cmdlet. For example, to get information about the virtual machine export cmdlet, enter the following cmdlet and then press Enter:

```
Get-Help Start-VMExport
```

The object returned includes the command name, synopsis, syntax, and any options you can use with the command.

Another method to get help for a specific cmdlet is to type the command name followed by -?. For example:

```
Start-VMExport -?
```

You can also request examples for a cmdlet by executing the following command:

```
>Get-Help Start-VMExport -examples
```

Rapid Recovery PowerShell module cmdlets

This section describes the cmdlets and options available in the Rapid Recovery PowerShell Module. All cmdlets in the Rapid Recovery PowerShell Module support the following common parameters:

- Verbose
- Debug
- ErrorAction
- ErrorVariable
- WarningAction
- WarningVariable
- OutBuffer
- OutVariable

For more information, use `Get-Help about_commonparameters`.

Add-EsxAutoProtectObjects

The `Add-EsxAutoProtectObjects` cmdlet enables auto protection for specified objects on a vCenter or ESXi server.

Usage

The usage for the command is as follows:

```
Add-EsxAutoProtectObjects -core [host name] -user [user name] -password [password] -  
repository [name] -protectedserver [name | IP address] -autoprotect [object name  
collection]
```

Command Options

The following table describes the options available for the `Add-EsxAutoProtectObjects` command:

Table 77: Add-EsxAutoProtectObjects command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-autoprotect	Optional. This option lets you list the new virtual machines that you want to automatically protect.

Example:

Put specific objects from a vCenter or ESXi server under auto-protection by the Core:

```
>Add-EsxAutoProtectObjects -protectedserver 10.10.8.150 -add -autoprotect  
"Folder1", "Folder2"
```

Add-EsxVirtualMachines

The `Add-EsxVirtualMachines` cmdlet lets you add specific virtual machines (VMs) on vCenter or ESXi server under the protection of a Core.

Usage

The usage for the command is as follows:

```
Add-EsxVirtualMachines -core [host name] -user [user name] -password [password] -  
repository [name] -protectedserver [name | IP address] -virtualmachines [virtual  
machines collection | all]
```

Command Options

The following table describes the options available for the `Add-EsxVirtualMachines` command:

Table 78: Add-EsxVirtualMachines command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to store the data of the virtual machine. NOTE: You must enclose the name in double quotes.
-protectedserver	Use this option to edit the vCenter or ESXi objects for a specific protected machine.
-virtualmachines	A list of virtual machines each separate by a comma.

Example:

Add two VMs from a vCenter or ESXi server under protection by the Core:

```
>Add-EsxVirtualMachines -repository "repository1" -protectedserver 10.10.10.10 -virtualmachines "vm1", "vm2"
```

Add-HyperVClusterSharedVirtualDisks

The Add-HyperVClusterSharedVirtualDisks cmdlet lets you add shared Hyper-V virtual disks under the protection of a Core.

Usage

The usage for the command is as follows:

```
Add-HyperVClusterSharedVirtualDisks -core [host name] -user [user name] -password [password] -repository [name] -shareddisks [shared virtual disks name or path collection | all]
```

Command Options

The following table describes the options available for the Add-HyperVClusterSharedVirtualDisks command:

Table 79: Add-HyperVClusterSharedVirtualDisks command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to store the data of the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to edit the shared virtual disks for a specific protected machine.
-shareddisks	A list of shared disks each separate by a comma.

Example:

Protect all of the shared virtual disks on a cluster:

```
>Add-HyperVClusterSharedVirtualDisks -protectedserver "HV-2012R2" -repository  
"Repository_10.10.55.133" -shareddisks "all"
```

Add-HyperVClusterVirtualMachines

The `Add-HyperVClusterVirtualMachines` cmdlet lets you add specific virtual machines (VMs) from a Hyper-V cluster under the protection of a Core.

Usage

The usage for the command is as follows:

```
Add-HyperVClusterVirtualMachines -core [host name] -user [user name] -password  
[password] -repository [name] -protectedserver [name | IP address] -virtualmachines  
[virtual machines collection | all]
```

Command Options

The following table describes the options available for the `Add-HyperVClusterVirtualMachines` command:

Table 80: Add-HyperVClusterVirtualMachines command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to store the data of the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to protect virtual machines.
-virtualmachines	A list of the virtual machines that you want to protect, each separated by a comma. The name of the VM must be enclosed in double quotes.

Example:

Add specific VMs of a Hyper-V cluster under protection by the Core:

```
>Add-HyperVClusterVirtualMachines -repository "Repository 1" -protectedserver  
hvcluster -virtualmachines "Win8x64-gen1", "Win2012x64-gen2"
```

Add-HyperVVirtualMachines

The `Add-HyperVVirtualMachines` cmdlet lets you add specific virtual machines (VMs) from a Hyper-V cluster under the protection of a Core.

Usage

The usage for the command is as follows:

```
Add-HyperVVirtualMachines -core [host name] -user [user name] -password [password] -  
repository [name] -protectedserver [name | IP address] -virtualmachines [virtual  
machines collection | all]
```

Command Options

The following table describes the options available for the `Add-HyperVVirtualMachines` command:

Table 81: Add-HyperVVirtualMachines command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to store the data of the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to edit Hyper-V objects for a specific virtual machine.
-virtualmachines	A list of the virtual machines that you want to protect, each separated by a comma. The name of the VM must be enclosed in double quotes.

Example:

Add specific VMs of a Hyper-V cluster under protection by the Core:

```
>Add-HyperVVirtualMachines -repository "Repository 1" -protectedserver HVServer1 -virtualmachines "Win8x64-gen1", "Win2012x64-gen2"
```

Disable-HyperVAutoProtection

The `Disable-HyperVAutoProtection` cmdlet lets you disable the auto-protection feature, which automatically protects new virtual machines (VMs), on a Hyper-V host.

Usage

The usage for the command is as follows:

```
Disable-HyperVAutoProtection -core [host name] -user [user name] -password [password] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Disable-HyperVAutoProtection` command:

Table 82: Disable-HyperVAutoProtection command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	The display name, host name, or IP address of the protected Hyper-V server.

Example:

Disable auto protection of new virtual machines on the specified Hyper-V host:

```
>Disable-HyperVAutoProtection -protectedserver "10.10.1.1"
```

Edit-AzureVirtualStandby

You can use the `Edit-AzureVirtualStandby` cmdlet to change the parameters of an existing Azure virtual standby continuous export.

Usage

The usage for the command is as follows:

```
Edit-AzureVirtualStandby -core [host name] -user [user name for Core] -password [password for Core] -protectedserver [name | IP address] -volumes [volume names | all] -containername [container] -foldername [folder name] -subscriptionid [Azure subscription ID] -forceedit
```

Command Options

The following table describes the options available for the `Edit-AzureVirtualStandby` command:

Table 83: Edit-AzureVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points that you want to export.
-volumes	Optional. List of additional volume names to be exported. If you use the value <code>all</code> or use no value, then all volumes export. Values must be enclosed in double quotes and separated by a space. Do not use trailing slashes in volumes names; for example, use <code>"c:" "d:"</code> .
-containername	The name of the container in the Azure storage account (classic). The name must contain between three and 63 characters (lowercase letters, numbers, and hyphens only), and start with a letter or a number. Every hyphen must be preceded and followed by a letter or number.
-foldername	Optional. The name of a folder inside of the Azure storage container. A folder name cannot contain any of the following characters: \ / : * ? " < > .
-subscriptionid	The identifier of a previously added Azure subscription.
-forceedit	Optional. This option lets you delete existing export files when you change an export location.

Example:

Edit an Azure virtual standby export:

```
>Edit-AzureVirtualStandby -protectedserver 10.10.5.22 -subscriptionid "111111-22222-33333-4444-555555" -containername container1 -foldername folder2
```

Edit-EsxiVirtualStandby

The `Edit-EsxiVirtualStandby` command lets you use PowerShell to make changes to an existing virtual export to an ESXi virtual machine (VM).

Usage

The usage for the command is as follows:

```
Edit-EsxiVirtualStandby [-HostName <String>] [-HostPort <String>] [-HostUserName <String>] [-HostPassword <String>] [-DiskProvisioning <String>] [-DiskMapping <String>] [-ProtectedServer <String>] [-Volumes <String[]>] [-VMName <String>] [-UseSourceRam] [-Ram <String>] [-User <String>] [-Core <String>] [-Password <String>] [-Verbose] [-Debug] [-ErrorAction<ActionPreference>] [-WarningAction<ActionPreference>] [-ErrorVariable String] [-WarningVariable <String>] [-OutVariable <String>] [-OutBuffer <Int32>]
```

Command Options

The following table describes the options available for the `Edit-EsxiVirtualStandby` command:
Updated option descriptions TK.

Table 84: Edit-EsxiVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now) #h or #H (where # is number for the period of hours before now until now) "time date 1", "time date 2" (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all active jobs on the local Core:

```
>Get-activejobs -all
```

Edit-HyperVVirtualStandby

The `Edit-HyperVVirtualStandby` command lets you use PowerShell to make changes to an existing virtual export to a Hyper-V virtual machine (VM).

Usage

The usage for the command is as follows:

```

Edit-HyperVVirtualStandby [-HostName <String>] [-HostPort <String>] [-HostUserName <String>] [-HostPassword <String>] [-VMLocation <String>] [-UseLocalMachine] [-gen2] [-UseVhdx] [-ProtectedServer <String>] [-Volumes <String[]>] [-VMName <String>] [-UseSourceRam] [-Ram <String>] [-User <String>] [-Core <String>] [-Password <String>] [-Verbose] [-Debug] [-ErrorAction <ActionPreference>] [-WarningAction <ActionPreference>] [-ErrorVariable <String>] [-WarningVariable <String>] [-OutVariable <String>] [-OutBuffer <Int32>] -exportvmconfigfiles

```

Command Options

The following table describes the options available for the `Edit-HyperVVirtualStandby` command:

Table 85: Edit-HyperVVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-hostname	Virtual server host name.
-hostport	Virtual server port number.
-hostusername	Login to the virtual server host.
-hostpassword	Password to the virtual server host.
-vmlocation	Location of the virtual machine.
-uselocalmachine	Optional. Connect to the local Hyper-V server. In this case, the command ignores the following options: 'hostname', 'hostport', 'hostusername', and 'hostpassword'.
-gen2	Optional. The virtual machine generation. If not specified, the command uses generation 1. Windows Server 2012 R2 and
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Option	Description
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now) #h or #H (where # is number for the period of hours before now until now) "time date 1", "time date 2" (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).
-exportvmconfigfiles	Optional. Specify whether to export virtual machine configuration files. This option is available only both when the source is a virtual protected agentlessly and when the target hypervisor is the same as the source hypervisor.

Example:

Lists all active jobs on the local Core:

```
>Get-activejobs -all
```

Edit-OracleDBVerifyNightlyJob

Use the command `Edit-OracleDBVerifyNightlyJob` to enable or disable this nightly job for specific Oracle machines that are under protection.

Usage

The usage for the command is as follows:

```
Edit-OracleDBVerifyNightlyJob -core [host name] -user [user name] -password  
[password] -protectedserver [name | IP address] [-enable | -disable] [-global]
```

Command Options

The following table describes the options available for the `Edit-OracleDBVerifyNightlyJob` command:

Table 86: Edit-OracleDBVerifyNightlyJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle DBVerify nightly job.
-enable	Use this option to enable the DBVerify nightly job for the specified protected machine.
-disable	Use this option to disable the DBVerify nightly job for the specified protected machine.
-global	Use this option to apply the specified setting as the default for this Core.

Examples:

Enable the Oracle DBVerify nightly job for a protected server:

```
Edit-OracleDBVerifyNightlyJob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -enable
```

Disable the Oracle DBVerify nightly job for a protected server:

```
Edit-OracleDBVerifyNightlyJob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -disable
```

Edit-OracleLogTruncationNightlyJob

Use the command `Edit-OracleLogTruncationNightlyJob` to enable or disable this nightly job for specific Oracle machines that are under protection and to set the deletion policy and retention duration for the logs.

Usage

The usage for the command is as follows:

```
Edit-OracleLogTruncationNightlyJob -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] [-enable | -disable] [-global] [-usedefault] -deletionpolicy [automatic | keepnewest | keepspecificnumber] -retentionduration [duration value] -retentionunit [day | week | month | year] -numberoffiles [number of archive files to create]
```

Command Options

The following table describes the options available for the `Edit-OracleLogTruncationNightlyJob` command:

Table 87: Edit-OracleLogTruncationNightlyJob command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-protectedserver</code>	Use this option to specify the protected machine for which you want to enable Oracle log truncation as a nightly job.
<code>-enable</code>	Use this option to enable log truncation for the specified protected machine. This is the default option and can be omitted.
<code>-disable</code>	Use this option to disable log truncation for the specified protected machine.
<code>-global</code>	Use this option to apply the specified setting as the default for this Core.
<code>-all</code>	This option applies the specified changes for every protected machine that has at least one Oracle instance installed.
<code>-usedefault</code>	Optional. Use this option to apply the default Core settings to the specified machine, which may also be set by using the <code>-global</code> option.
<code>-deletionpolicy</code>	Optional. This option must be represented by one of the following values: <ul style="list-style-type: none">• "automatic"• "keepnewest"• "keepspecificnumber"
<code>-retentionduration</code>	Optional. This value determines the length of time to keep a log before truncating and is constrained to positive integer values. If using the "keepnewest" value of the <code>-deletionpolicy</code> option, a retention duration value is required.
<code>-retentionunit</code>	Optional. This option identifies the time unit for the <code>-retentionduration</code> option. It must be represented by one of the following values: <ul style="list-style-type: none">• "day"• "week"• "month"• "year"
<code>-numberoffiles</code>	Optional. This option sets the number of recent archive log files to keep. If using the "keepspecificnumber" value of the <code>-deletionpolicy</code> option, a number of files value is required.

Examples:

Edit the Oracle log truncation nightly job settings for the Core globally:

```
Edit-OracleLogTruncationNightlyJob -core 10.10.127.42 -user admin -password 676df#df  
-protectedserver 10.10.34.88 -global -deletionpolicy keepspecificnumber -  
numberoffiles 15
```

Disable the Oracle log truncation nightly job for a specified protected server:

```
Edit-OracleLogTruncationNightlyJob -core 10.10.127.42 -user admin -password 676df#df  
-protectedserver 10.10.34.88 -disable
```

Edit-Replication

Use the `Edit-Replication` to make changes to an existing replication relationship between two Cores.

Usage

The usage for the command is as follows:

```
Edit-Replication -core [host name] -user [user name] -password [password] -  
protectedserver [name | IP address] -incoming [host name] -outgoing [host name] -add
```

Command Options

The following table describes the options available for the `Edit-Replication` command:

Table 88: Edit-Replication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable Oracle log truncation as a nightly job.
-add	Add protected servers to an existing replication.
-scheduletype	The type of replication schedule. This option should be specified by one of the following values: <ul style="list-style-type: none">1. "atalltimes" - to automatically replicate at all times.

Option	Description
	<ul style="list-style-type: none"> 2. "daily" - to automatically replicate once each day, with specific "-dailystarttime" and "-dailyendtime" parameters. 3. "custom" - to automatically replicate on specified weekdays or weekends designated by "-weekdaystarttime," "-weekdayendtime," "-weekendstarttime," and "-weekendendtime" parameters.
-dailystarttime	Use only for the daily value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the earliest time of day when you want replication to start.
-dailyendtime	Use only for the daily value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of day when you want replication to start.
-weekdaystarttime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the earliest time of a weekday when you want replication to start.
-weekdayendtime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of a weekday when you want replication to start.
-weekendstarttime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the earliest time of the weekend when you want replication to start.
-weekendendtime	Use only for the custom value of the -scheduletype option. It is used to establish a window of time for when replication should occur. Use this option to specify the latest time of the weekend when you want replication to start.

Examples:

Edit the replication schedule by specifying weekdays and weekends:

```
>Edit-Replication -id RemoteServerHostName -scheduletype custom -weekdaystarttime "9:00 AM" -weekdayendtime "6:00 PM" -weekendstarttime "9:00 AM" -weekendendtime "6:00 PM"
```

Add protected servers to existing replication:

```
>Edit-Replication -id RemoteServerHostName -protectedserver "10.10.1.1","Repository1"
```

Edit-ScheduledArchive

The `Edit-ScheduledArchive` command lets you use PowerShell to make changes to an existing scheduled archive.

Usage

The usage for the command is as follows:

```

Edit-ScheduledArchive -core [host name] -user [login] -password [password] -all | -
protectedserver [name | IP address | "[name1 | IP address1]" "[name2 | IP
address2]"] -path [location] -cloudaccountname [name] -cloudcontainer [name] -
recycleaction [type] -scheduletype [type] -dayofweek [name] -dayofmonth [number] -
time [time] -initialpause -id [id]

```

Command Options

The following table describes the options available for the `Edit-ScheduledArchive` command:

Table 89: Edit-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	The protected machine with recovery points that you want to archive. You can specify multiple machine names enclosed in double quotes and separated by commas.
-all	Archive recovery points for all protected machines.
-path	The path to where to save the archived data. For example: <ul style="list-style-type: none"> Local machine: "d:\work\archive" Network path: "\\servername\sharename" Folder in a cloud account: "Folder Name" Note: The number of symbols should not be greater than 100 for local and network locations, and should not be greater than 150 for a cloud location.
-cloudaccountname	Optional. Use only for cloud archiving. The name of the cloud account where you want to save the archive.
-cloudcontainer	Optional. Use only for cloud archiving. The name of the cloud container in the chosen cloud account, where the archive will be saved. When you use this option, you should also specify the "-cloudaccountname" parameter.
-recycleaction	The type of recycle action. Specified by using one of the following four values: <ul style="list-style-type: none"> "replacethiscore" - Overwrites any pre-existing archived data pertaining to this Core, but leaves the data for other Cores intact. "erasecompletely" - Clears all archived data from the directory before writing the new archive.

Option	Description
	<ul style="list-style-type: none"> "incremental" - Lets you add recovery points to an existing archive. It compares recovery points to avoid duplicating data that already exists in the archive.
-scheduletype	<p>Type of schedule interval. Specified the option with one of the following four values:</p> <ul style="list-style-type: none"> "daily" - For a daily automatically created archive. "weekly" - For a weekly automatically created archive. You must specify the "-dayofweek" parameter. "monthly" - For a monthly automatically created archive. You must specify the "-dayofmonth" parameter. If a month does not have the day specified—for example, "31"—then the archive will not occur for that month. "lastdayofmonth" - For automatically creating an archive on the last day of each month.
-dayofweek	Use only for the "weekly" option of the "-scheduletype" parameter. The day of the week on which to automatically create the archive (for example, "Monday").
-dayofmonth	Use only for the "month" option of the "-scheduletype" parameter. The day (number) of the month on which to automatically create the archive (for example, "15").
-time	The hour of the day when you want to create an archive.
-initialpause	Optional. Specify this option if you want to initially pause archiving after you configure the archiving schedule.
-id	The identifier of the scheduled archive that you want to edit.

Example:

Edit a scheduled archive on the local Core:

```
>Edit-ScheduledArchive -protectedserver protectedserver1 -path d:\work\archive -
cloudaccountname cloud1 -cloudcontainer cloudarchives -recycleaction incremental -
scheduletype daily -time 12:00 AM -initialpause -i
    d archiveid
```

Edit-VBVirtualStandby

The `Edit-VBVirtualStandby` command lets you use PowerShell to make changes to an existing virtual export to a VirtualBox virtual machine (VM).

Usage

The usage for the command is as follows:

```
Edit-VBVirtualStandby [-TargetPath <String>] [-PathUserName <String>] [-PathPassword
<String>] [-LinuxHostName <String>] [-HostPort <UInt32>] [-AccountUserName <String>]
```

```
[-AccountPassword <String>] [-ProtectedServer <String>] [-Volumes <String[]>] [-VMName <String>] [-UseSourceRam] [-Ram <String>] [-User <String>] [-Core <String>] [-Password <String>] [-Verbose] [-Debug] [-ErrorAction <ActionPreference>] [-WarningAction <ActionPreference>] [-ErrorVariable <String>] [-WarningVariable <String>] [-OutVariable <String>] [-OutBuffer <Int32>]
```

Command Options

The following table describes the options available for the `Edit-VBVirtualStandby` command:
Updated option descriptions TK.

Table 90: Edit-VBVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now) #h or #H (where # is number for the period of hours before now until now) "time date 1", "time date 2" (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all active jobs on the local Core:

```
>Get-activejobs -all
```

Edit-VMVirtualStandby

The `Edit-VMVirtualStandby` command lets you use PowerShell to make changes to an existing virtual export to a VMware Workstation virtual machine (VM).

Usage

The usage for the command is as follows:

```
Edit-VMVirtualStandby [-TargetPath <String>] [-PathUserName <String>] [-PathPassword <String>] [-ProtectedServer <String>] [-Volumes <String[]>] [-VMName <String>] [-UseSourceRam] [-Ram <String>] [-User <String>] [-Core <String>] [-Password <String>] [-Verbose] [-Debug] [-ErrorAction <ActionPreference>] [-WarningAction <ActionPreference>] [-ErrorVariable <String>] [-WarningVariable <String>] [-OutVariable <String>] [-OutBuffer <Int32>]
```

Command Options

The following table describes the options available for the `Edit-VMVirtualStandby` command:

Table 91: Edit-VMVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-targetpath	The local or network path (or Linux path, only for VirtualBox export) to the folder for storing the virtual machine files.
-pathusername	The credentials for the target path when it is located on a network share and you specified it with the <code>-targetpath</code> option.
-pathpassword	The password for the target path when it is located on a network share and you specified it with the <code>-targetpath</code> option.
-protectedserver	The protected machine with recovery points that you want to export, indicated by IP address.
-volumes	Optional. A list of volume names that you want to export. When not specified, all

Option	Description
	volumes export. Values must be separated by a comma. Do not use trailing slashes in volume names. For example: C, F, E.
-vmname	The Windows name of the virtual machine.
-ram	Use this option to allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate all of the amount of RAM on the target virtual server that is used on the source virtual server.

Example:

Edit a specific amount of RAM on the existing Virtual Standby:

```
>Edit-VMVirtualStandby -targetpath "\\servername\sharename" -pathusername "login" -pathpassword "password" -protectedserver 10.10.11.245 -vmname "name" -ram 2048
```

Edit the list of volume names to be exported to the existing Virtual Standby:

```
>Edit-VMVirtualStandby -targetpath "\\servername\sharename" -pathusername "login" -pathpassword "password" -protectedserver 10.10.11.245 -vmname "name" -volumes C,F
```

Enable-HyperVAutoProtection

The `Enable-HyperVAutoProtection` cmdlet lets you enable the auto-protection of new virtual machines (VMs) on a Hyper-V host.

Usage

The usage for the command is as follows:

```
Enable-HyperVAutoProtection -core [host name] -user [user name] -password [password] -repository [name] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Enable-HyperVAutoProtection` command:

Table 92: Enable-HyperVAutoProtection command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Option	Description
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to store the data of the virtual machine. Note: You must enclose the name in double quotes.
-protectedserver	Use this option to protect virtual machines.

Example:

Enable auto-protection of new VMs on a Hyper-V host:

```
>Enable-HyperVAutoProtection -protectedserver 10.10.1.1 -repository "Repository 1"
```

Enable-OracleArchiveLogMode

Use the command `Enable-OracleArchiveLogMode` to enable or disable this mode for specific Oracle machines that are under protection.

Usage

The usage for the command is as follows:

```
Enable-OracleArchiveLogMode -core [host name] -user [user name] -password [password]
-protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Enable-OracleArchiveLogMode` command:

Table 93: Enable-OracleArchiveLogMode command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle archive log mode.

Example:

Enable the Oracle archive log mode for a protected server:

```
>Enable-OracleArchiveLogMode -core 10.10.127.42 -user admin -password 676df#df -  
protectedserver 10.10.34.88
```

Get-ActiveJobs

The `Get-ActiveJobs` command returns all active jobs from the Core. The `-jobtype` parameter could be used to observe specific jobs.

Usage

The usage for the command is as follows:

```
Get-ActiveJobs -core [host name] -user [user name] -password [password] -all | -  
protectedserver [server name or IP address] -number [all | f[number] | l[number] |  
number] -jobtype [type] -time [time]
```

Command Options

The following table describes the options available for the `Get-ActiveJobs` command:

Table 94: Get-ActiveJobs command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and

Option	Description
	remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now) #h or #H (where # is number for the period of hours before now until now) "time date 1", "time date 2" (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all active jobs on the local Core:

```
>Get-activejobs -all
```

Get-CloudAccounts

The `Get-CloudAccounts` command lets you get information about the cloud accounts that have been added to the Core.

Usage

The usage for the command is as follows:

```
Get-CloudAccounts -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Get-CloudAccounts` command:

Table 95: Get-CloudAccounts command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Option	Description
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Get information about cloud accounts:

```
>Get-CloudAccounts -core 10.10.10.10 -user administrator -password 23WE@#$sdd
```

Get-Clusters

The `Get-Clusters` command returns information about server clusters protected in the Core.

Usage

The usage for the command is as follows:

```
Get-Clusters -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Get-Clusters` command:

Table 96: Get-Clusters command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

List server clusters protected on the local Core:

```
>Get-Clusters
```

Get-CompletedJobs

The `Get-CompletedJobs` command returns a list of jobs completed on the Core. The `-jobtype` parameter could be used to observe specific jobs.

Usage

The usage for the command is as follows:

```
Get-CompletedJobs -core [host name] -user [user name] -password [password] -all |  
-protectedserver [server name or IP address] -number [all | f[number] | l[number] |  
number] -jobtype [type] -time [time]
```

Command Options

The following table describes the options available for the `Get-CompletedJobs` command:

Table 97: Get-CompletedJobs command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include:

Option	Description
	#d or DD (where # is a number for the period of time of days before now until now)
	#h or #H (where # is number for the period of hours before now until now)
	“time date 1”, “time date 2” (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all active jobs on the local Core:

```
>Get-CompletedJobs -all
```

Lists all completed create repository jobs on the local Core:

```
>Get-CompletedJobs -jobtype repository
```

Get-ExchangeMailStores

The `Get-ExchangeMailStores` command returns information about mail stores on Exchange servers Protected by the Core.

Usage

The usage for the command is as follows:

```
Get-ExchangeMailStores -core [host name] -user [user name] -password [password] -protectedserver [server name or IP address]
```

Command Options

The following table describes the options available for the `Get-ExchangeMailStores` command:

Table 98: Get-ExchangeMailStores command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Example:

Lists Exchange mail stores for Exchange server for the local Core:

```
>Get-ExchangeMailStores -protectedserver 10.10.10.10
```

Get-Failed

The `Get-Failed` command returns information about failed recovery points on the local Core.

Usage

The usage for the command is as follows:

```
Get-Failed -core [host name] -user [user name] -password [password] -all | -  
protectedserver [server name or IP address] -number [all | f[number] | l  
[number] | number]
```

Command Options

The following table describes the options available for the `Get-Failed` command:

Table 99: Get-Failed command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.

Example:

Lists all failed recovery points:

```
>Get-failed -protectedserver 10.10.10.10
```

Get-FailedJobs

The `Get-FailedJobs` command returns all failed jobs from the local Core.

Usage

The usage for the command is as follows:

```
Get-FailedJobs -core [host name] -user [user name] -password [password] -all | -  
protectedserver [server name or IP address] -number [all | f[number] | l[number] |  
number] -jobtype [type] -time [time]
```

Command Options

The following table describes the options available for the `Get-FailedJobs` command:

Table 100: Get-FailedJobs command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now)

Option	Description
	#h or #H (where # is number for the period of hours before now until now) “time date 1”, “time date 2” (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all failed jobs on the local Core:

```
>Get-FailedJobs -all
```

Lists all failed create backup jobs on the local Core:

```
>Get-FailedJobs -type backup
```

Get-HyperVClusterSharedVirtualDisks

The `Get-HyperVClusterSharedVirtualDisks` command provides information about machines protected on the local Core.

Usage

The usage for the command is as follows:

```
Get-HyperVClusterSharedVirtualDisks -protectedserver [name | IP address] -shareddisk [shared virtual disk name (path)]
```

Command Options

The following table describes the options available for the `Get-HyperVClusterSharedVirtualDisks` command:

Table 101: Get-HyperVClusterSharedVirtualDisks command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Option	Description
-protectedserver	This option shows all of the shared virtual disks for a specific protected cluster.
-shareddisk	The name of a specific shared disk.

Example:

Retrieve a collection of all shared disks:

```
>Get-HyperVClusterSharedVirtualDisks -protectedserver "HV-2012R2" -shareddisk
"Shared Disk 1"
```

Get-ListAzureVMSizes

The `Get-ListAzureVMSizes` command provides a list of the available virtual machines sizes for deploying to Azure.

Usage

The usage for the command is as follows:

```
Get-ListAzureVMSizes -core [host name] -user [user name] -password [password] -
cloudaccountname [Azure account name] -storageaccountname [Azure storage account
name] -subscriptionid [subscription ID] -cloudservicename [service name]
```

Command Options

The following table describes the options available for the `Get-ListAzureVMSizes` command:

Table 102: Get-ListAzureVMSizes command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-cloudaccountname	Optional when specifying <code>-storageaccountname</code> . Specify the name of the Azure cloud account.
-storageaccountname	Optional when specifying <code>-cloudaccountname</code> . Specify the name of the Azure

Option	Description
	storage account.
-subscriptionid	The Azure subscription ID.
-cloudservicename	The name of the Azure cloud service.

Example:

View a list of the available virtual machine sizes for the cloud account Account1:

```
>Get-CloudAccounts -cloudaccountname Account1 -cloudservicename Service
```

View a list of the available virtual machine sizes for the storage account named "teststorage:"

```
>Get-CloudAccounts -storageaccountname teststorage -cloudservicename Service
```

Get-Mounts

The `Get-Mounts` command returns all recovery points mounted on the local Core.

Usage

The usage for the command is as follows:

```
Get-Mounts -core [host name] -user [user name] -password [password] -protectedserver  
[server name or IP address]
```

Command Options

The following table describes the options available for the `Get-Mounts` command:

Table 103: Get-Mounts command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Example:

Show all mounted recovery points:

```
>Get-Mounts -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd -  
protectedserver 10.10.5.22
```

Get-OracleInstances

The `Get-OracleInstances` command lists the Oracle instances that are running a specified protected server.

Usage

The usage for the command is as follows:

```
Get-OracleInstances -core [host name] -user [user name] -password [password] -  
protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Get-OracleInstances` command:

Table 104: Get-OracleInstances command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.

Example:

List the Oracle instances running on a specified protected server:

```
Get-OracleInstances -core 10.10.127.42 -user admin -password -676df#df -  
protectedserver 10.10.34.88
```

Get-Passed

The `Get-Passed` command returns information about recovery points that have passed verification checks on the Core.

Usage

The usage for the command is as follows:

```
Get-Passed -core [host name] -user [user name] -password [password] -protectedserver  
[server name or IP address] -number [all | f[number] | l[number] | number]
```

Command Options

The following table describes the options available for the `Get-Passed` command:

Table 105: Get-Passed command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Lists all recovery points on the local Core the passed verification checks:

```
>Get-Passed -protectedserver 10.10.10.10
```

Get-ProtectedServers

The `Get-ProtectedServers` command provides information about machines protected on the local Core.

Usage

The usage for the command is as follows:

```
Get-ProtectedServers -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Get-ProtectedServers` command:

Table 106: Get-ProtectedServers command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
<code>-withclusters</code>	Optional. If they exist, include clusters and cluster nodes in the resulting protected server list.

Example:

Lists all machines, including clusters and cluster nodes, protected by the specified Core:

```
>Get-ProtectedServers -core 10.10.10.10 -user administrator -password 23WE@#$sdd -withclusters
```

Get-ProtectionGroups

The `Get-ProtectionGroups` command returns information about protection groups on the local Core.

Usage

The usage for the command is as follows:

```
Get-ProtectionGroups -core [host name] -user [user name] -password [password] -all |  
-protectedserver [server name or IP address]
```

Command Options

The following table describes the options available for the `Get-ProtectionGroups` command:

Table 107: Get-ProtectionGroups command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Example:

Lists protection groups on the local Core:

```
>Get-ProtectionGroups -protectedserver 10.10.10.10
```

Get-QueuedJobs

The `Get-QueuedJobs` command returns all jobs waiting to begin from the Core.

Usage

The usage for the command is as follows:

```
Get-QueuedJobs -core [host name] -user [login] -password [password] -all | -
protectedserver [name | IP address] -number [all | f[number] | l[number] | number] -jobtype [type] -time [time]
```

Command Options

The following table describes the options available for the `Get-ActiveJobs` command:

Table 108: Get-ActiveJobs command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password.

Option	Description
	If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-all	Show all jobs, including those performed by the Core and all protected servers.
-number	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.
-jobtype	Optional. Specifies the job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy agents), 'rollback' (restoring from a recovery point), 'rollup' (recovery point rollups), 'sqlattach' (agent attachability checks), and 'mount' (mount repository). By default, all jobs of the specified type are returned.
-time	Optional. Filter output by date and time for the job started. Available types of input include: #d or DD (where # is a number for the period of time of days before now until now) #h or #H (where # is number for the period of hours before now until now) "time date 1", "time date 2" (to show a custom range of time from a specific date appearing before the comma to a specific date following the comma).

Example:

Lists all queued jobs on the local Core:

```
>Get-QueuedJobs -all
```

Get-RecoveryPoints

The `Get-RecoveryPoints` command returns information about recovery points for machines protected on the local Core.

Usage

The usage for the command is as follows:

```
Get-RecoveryPoints -core [host name] -user [user name] -password [password] -
protectedserver [server name or IP address] -number [all | f[number] | l
[number] | number]
```

Command Options

The following table describes the options available for the `Get-RecoveryPoints` command:

Table 109: Get-RecoveryPoints command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
<code>-protectedserver</code>	Show jobs for a specific protected machine, indicated by IP address.
<code>-number</code>	Optional. Determine how many records to display. available values are: all (display all jobs); l[number] or [number] (fetches ## most recent jobs sorted by execution and time); f[number] (displays first ## recovery jobs sorted by execution and time). By default, the 20 most recent jobs are shown.

Example:

Lists recovery points for machines protected on the local Core:

```
>Get-RecoveryPoints -protectedserver 10.10.10.10
```

Get-ReplicatedServers

The `Get-ReplicatedServers` command returns information about machines replicated on the Core.

Usage

The usage for the command is as follows:

```
Get-ReplicatedServers -core [host name] -user [user name] -password [password]
```

Quest recommends you consider security when using commands to return values. For example, this command returns the administrator password for each replicated server. If used in an MSP environment from the target Core, this can potentially expose the login password of the administrator user. For environments with encrypted repository data, this does not pose substantial security issues.

Command Options

The following table describes the options available for the `Get-ReplicatedServers` command:

Table 110: Get-ReplicatedServers command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Lists all replicated servers on the local Core:

```
>Get-ReplicatedServers
```

Get-Repositories

The `Get-Repositories` command returns information about repositories on the Core.

Usage

The usage for the command is as follows:

```
Get-Repositories -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Get-Repositories` command:

Table 111: Get-Repositories command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Lists repositories on the local Core:

```
>Get-Repositories
```

Get-ScheduledArchives

The `Get-ScheduledArchives` command lets you use PowerShell to view information about the existing Rapid Recovery scheduled archives associated with this Core.

Usage

The usage for the command is as follows:

```
Get-ScheduledArchives -core [host name] -user [login] -password [password]
```

Command Options

The following table describes the options available for the `Get-ScheduledArchives` command:

Table 112: Get-ScheduledArchives command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Get information about the scheduled archives on this Core:

```
>Get-ScheduledArchives -core 10.10.10.10 -user administrator -password password
```

Get-SqlDatabases

The `Get-SqlDatabases` command returns a list of SQL databases from the specified protected machine.

Usage

The usage for the command is as follows:

```
Get-SqlDatabases -core [host name] -user [user name] -password [password] -  
protectedserver [server name or IP address]
```

Command Options

The following table describes the options available for the `Get-SqlDatabases` command:

Table 113: Get-SqlDatabases command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Example:

Lists all SQL databases jobs on the local Core:

```
>Get-SqlDatabases -protectedserver 10.10.10.10
```

Get-TransferQueueEntries

The `Get-TransferQueueEntries` command shows a list of the transfer jobs that are still in the queue and have yet to occur.

Usage

The usage for the command is as follows:

```
Get-TransferQueueEntries -core [host name] -user [user name] -password [password] -  
protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Get-TransferQueueEntries` command:

Table 114: Get-TransferQueueEntries command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.

Example:

View the transfer queue entries on Core "10.10.10.10" for Agent "10.10.5.22:"

```
Get-TransferQueueEntries -core 10.10.10.10 -user administrator -password -23WE@#$sdd  
-protectedserver 10.10.5.22
```

Get-UnprotectedVolumes

The `Get-UnprotectedVolumes` command returns information about volumes that are available for protection but not currently protected on the Core.

Usage

The usage for the command is as follows:

```
Get-UnprotectedVolumes  
-core [host name] -user [user name] -password [password] -protectedserver [server  
name or IP address]
```

Command Options

The following table describes the options available for the `Get-UnprotectedVolumes` command:

Table 115: Get-UnprotectedVolumes command options

Option	Description
-?	Display this help message.

Option	Description
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
<code>-protectedserver</code>	Show jobs for a specific protected machine, indicated by IP address.

Example:

Lists all volumes available for protection (but not get protected) on the specified agent machine:

```
>Get-UnprotectedVolumes -protectedserver 10.10.10.10
```

Get-Version

The `Get-Version` command retrieves the product version of a Core or Agent software installation.

Usage

The usage for the command is as follows:

```
Get-Version -core [host name] -user [user name] -password [password] -  
protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Get-Version` command:

Table 116: Get-Version command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.

Example:

Retrieve the product version of the present Core installation:

```
Get-Version
```

Get-VirtualizedServers

The `Get-VirtualizedServers` command returns information about virtualized servers.

Usage

The usage for the command is as follows:

```
Get-VirtualizedServers -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Get-VirtualizedServers` command:

Table 117: Get-VirtualizedServers command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a

Option	Description
	password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Example:

Lists all virtualized servers on the local Core:

```
>Get-VirtualizedServers
```

Get-Volumes

The `Get-Volumes` command returns information about volumes on a specified machine that is protected by the Core.

Usage

The usage for the command is as follows:

```
Get-Volumes -core [host name] -user [user name] -password [password] -  
protectedserver [server name or IP address]
```

Command Options

The following table describes the options available for the `Get-Volumes` command:

Table 118: Get-Volumes command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on.

Option	Description
	If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.

Example:

Lists all volumes on the specified machine:

```
>Get-Volumes -protectedserver 10.10.10.10
```

New-AzureVirtualStandby

You can use the `New-AzureVirtualStandby` command to export a virtual machine (VM) to a Microsoft Azure cloud account as a virtual standby machine.

Usage

The usage for the command is as follows:

```
New-AzureVirtualStandby -core [host name] -user [user name for Core] -password
[password for Core] -protectedserver [name | IP address] -volumes [volume names |
all] -initialexport -cloudaccountname [cloud account name] -storageaccountname
[storage account name] -containername [container name] -foldername [folder name] -
subscriptionid [Azure subscription ID]
```

Command Options

The following table describes the options available for the `New-AzureVirtualStandby` command:

Table 119: New-AzureVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points that you want to export.
-volumes	Optional. List of additional volume names to be exported. If you use the value <code>all</code>

Option	Description
	or use no value, then all volumes export. Values must be enclosed in double quotes and separated by a space. Do not use trailing slashes in volumes names; for example, use "c:" "d:".
-initialexport	Optional. Include this option if you need to start an initial ad-hoc virtual machines export to configure the virtual standby.
-cloudaccountname	Optional. You can use this option if you do not specify the -storageaccountname. It is the display name for the cloud account previously registered on the Core.
-storageaccountname	Optional. You can use this option if you do not specify the -cloudaccountname. It is the name of the storage account in Azure Classic.
-containername	The name of the container in the Azure storage account (classic). The name must contain between three and 63 characters (lowercase letters, numbers, and hyphens only), and start with a letter or a number. Every hyphen must be preceded and followed by a letter or number.
-foldername	Optional. The name of a folder inside of the Azure storage container. A folder name cannot contain any of the following characters: \ / : * ? " < > .
-subscriptionid	The identifier of a previously added Azure subscription.

Example:

Create a new Azure virtual standby:

```
>New-AzureVirtualStandby -protectedserver Win2008R2 -storageaccountname exports3 -
containername container1 -foldername Win2008R2 -subscriptionid 4db3a063-0d9c-42d8-
a994-d5e5c4b82c0
```

New-Base

The **New-Base** command forces a new base image resulting in a data transfer for the current protected machine. When you force a base image, the transfer will start immediately or will be added to the queue. Only the data that has changed from a previous recovery point will be transferred. If there is no previous recovery point, all data on the protected volumes will be transferred.

Usage

The usage for the command is as follows:

```
New-Base [[-all] | -protectedserver [machine name]] -core [host name] -user [user
name] -password [password]
```

Command Options

The following table describes the options available for the **New-Base** command:

Table 120: New-Base command options

Option	Description
-?	Display this help message.
-all	Base image for all agents.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Force for the current protected machine's name.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Force base image for all protected machines:

```
>New-Base -all
```

New-BootCD

This command lets you create a bare metal restore (BMR) boot CD without using the Rapid Recovery Core Console.

Usage

The usage for the command is as follows:

```
New-BootCD -core [host name] -user [user name] -password [password] -ip [IP address]
-mask [mask] -defaultgateway [defaultgateway] -dnsserver [dnsserver] -vncpassword
[vncpassword] -vncport [vncport] -isofilepath [destination for the boot image] -
driverspath [drivers path]
```

Command Options

The following table describes the options available for the `New-BootCD` command:

Table 121: New-BootCD command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-ip	Optional. This option specifies the IP address of the target BMR machine. By default, it generates automatically.
-mask	Optional. This option specifies the subnet mask of the target BMR machine. By default, it generates automatically.
-defaultgateway	Optional. This option specifies the default gateway of the target BMR machine. By default, it generates automatically.
-dnsserver	Optional. This option specifies the DNS server for the target BMR machine. By default, it generates automatically.
-vncpassword	Optional. This option specifies the user password for an existing UltraVNC account. By default, this option is empty.
-vncport	Optional. This option specifies the port to use for UltraVNC. You can change it only if you used the -vncpassword option. By default, the port is 5900.
-isofilepath	Optional. This option specifies the path to the boot CD file. The default path is C:\ProgramData\AppRecovery\Boot CDs.
-driverspath	Optional. This option specifies the path to the archive of drivers.

Example:

Create a boot CD:

```
>New-BootCD -ip 192.168.20.188 -mask 255.255.255.0 -defaultgateway 192.168.20.2 -
dnsserver 192.168.20.2 -isofilepath D:\bcd\newbcd3.iso
```

New-CloudAccount

The `New-CloudAccount` command lets you add a new cloud account to the Rapid Recovery Core.

Usage

The usage for the command is as follows:

```
New-CloudAccount -core [host name] -user [login] -password [password] -
displayname [display name] -type [cloud account type] -username [user name] - key [secret key] -region [region] -
tenantid [tenant Id] -authurl [authorization url]
```

Command Options

The following table describes the options available for the `New-CloudAccount` command:

Table 122: New-CloudAccount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-displayname	The name of the cloud account to display.
-type	The type of cloud account you want to add. Supported values include: <ul style="list-style-type: none">• amazon• openstack• rackspace• windowsazure• "windows azure"• azure
-username	The user name for the cloud account that you want to add. It is used in the authentication process. This property resolves as "Access Key" for Amazon™ cloud, "User Name" for Rackspace and OpenStack, and "Storage Account Name" for Windows Azure cloud accounts.
-key	The key for the cloud account you want to add. It is used in the authentication process. This property resolves as "Secret Key" for Amazon™ cloud, "Api Key" for Rackspace and OpenStack, and "Access Key" for a Windows Azure cloud accounts.
-region	The region of the cloud account that you want to add. This property is required only for RackSpace and OpenStack cloud accounts.
-tenantid	The identifier that is used in the authentication process of an OpenStack cloud account. This option is required only for OpenStack cloud accounts.
-authurl	The URL that is used in the authentication process of an OpenStack cloud account. This option is required only for OpenStack cloud accounts.

Example:

Create a new Amazon™ S3 cloud account named "Amazon S3 Account" with the access key "akey" and the secret key "skey."

```
>New-CloudAccount -displayname "Amazon S3 Account" -type Amazon -username akey  
-key skey
```

New-EncryptionKey

The `New-EncryptionKey` command lets you create a new encryption key for securing your Rapid Recovery backed up data.

Usage

The usage for the command is as follows:

```
New-EncryptionKey -core [host name] -user [login] -password [password] -name  
[encryption key name] -passphrase [pas  
sphrase] -comment [comment]
```

Command Options

The following table describes the options available for the `New-EncryptionKey` command:

Table 123: New-EncryptionKey command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-name	The name of the encryption key that you want to create.
-passphrase	The passphrase to the encryption key that you want to create.
-comment	Optional. The description of the encryption key.

Example:

Create an encryption key on the local Core:

```
>New-EncryptionKey -name EncryptionKey1 -passphrase 123456
```

New-EsxiVirtualStandby

The `New-EsxiVirtualStandby` PowerShell command lets you create a new ESXi virtual standby machine using Rapid Recovery.

Usage

The usage for the command is as follows:

```
New-EsxiVirtualStandby -core [host name] -user [login] -password [password] -
protectedserver [name | IP address] -volumes [volumes names] -vmname [virtual
machine name] -hostname [virtual host name] -hostport [virtual host port number] -
hostusername [virtual host login] -hostpassword [virtual host password] [-ram [total
megabytes] | -usesourceram] -diskprovisioning [thin | thick] -diskmapping [automatic
| manual | withvm] -initialexport
```

Command Options

The following table describes the options available for the `New-EsxiVirtualStandby` command:

Table 124: New-EsxiVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-volumes	Optional. List the volume names you want to export. If not specified, all volumes in the recovery point(s) are exported. Values must be enclosed in double quotes and separated by space; for example, "c:", "d:". Note: Do not use trailing slashes in volume names.
-vmname	The Microsoft Windows name of the virtual machine.
-hostname	The name of the virtual server host.
-hostport	The port number to use for communicating with the virtual server.
-hostusername	The user name for logging in to the virtual server host.

Option	Description
-hostpassword	The password for logging in to the virtual server host.
-ram	Allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server that the source protected machine has.
-diskprovisioning	Optional. The amount of disk space to allocate on the virtual machine. Available values include: <ul style="list-style-type: none"> Thick - Specify 'thick' to make the virtual disk as large as the original drive on the protected server. Thin - Specify 'thin' to allocate the amount of actual disk space occupied on the original drive plus some additional megabytes. The default disk provisioning is 'thin'.
-diskmappingjg	Optional. It determines how to map the disks from the recovery point to the virtual machine. Available values include: <ul style="list-style-type: none"> 'auto' 'manual' 'withvm' The default setting is 'auto'.
-initialexport	Optional. Specify this option if you need to start an initial on-demand virtual machine export after configuring the virtual standby.

Example:

Create a new ESXi virtual standby:

```
>New-EsxiVirtualStandby -protectedserver 10.10.10.4 -vmname ExportedMachine -
hostname 10.10.10.127 -hostport 443 -hostusername root -hostpassword pass123 -
usesourceram -diskprovisioning thin -diskmapping auto
```

New-FileSearch

The `New-FileSearch` command lets you search for a specific file among the recovery points in a repository, which helps you determine which recovery point you need to mount for a restore.

Usage

The usage for the command is as follows:

```
New-FileSearch -core [host name] -user [user name] -password [password] -
protectedserver [name | IP address] -startdate [start date] -enddate [end date]
-filemasks [file masks] -paths [paths] -subdiroff -ntfsfastoff -limitsearch
[limit search]
```

Command Options

The following table describes the options available for the `New-FileSearch` command:

Table 125: New-FileSearch command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle archive log mode.
-startdate	The earliest date of a period within you want to conduct your search. Use the date pattern "MM/DD/YYYY HH:mm:ss AM."
-enddate	The latest date of a period within you want to conduct your search. Use the date pattern "MM/DD/YYYY HH:mm:ss AM."
-filemasks	A combination of fixed and wildcard characters to search for the file. It can be one string or an array of strings. All masks should be separated by a space; for example: <code>-filemasks "first" "second."</code>
-paths	Optional. If there are specific directories in which you want to search, use this option to list the paths. It can be one string or an array of strings. All directories should be separated by a space; for example: <code>-paths "E:\" "C:\Program Files."</code>
-subdiroff	Optional. By default, the file search is performed in subdirectories. Use this option if you want to turn this feature off and not search in subdirectories.
-ntfsfastoff	Optional. By default, the file search is performed using the NTFS fast algorithm. If you want to perform the search without this feature, specify this option.
-limitsearch	Optional. Use this option to limit the number of search results. The default value is 1000.

Examples:

Perform a file search with one file mask:

```
New-FileSearch -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.10.10 -filemasks "sample"
```

Perform a file search with multiple file masks in specified directories and without the NTFS fast algorithm:

```
New-FileSearch -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.10.10 -filemasks "sample" "second" -paths "C:\dir" -ntfsfastoff
```

New-HyperVVirtualStandby

The `New-HyperVVirtualStandby` PowerShell command lets you create a new Hyper-V virtual machine (VM) using Rapid Recovery.

Usage

The usage for the command is as follows:

```
New-HyperVVirtualStandby -core [host name] -user [login] -password [password] -protectedserver [name | IP address]
    -volumes [volumes names] -vmname [virtual machine name] [-gen2] -useVhdx [-uselocalmachine] | -hostname [virtual host name] -hostport [virtual host port number] -hostusername [virtual host login] -hostpassword [virtual host password] -vmlocation [location] [-ram [total megabytes] | -usesourceram] -initialexport -exportvmconfigfiles
```

Command Options

The following table describes the options available for the `New-HyperVVirtualStandby` command:

Table 126: New-HyperVVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-volumes	Optional. List the volume names you want to export. If not specified, all volumes in the recovery point(s) are exported. Values must be enclosed in double quotes and separated by space; for example, "c:", "d:". Note: Do not use trailing slashes in volume names.
-vmname	The Microsoft Windows name of the virtual machine.
-gen2	Optional. Specify to use the second VM generation. If not specified, generation 1 is used. Rapid Recovery supports generation 2 from Windows Server 2012 R2 through Windows 8.1.
-usevhdx	Optional. If you specify this option, Rapid Recovery uses the VHDX disk format to create the VM. If you do not, it uses the VHD disk format. Generation 2 uses only the VHDX format.

Option	Description
-uselocalmachine	Optional. Connect to the local Hyper-V server. When you specify this value, Rapid Recovery ignores the following options: <ul style="list-style-type: none"> • hostname • hostport • hostusername • hostpassword
-hostname	The name of the virtual server host.
-hostport	The port number to use for communicating with the virtual server.
-hostusername	The user name for logging in to the virtual server host.
-hostpassword	The password for logging in to the virtual server host.
-vmlocation	Local or network path to the folder where you want to store the virtual machine files.
-ram	Allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server that the source protected machine has.
-initialexport	Optional. Specify this option if you need to start an initial on-demand virtual machine export after configuring the virtual standby.
-exportvmconfigfiles	Optional. Specify whether to export virtual machine configuration files. This option is available only both when the source is a virtual protected agentlessly and when the target hypervisor is the same as the source hypervisor.

Example:

Create a new Hyper-V virtual standby machine:

```
>New-HyperVVirtualStandby -core [host name] -user [login] -password [password] -
protectedserver [name | IP address]
    -volumes [volumes names] -vmname [virtual machine name] [-gen2] -useVhdx [-
uselocalmachine] | -hostname [virtual ho
    st name] -hostport [virtual host port number] -hostusername [virtual host login]
-hostpassword [virtual host passwo
    rd]] -vmlocation [location] [-ram [total megabytes] | -usesourceram] -
initialexport
```

New-Mount

The `New-Mount` command mounts a snapshot of one or more drives.

Usage

The usage for the command is as follows:

```
New-Mount -core [host name] -user [user name] -password [password] -protectedserver
[machine name] -mounttype [read | write | readonlywithpreviouswrites] -drives
[drive names] -path [location] -time [MM/DD/YYYY hh:mm:ss tt | passed | latest] -
rpn [number]
```

Command Options

The following table describes the options available for the `New-Mount` command:

Table 127: New-Mount command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-protectedserver	The protected server IP address or machine name (depends on how the particular machine was protected).
-time	Optional. The timestamp of the Recovery Point to mount. This should be in the format that is specified by the OS on the current PC. The administrator is able to get the latest recovery point by specifying latest or last checked recovery point by passed parameter value. By default the latest time option is chosen.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-path	Path on the Core machine to which recovery points will be mounted.
-mounttype	Optional. Specifies a mount mode. Available options are 'read', 'readOnlyWithPreviousWrites' (read-only with previous writes), 'write' (writable). Default mode is read-only.
-volumes	Optional. Space-separated list of volume names to mount. If the volume's name contains spaces or special characters, it has to be specified using double quotes. If not specified, all volumes will be mounted.
-rpn	Optional. Recovery point number for the mount. You can obtain this using the <code>get-mounts</code> command. Specify several numbers for the <code>rpn</code> parameter to mount different points with a single command. Note: If you set an array of points to mount, each point will be located in a separate child directory. The name describes the time when the recovery point was created. When you call <code>dismount</code> , all child directories will be removed. You should remove the parent directory manually.

Example:

```
>New-Mount -core 10.10.10.10:8006 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -path C:\MountedRecoveryPoint -mounttype read -
volumes c "d, ko"
```

Mount an array of recovery points:

```
>New-Mount -rpn 10 52 41 -protectedserver localhost -path "D:/Folder for mount"
```

Mount a recovery point with certain time created:

```
>New-Mount -protectedserver 10.10.5.56 -path "D:/Folder for mount" -time  
"8/24/2012 11:46 AM"
```

New-Replication

The `New-Replication` command lets you set up and force replication for a protected server or servers.

Usage

The usage for the command is as follows:

```
New-Replication -core [host name] -user [login] -password [password] -targetserver  
[host name] -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `New-Replication` command:

Table 128: New-Replication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-replicationname	Name of the replication configuration on the target Core.
-targetserver	The host name, user name, and password for the target Core.
-protectedserver	The name of the protected machine and repository on the target Core for setting up replication.

Example:

Create new replication for the protected machine with IP 10.10.10.4:
Pending examples from QA.

```
>New-Replication -targetserver 10.10.10.128 -protectedserver 10.10.10.4
```

New-Repository

The `New-Repository` command creates a new DVM repository in the Rapid Recovery Core. The size specified must be between 250MB and 16TB.

Usage

The usage for the command is as follows:

```
New-Repository | -name [name] -size [size] -datapath [location] -metadatapath [location]
```

Command Options

The following table describes the options available for the `New-Repository` command:

Table 129: New-Repository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-name	Repository name.
-size	Size of repository extent. Available units are: b, Kb, MB, GB, TB, PB.
-datapath	For local location only. Determines data path of repository extent.
-metadatapath	For local location only. Determines metadata path of repository extent.
-uncpath	For share location only. Determines data and metadata paths of repository extent.
-shareusername	For share location only. Determines login to share location.
-sharepassword	For share location only. Determines password to share location.
-comment	Optional. Description of repository.
-concurrent Operations	Optional. Maximum number of operations that can be pending at one time. Value by default: 64.

Example:

Create new DVM repository of minimum size in local drive E:

```
>New-Repository -name Repository2 -size 250Mb -datapath e:\Repository\Data -  
metadatapath e:\Repository\Metadata
```

New-ScheduledArchive

The `New-ScheduledArchive` command lets you use PowerShell to make changes to an existing scheduled archive.

Usage

The usage for the command is as follows:

```
New-ScheduledArchive -core [host name] -user [login] -password [password] -all | -  
protectedserver [name | IP address] -path [location] -archiveusername [name] -  
archivepassword [password] -cloudaccountname [name] -cloudcontainer [name] -  
recycleaction [type] -schdeuletype [type] -dayofweek [name] -dayofmonth [number] -  
time [time]
```

Command Options

The following table describes the options available for the `New-ScheduledArchive` command:

Table 130: New-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	The protected machine with recovery points that you want to archive. You can specify multiple machine names enclosed in double quotes and separated by commas.
-all	Archive recovery points for all protected machines.
-path	The path to where to save the archived data. For example: <ul style="list-style-type: none">Local machine: "d:\work\archive"Network path: "\\servername\sharename"Folder in a cloud account: "Folder Name" Note: The number of symbols should not be greater than 100 for local and network locations, and should not be greater than 150 for a cloud location.

Option	Description
-archiveusername	Optional. The user name for logging in to the remote machine. It is required for a network path only.
-archivepassword	Optional. The password for logging in to the remote machine. It is required for a network path only.
-cloudaccountname	Optional. Use only for cloud archiving. The name of the cloud account where you want to save the archive.
-cloudcontainer	Optional. Use only for cloud archiving. The name of the cloud container in the chosen cloud account, where the archive will be saved. When you use this option, you should also specify the "-cloudaccountname" parameter.
-recycleaction	<p>The type of recycle action. Specified by using one of the following four values:</p> <ul style="list-style-type: none"> "replacethiscore" - Overwrites any pre-existing archived data pertaining to this Core, but leaves the data for other Cores intact. "erasecompletely" - Clears all archived data from the directory before writing the new archive. "incremental" - Lets you add recovery points to an existing archive. It compares recovery points to avoid duplicating data that already exists in the archive.
-scheduletype	<p>Type of schedule interval. Specified the option with one of the following four values:</p> <ul style="list-style-type: none"> "daily" - For a daily automatically created archive. "weekly" - For a weekly automatically created archive. You must specify the "-dayofweek" parameter. "monthly" - For a monthly automatically created archive. You must specify the "-dayofmonth" parameter. If a month does not have the day specified—for example, "31"—then the archive will not occur for that month. "lastdayofmonth" - For automatically creating an archive on the last day of each month.
-dayofweek	Use only for the "weekly" option of the "-scheduletype" parameter. The day of the week on which to automatically create the archive (for example, "Monday").
-dayofmonth	Use only for the "month" option of the "-scheduletype" parameter. The day (number) of the month on which to automatically create the archive (for example, "15").
-time	The hour of the day when you want to create an archive.
-initialpause	Optional. Specify this option if you want to initially pause archiving after you configure the archiving schedule.

Examples:

Archive all recovery points with creation dates starting from 04/30/2012 02:55 PM for all machines on the Core, and replace pre-existing archived data pertaining to this Core:

```
>New-ScheduledArchive -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
path "d:\work\archive" -s
tartdate "04/30/2012 02:55 PM" -all -recycleaction replacethiscore
```

Archive recovery points that fall within a date range for two protected machines, and clear all archived data from the directory before writing the new archive:

```
>New-ScheduledArchive -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
protectedserver "10.20.30.40" "20.20.10.1" -path "d:\work\archive" -startdate
"04/30/2012 02:55 PM" -enddate "05/31/2012 11:00 AM" -recycleaction erasecompletely
```

Create an incremental archive for all recovery points with creation dates starting from 04/30/2012 02:55 PM for all machines on the Core to the cloud account with the name "Amazon S3" and a container named "Container":

```
>New-ScheduledArchive -core 10.10.10.10 -user administrator -password 23WE@#$sdd -
path "ArchiveOnCloud" -cloudaccountname "Amazon S3" -cloudcontainer "Container" -
startdate "04/30/2012 02:55 PM" -all -recycleaction incremental
```

New-Snapshot

The `New-Snapshot` command forces a snapshot resulting in a data transfer for the current protected machine. When you force a snapshot, the transfer will start immediately or will be added to the queue. Only the data that has changed from a previous recovery point will be transferred. If there is no previous recovery point, all data on the protected volumes will be transferred.

Usage

The usage for the command is as follows:

```
New-Snapshot [-all] | -protectedserver [machine name]] -core [host name] -user [user
name] -password [password]
```

Command Options

The following table describes the options available for the `New-Snapshot` command:

Table 131: New-Snapshot command options

Option	Description
-?	Display this help message.
-all	Force all protected machines.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Force for the current protected machine's name.

Option	Description
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Force a snapshot for all protected machines:

```
>New-Snapshot -all
```

New-VBVirtualStandby

The `New-VBVirtualStandby` command lets you use PowerShell to create a new virtual export to a VirtualBox virtual machine (VM).

Usage

The usage for the command is as follows:

```
New-VBVirtualStandby -core [host name] -user [login] -password [password] -
protectedserver [name | IP address] -volumes [volumes names] -vmname [virtual
machine name] [-ram [total megabytes] | -usesourceram] -linuxhostname [linux
hostname] -hostport [linux port] -targetpath [location] -pathusername [login] -
pathpassword [password] -initialexport
```

Command Options

The following table describes the options available for the `New-VBVirtualStandby` command:

Table 132: New-VBVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-volumes	Optional. List the volume names you want to export. If not specified, all volumes in the

Option	Description
	recovery point(s) are exported. Values must be enclosed in double quotes and separated by space; for example, "c:", "d:". Note: Do not use trailing slashes in volume names.
-vmname	The Microsoft Windows name of the virtual machine.
-ram	Allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server that the source protected machine has.
-linuxhostname	The Linux VirtualBox server host name.
-hostport	The Linux VirtualBox server port.
-targetpath	The local, network, or Linux path to the folder where you want to store the virtual machine files.
-pathusername	The user name for logging in to the network machine. It is only required when you specify a network location for the target path.
-pathpassword	The password for logging in to the network machine. It is only required when you specify a network location for the target path.
-accountusername	Optional. You can specify a user account with which to register the exported virtual machine. It is the user name for logging in to the user account. Use this option for a local or network machine only.
-accountpassword	Optional. You can specify a user account with which to register the exported virtual machine. It is the password for logging in to the user account. Use this option for a local or network machine only.
-initialexport	Optional. Specify this option if you need to start an initial on-demand virtual machine export after configuring the virtual standby.

Example:

Create a VirtualBox virtual standby machine named ExportedMachine1 in a specified location:
Pending example from QA.

```
>New-VBVirtualStandby -protectedserver 10.10.10.4 -volumes C:\ -vmname
ExportedMachine1 -usesourceram -targetpath I:\VMExport
```

New-VMVirtualStandby

The `New-VMVirtualStandby` PowerShell command lets you create a new VMware Workstation virtual standby machine using Rapid Recovery.

Usage

The usage for the command is as follows:

```
New-VMVirtualStandby -core [host name] -user [login] -password [password] -
protectedserver [name | IP address] -volumes [volumes names] -vmname [virtual
```

```
machine name] [-ram [total megabytes] | -usesourceram] -targetpath [location] -
pathusername [login] -pathpassword [password] -initialexport
```

Command Options

The following table describes the options available for the `New-VMVirtualStandby` command:

Table 133: New-VMVirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Show jobs for a specific protected machine, indicated by IP address.
-volumes	Optional. List the volume names you want to export. If not specified, all volumes in the recovery point(s) are exported. Values must be enclosed in double quotes and separated by space; for example, "c: "; "d:". Note: Do not use trailing slashes in volume names.
-vmname	The Microsoft Windows name of the virtual machine.
-ram	Allocate a specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server that the source protected machine has.
-pathusername	The user name for logging in to the network machine. It is only required when you specify a network location for the target path.
-pathpassword	The password for logging in to the network machine. It is only required when you specify a network location for the target path.
-initialexport	Optional. Specify this option if you need to start an initial on-demand virtual machine export after configuring the virtual standby.

Example:

Create a new VMware Workstation virtual standby:

```
>New-VMVirtualStandby -protectedserver 10.10.10.4 -volumes C:\ -vmname
ExportedMachine1 -usesourceram -targetpath I:\VMExport
```

Script pauses, requiring user to specify an index number for the appropriate workstation. Enter the index number for the script to complete (in this case, 2). Example continues:

```
2
Verify location ...
Virtual Standby successfully configured
PS C:\Users\Administrator>
```

Push-Replication

The `Push-Replication` command forces replication for one or more protected machines.

Usage

The usage for the command is as follows:

```
Push-Replication -core [host name] -user [user name] -password [password] -
targetcore [host name] -all | -protectedserver [machine name | IP address]
```

Command Options

The following table describes the options available for the `Push-Replication` command:

Table 134: Push-Replication command options

Option	Description
-?	Display this help message.
-all	Force replication for all machines being replicated to the target Core.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Protected machine name on the target Core against which to force replication.
-user	Optional. Login for the remote Core host machine. If you specify a login, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Push replication for a single protected machine:

```
>Push-Replication -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd
  -targetcore 10.10.10.20:8006 -protectedserver 10.10.5.22
```

Push replication for all protected machines:

```
>Push-Replication -all
```

Push-Rollup

The `Push-Rollup` command forces rollup for a protected machine.

Usage

The usage for the command is as follows:

```
Push-Rollup -core [host name] -user [user name] -password [password] -  
protectedserver [machine name | IP address]
```

Command Options

The following table describes the options available for the `Push-Rollup` command:

Table 135: Push-Rollup command options

Option	Description
-?	Display this help message.
-all	Force all protected machines.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Force for the current protected machine's name.
-user	Optional. Login for the remote Core host machine. If you specify a login, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Push rollup for a single protected machine:

```
>Push-Rollup -core 10.10.10.10:8006 -user administrator -password 23WE@#sdd -  
protectedserver 10.10.5.22
```

Push rollup for all protected machines:

```
>Push-Rollup -all
```

Remove-Agent

The `Remove-Agent` PowerShell command lets you remove a machine from Rapid Recovery Core protection.

Usage

The usage for the command is as follows:

```
Remove-Agent -core [host name] -user [login] -password [password] -protectedserver  
[name | IP address] -deleterecoverypoints -all
```

Command Options

The following table describes the options available for the `Remove-MountAgent` command:

Table 136: Remove-Agent command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Dismount all mounted recovery points for the current protected machine.
-deleterecoverypoints	Optional. Delete all recovery points for this protected machine.
-all	Optional. Delete all protected machines from the Core.

Example:

Dismount all protected machines and their recovery points:

```
>Remove-Agent -core 10.10.10.10:8006 -user administrator -password 23WE@#sdd -  
deleterecoverypoints -all
```

Remove-EsxAutoProtectObjects

The `Remove-EsxAutoProtectObjects` cmdlet lets you remove specific objects on vCenter or ESXi server from protection by a Core.

Usage

The usage for the command is as follows:

```
Remove-EsxAutoProtectObjects -core [host name] -user [user name] -password  
[password] -protectedserver [name | IP address] -autoprotectobjects
```

Command Options

The following table describes the options available for the `Remove-EsxAutoProtectObjects` command:

Table 137: Remove-ESXAutoProtectObjects command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
<code>-protectedserver</code>	Use this option to edit the vCenter or ESXi objects for a specific protected machine.
<code>-autoprotectobjects</code>	A list of vCenter or ESXi objects each enclosed in double quotes and separated by a comma.

Example:

Remove specific vCenter or ESXi objects from protection auto-protection by the Core:

```
>Remove-EsxAutoProtectObjects -protectedserver 10.10.8.150 -autoprotectobjects  
"vm1", "vm2"
```

Remove-HyperVClusterSharedVirtualDisks

The `Remove-HyperVClusterSharedVirtualDisks` cmdlet lets you remove shared Hyper-V virtual disks from protection of a Core.

Usage

The usage for the command is as follows:

```
Remove-HyperVClusterSharedVirtualDisks -core [host name] -user [user name] -password  
[password] -sharedddisks [shared virtual disks name or path collection | all]
```

Command Options

The following table describes the options available for the `Remove-HyperVClusterSharedVirtualDisks` command:

Table 138: Remove-HyperVClusterSharedVirtualDisks command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Use this option to edit the shared virtual disks for a specific protected machine.
-shareddisks	A list of shared disks each separate by a comma.

Example:

Remove one shared virtual disk from protection:

```
>Remove-HyperVClusterSharedVirtualDisks -protectedserver "HV-2012R2" -shareddisks  
"Shared Disk 1"
```

Remove-HyperVClusterVirtualMachines

The `Remove-HyperVClusterVirtualMachines` cmdlet lets you remove specific virtual machines (VMs) of a Hyper-V cluster from protection of a Core.

Usage

The usage for the command is as follows:

```
Remove-HyperVClusterVirtualMachines -core [host name] -user [user name] -password  
[password] -repository [name] -protectedserver [name | IP address] -virtualmachines  
[virtual machines collection | all]
```

Command Options

The following table describes the options available for the `Remove-HyperVClusterVirtualMachines` command:

Table 139: Remove-HyperVClusterVirtualMachines command options

Option	Description
-?	Display this help message.

Option	Description
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Use this option to protect virtual machines.
-virtualmachines	A list of the virtual machines that you want to protect, each separated by a comma. The name of the VM must be enclosed in double quotes.
-deleterecoverypoints	Optional. Include this option if you want to delete all of the recovery points for this VM.

Example:

Remove specific virtual machines of a Hyper-V cluster from protection by the Core and delete its recovery points:

```
>Remove-HyperVClusterVirtualMachines -protectedserver hvcluster -virtualmachines
"Win8x64-gen1", "Win2012x64-gen2" -deleterecoverypoints
```

Remove-HyperVVirtualMachines

The `Remove-HyperVVirtualMachines` cmdlet lets you remove specific Hyper-V virtual machines (VMs) from the protection of a Core.

Usage

The usage for the command is as follows:

```
Remove-HyperVVirtualMachines -core [host name] -user [user name] -password
[password] -protectedserver [name | IP address] -virtualmachines [virtual machines
collection | all] -deleterecoverypoints
```

Command Options

The following table describes the options available for the `Remove-HyperVVirtualMachines` command:

Table 140: Remove-HyperVVirtualMachines command options

Option	Description
-?	Display this help message.

Option	Description
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Use this option to edit Hyper-V objects for a specific virtual machine.
-virtualmachines	A list of the virtual machines that you want to protect, each separated by a comma. The name of the VM must be enclosed in double quotes.
-deleterecoverypoints	Optional. Include this option if you want to delete all of the recovery points for this VM.

Example:

Remove specific Hyper-V VMs from protection and delete its recovery points:

```
>Remove-HyperVVirtualMachines -protectedserver HVServer1 -virtualmachines "Win8x64-gen1", "Win2012x64-gen2" -deleterecoverypoints
```

Remove-Mount

The `Remove-Mount` command dismounts a mounted recovery point specified by the `/Path`. Dismount points for the selected machine using the `-protectedserver` parameter or dismount points for all the mounted recovery points by using the `-all` parameter.

Usage

The usage for the command is as follows:

```
Remove-Mount -core [host name] -user [user name] -password [password] [-protectedserver [machine name] | -path [mount path]]
```

Command Options

The following table describes the options available for the `Remove-Mount` command:

Table 141: Remove-Mount command options

Option	Description
-?	Display this help message.

Option	Description
-all	Dismount all mounted recovery points.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-path	Dismount selected mount point.
-protectedserver	Dismount all mounted recovery points for the current protected machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Dismount the recovery point specified by the path:

```
>Remove-Mount -core 10.10.10.10:8006 -user administrator -password 23WE@#sdd -path C:\mountedRecoveryPoint
```

Remove-Mounts

The `Remove-Mounts` command dismounts all mounted recovery points.

Usage

The usage for the command is as follows:

```
Remove-Mounts -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Remove-Mounts` command:

Table 142: Remove-Mounts command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also

Option	Description
	have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Dismount all recovery points on the specified Core:

```
>Remove-Mounts -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd
```

Remove-RecoveryPoints

The `Remove-RecoveryPoints` PowerShell command lets you delete recovery points for a specific machine.

Usage

The usage for the command is as follows:

```
Remove-RecoveryPoints -core [host name] -user [login] -password [password] -[range | chain | all] -protectedserver [name | IP address] -rpn [number | numbers] | -time [time string | time interval specified by two time strings]
```

Command Options

The following table describes the options available for the `Remove-RecoveryPoints` command:

Table 143: Remove-RecoveryPoints command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Dismount all mounted recovery points for the current protected machine.
-rpn	Optional. Only for chain deletion (base image with chain of incrementals or orphaned points). The sequential number of a recovery point to be deleted (use the <code>Get-RecoveryPoints</code> command to obtain the numbers). You can specify several space-separated numbers to delete multiple recovery points with a single command.

Option	Description
-time	Use this option to delete a chain of recovery points. Optional. To delete a single recovery point, select the recovery point by its creation time. Specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify date and time values of the time zone set on your computer. Required. For a date range, specify a time interval using two time strings separated by coma and space to select the range of recovery points to delete.
-range	Optional. The range of recovery points to delete by time interval.
-chain	Optional. A base image with sequential incrementals or a sequential set of orphaned points to delete selected by recovery point number or time of recovery point creation.
-all	Optional. Delete all protected machines from the Core.

Example:

Delete the recovery point specified by the date:

```
>Remove-RecoveryPoints -core 10.10.10.10:8006 -user administrator -password
23WE@#$sdd -time "2/24/2012 09:00 AM"
```

Remove-RemoteMount

The `Remove-RemoteMount` command dismounts a remotely mounted recovery point.

Usage

The usage for the command is as follows:

```
Remove-RemoteMount -core [host name] -user [user name] -password [password] [-
protectedserver [machine name] | -path [mount path]]
```

Command Options

The following table describes the options available for the `Remove-RemoteMount` command:

Table 144: Remove-Mount command options

Option	Description
-?	Display this help message.
-all	Dismount all mounted recovery points.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you

Option	Description
	also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-path	Dismount selected mount point.
-protectedserver	Dismount all mounted recovery points for the current protected machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Examples:

Dismount the remotely mounted recovery point by a specified path:

```
>Remove-RemoteMount -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd -path C:\mountedRecoveryPoint
```

Dismount all remotely mounted recovery points for a specified protected server:

```
>Remove-RemoteMount -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver "11.11.11.11"
```

Remove-RemoteMounts

The `Remove-RemoteMounts` command dismounts all remotely mounted recovery points.

Usage

The usage for the command is as follows:

```
Remove-RemoteMounts -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Remove-RemoteMounts` command:

Table 145: Remove-RemoteMounts command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also

Option	Description
	have to provide a password. If none are provided, then the logged-on user's credentials will be used.

Example:

Dismount all remotely mounted recovery points:

```
>Remove-RemoteMounts -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd
```

Remove-Replication

This command lets you remove a replication configuration from a source Core or target Core, as well as remove replicated recovery points.

Usage

The usage for the command is as follows:

```
Remove-Replication -core [host name] -user [user name] -password [password] -incoming [host name] -outgoing [host name] -deletepoints
```

Command Options

The following table describes the options available for the `Remove-Replication` command:

Table 146: Remove-Replication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-incoming	The identifier (ID) of the incoming replication that should be deleted. It could be a remote Core ID or a host name. Use the word "all" to delete all replications. Note: You can specify different protected machines for different replications by using the following pattern: <code>Replication1:Agent1,Agent2;Replication2:Agent2,Agent3</code> . If you do not specify a machine after the colon (:), the replication is deleted for all replicated machines.

Option	Description
-outgoing	The identifier (ID) of the outgoing replication that should be deleted. It could be a remote Core ID or a host name. Use the word "all" to delete all replications. Note: You can specify different protected machines for different replications by using the following pattern: Replication1:Agent1,Agent2;Replication2:Agent2,Agent3. If you do not specify a machine after the colon (:), the replication is deleted for all replicated machines.
-deletepoints	Specify which recovery points, if any, of the replicated machine that you want to remove.

Example:

Delete all incoming and all outgoing replications:

```
>Remove-Replication -incoming all -outgoing all
```

Delete two outgoing replications with all machines:

```
>Remove-Replication -outgoing TargetCore1;TargetCore2
```

Delete one protected machine from incoming replication and delete recovery points:

```
>Remove-Replication -incoming TargetCore1:10.10.10.10 -deletepoints
```

Remove-Repository

The `Remove-Repository` PowerShell command deletes a Rapid Recovery repository and its contents from the Core.

Usage

The usage for the command is as follows:

```
Remove-Repository -core [host name] -user [login] -password [password] -name  
[repository name] -all
```

Command Options

The following table describes the options available for the `Remove-Repository` command:

Table 147: Remove-Repository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also

Option	Description
	have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-name	The name of the repository that you want to delete.
-all	Delete all repositories associated with this Core.

Example:

Remove all repositories on the local Core:

```
>Remove-repository -all
```

Remove-ScheduledArchive

If you scheduled Rapid Recovery to regularly archive recovery points for a specific machine, you can use the `Remove-ScheduledArchive` PowerShell command to remove that scheduled archive from the Core.

Usage

The usage for the command is as follows:

```
Remove-ScheduledArchive -core [host name] -user [login] -password [password] -all -ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `Remove-ScheduledArchive` command:

Table 148: Remove-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.

Option	Description
-all	Remove all archives associated with this Core.
-id	The identifier of the archive that you want to remove. To list more than one archive, separate each ID with a space.

Example:

Remove several scheduled archives from the local Core:

```
>Remove-ScheduledArchive -ids 799138c8-3dfc-4398-9711-1823733c2a31, 26c29bb7-b320-47f5-b5a8-dffc49f50e25
```

Remove-VirtualStandby

If you scheduled Rapid Recovery to continuously export data to a virtual machine, then you can use the `Remove-VirtualStandby` PowerShell command to cancel and delete this scheduled job.

Usage

The usage for the command is as follows:

```
Remove-VirtualStandby -core [host name] -user [login] -password [password] -all | -protectedserver [name(s) | IP address]
```

Command Options

The following table describes the options available for the `Remove-VirtualStandby` command:

Table 149: Remove-VirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Remove all virtual standby jobs associated with this Core.
-protectedserver	The name or IP address for the protected machine for which you want to remove virtual standby.

Example:

Remove all virtual standby jobs associated with this Core:

```
>Remove-VirtualStandby -all
```

Restart-CoreService

If the Core service on the Core machine is stopped, use the `Restart-CoreService` command to start it again.

Usage

The usage for the command is as follows:

```
Restart-CoreService -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false] -wait [time in seconds]
```

Command Options

The following table describes the options available for the `Restart-CoreService` command:

Table 150: Restart-CoreService command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."
-wait	Optional. This option indicates that the command should wait until the Core service is fully restarted for the specified period of time in seconds before canceling active jobs.

Example:

Restart the Core service:

```
>Restart-CoreService -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true -wait 600
```

Resume-Replication

The `Resume-Replication` command lets you resume replication. See [Suspend-Replication](#) for more details.

Usage

The usage for the command is as follows:

```
Resume-Replication -core [host name] -user [user name] -password [password] -all  
| -protectedserver [machine name | IP address] -incoming [host name] | -  
outgoing [host name]
```

Command Options

The following table describes the options available for the `Resume-Replication` command:

Table 151: Resume-Replication command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-all	All protected servers.
-protectedserver	Resume replication for the specified machine.
-incoming	Host name of the remote Core that replicates to the Core machine. Replication is resumed for all protected machines on the remote Core.
-outgoing	Host name of the remote target core to which data is replicating. Replication is resumed for all protected machines on the remote core.

Example:

Resume replication for the protected machine with IP 10.10.10.128 for the local Core, specifying the repository being used:

```
>Resume-Replication replicationname Replication1 -targetserver  
10.10.10.128,Administrator,123asdQ -protectedserver 10.10.10.4
```

```
# Repository  
- -----
```

```

1 Repository A
2 Repository B
Please, input number of Repository from the list above or type 'exit' to exit:

Script pauses, requiring user to specify an index number for the appropriate repository. Enter the index number for
the script to complete (in this case, 2). Example continues:

2
Replication job was started.
True
PS C:\Users\Administrator>

```

Resume-ScheduledArchive

The `Resume-ScheduledArchive` command lets you resume a scheduled archive that had been paused or stopped.

Usage

The usage for the command is as follows:

```
Resume-ScheduledArchive -core [host name] -user [user name] -password [password] -
all -ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `Resume-ScheduledArchive` command:

Table 152: Resume-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-all	Use this option to force all scheduled archives.
-ids	The identifier (ID) or IDs separated by spaces of the scheduled archives that you want to force.

Examples:

Resume all scheduled archives:

```
>Resume-ScheduledArchive -all
```

Resume one scheduled archive:

```
>Resume-ScheduledArchive -ids 6c123c39-5058-4586-bd0c-7c375e72017b
```

Resume multiple scheduled archives:

```
>Resume-ScheduledArchive -ids 6c123c39-5058-4586-bd0c-7c375e72017b, 26c29bb7-b320-47f5-b5a8-dffc49f50e25
```

Resume-Snapshot

An administrator is able to resume snapshots, export to virtual machines, and perform replication. See [Start-VMExport](#) for more details.

Usage

The usage for the command is as follows:

```
Resume-Snapshot -core [host name] -user [user name] -password [password] -all | -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Resume-Snapshot` command:

Table 153: Resume-Snapshot command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-all	All protected servers.
-protectedserver	Resume snapshot for the specified machine.

Example:

Resume snapshots for the protected machine with IP 10.10.10.4 for the local Core:

```
>Resume-Snapshot -protectedserver 10.10.10.4
```

Resume-VirtualStandby

The `Resume-VirtualStandby` PowerShell command lets you resume the suspended export of data to a Rapid Recovery virtual standby machine.

Usage

The usage for the command is as follows:

```
Resume-VirtualStandby -core [host name] -user [login] -password [password] -all | -protectedserver [name(s) | IP address]
```

Command Options

The following table describes the options available for the `Resume-VirtualStandby` command:

Table 154: Resume-VirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Resume exports for all virtual standby machines.
-protectedserver	The name or names—separated by a comma and space—of the protected machines with virtual standby machines that you want to resume.

Example:

Resume virtual standby exports for a protected machine:

```
>Resume-VirtualStandby -core 10.10.10.10:8006 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22
```

Set-AgentMetadataCredentials

The `Set-AgentMetadataCredentials` command sets the metadata credentials for a specified protected machine.

Usage

The usage for the command is as follows:

```
Set-AgentMetadataCredentials -core [host name] -user [user name] -password  
[password] -protectedserver [name | IP address] -target [default | SQL | Exchange] -  
metadatausername [user name] -metadatapassword [password] -sqlinstancename [SQL  
instance name] -usewindowsauthentication
```

Command Options

The following table describes the options available for the `Set-AgentMetadataCredentials` command:

Table 155: Set-AgentMetadataCredentials command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the protected machine.
-target	Optional. The type of metadata, such as SQL, Exchange, or default.
-metadatausername	Optional. The metadata-related login.
-metadatapassword	Optional. The metadata-related password.
-sqlinstancename	Optional. The specific SQL instance name. Use this option in conjunction with the -target "sql."
-usewindowsauthentication	Optional. Use this option if your SQL credentials are also used for Windows authentication.

Example:

Set credentials for Exchange metadata:

```
>Set-AgentMetadataCredentials -core 10.10.10.10 -user administrator -password -  
23WE@#$sdd -protectedserver 10.10.20.20 -target exchange -metadatausername  
administrator -metadatapassword 123#
```

Set-DedupCacheConfiguration

This command lets you use the Command Line Utility to set the location, size, and metadata location for the primary and secondary cache of a DVM repository.

Usage

The usage for the command when creating a DVM repository is as follows:

```
Set-DedupCacheConfiguration -core [host name] -user [user name] -password [password]
-primary [cache location] -secondary [cache location] -metadata [metadata location]
-size [cache size] -restoredefault
```

Command Options

The following table describes the options available for the `Set-DedupCacheConfiguration` command:

Table 156: Set-DedupCacheConfiguration command options

Option	Description
-?	Display help on the command.
-core	Optional. Remote core host machine IP address (with an optional port number). By default, the connection is made to the core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-primary	Optional. Primary cache location.
-secondary	Optional. Secondary cache location.
-metadata	Optional. Metadata cache location.
-size	Optional. Deduplication cache size in GB.
-restoredefault	Optional. Restore to default deduplication cache configuration. If this parameter is specified, all other parameters are ignored.

Examples:

Set primary deduplication cache location and deduplication cache size:

```
>Set-DedupCacheConfiguration -primary D:\primary -size 6
```

Set secondary and metadata deduplication location:

```
>Set-DedupCacheConfiguration -secondary D:\secondary -metadata D:\metadata
```

Restore default deduplication configuration:

```
>Set-DedupCacheConfiguration -restoredefault
```

Set-License

There may be times when you need to change the Rapid Recovery license applied to a machine, such as when moving from a trial license to a subscription or perpetual license. In such instances, you can change the license in the Command Prompt by using the `Set-License` command.

Usage

The usage for the command is as follows:

```
Set-License -core [host name] -user [user name] -password [password] -licensekey  
[license key] -licensepath [license file path] -licensenumbr [license number] -  
email [email address]
```

Command Options

The following table describes the options available for the `Set-License` command:

Table 157: Set-License command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-licensekey	Optional. A 30-character key comprising six groups of five alphanumeric characters, each separate by a hyphen. Use this key when a license file is not available.
-licensepath	Optional. The path to the file that ends with the .lic extension. If a license file is available, you can use this option instead of the <code>-licensekey</code> .
-licensenumbr	Optional. You may have received this nine-digit license number in an order confirmation email. If you provide this number, use the email address that received it for verification.
-email	Optional. If you use the <code>-licensenumbr</code> , you must include the email address that received it for verification.

Examples:

Change the license key associated with this Core to JL09F-89FSD-6THFS-DSE34-KS3D5-65DF2:

```
>Set-License -core 10.10.10.10 -user admin -password 676df#df -licensekey JL09F-89FSD-6THFS-DSE34-KS3D5-65DF2
```

Change the license key associated with this Core to the key contained in the license file:

```
>Set-License -core 10.10.10.10 -user admin -password 676df#df -licensepath C:\MyLicenseFile.lic
```

Change the license number associated with this Core to 111-111-111 using john.doe@example.com to verify the license:

```
>Set-License -core 10.10.10.10 -user admin -password 676df#df -licensenum 111-111-111 -email john.doe@example.com
```

Set-OracleMetadataCredentials

The `Set-OracleMetadataCredentials` command lets you set the metadata credentials for a specified Oracle instance.

Usage

The usage for the command is as follows:

```
Set-OracleMetadataCredentials -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -instancename [Oracle instance SID] -connectiontype [-basic | TNS] -hostname [host name | IP address] -port [port number] [-usesid] -instanceservicename [service name] -tnsnetworkalias [TNS alias] [-usewindowsauthentication] -oracleusername [user name] -oraclepassword [password] [-edit]
```

Command Options

The following table describes the options available for the `Set-OracleMetadataCredentials` command:

Table 158: Set-OracleMetadataCredentialscommand options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-protectedserver	The name or IP address of the protected machine.
-instancename	The Oracle SID from which you want to fetch metadata.
-connectiontype	Use this option to identify the connection type. It must be represented by either <code>basic</code> or <code>TNS</code> .
-hostname	Optional. The name of the Oracle host. Use it for the <code>basic</code> connection type.
-port	Optional. A port number. Use it for the <code>basic</code> connection type.
-usesid	Optional. This option uses the <code>-instancename</code> to identify the Oracle instance. Use it for the <code>basic</code> connection type.
-instanceservicename	Optional. The Oracle instance service name. Use it when the <code>-usesid</code> is not specified and for the <code>basic</code> connection type.
-tnsnetworkalias	Optional. Use this option to identify the TNS network alias when using the <code>TNS</code> connection type.
-usewindowsauthentication	Optional. This option lets you authenticate with your Windows credentials.
-oracleusername	Optional. The user name for the Oracle instance.
-oraclepassword	Optional. The password for the Oracle instance.
-edit	Optional. This option lets you omit any number of options.

Examples:

Set the metadata credentials for the ORCL instance on a protected server using the `basic` connection type:

```
>Set-OracleMetadataCredentials -core 10.10.127.42 -user admin -password -676df#df -
protectedserver 10.10.34.88 -instancename ORCL -connectiontype basic -hostname
localhost -port 1521 -usesid -oracleusername User-ORA -oraclepassword 676df#df
```

Set the metadata credentials for the ORCL instance on a protected server using the `TNS` connection type and Windows authentication:

```
>Set-OracleMetadataCredentials -core 10.10.127.42 -user admin -password -676df#df -
protectedserver 10.10.34.88 -instancename ORCL -connectiontype TNS -tnsnetworkalias
ORCL_ALIAS -usewindowsauthentication
```

Set-ReplicationResponse

Use the `Set-ReplicationResponse` command to manage pending replication requests.

Usage

The usage for the command is as follows:

```
Set-ReplicationResponse -core [host name] -user [user name] -password [password] -id
[replication ID] -accept | -deny | -ignore -protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Set-ReplicationResponse` command:

Table 159: Set-ReplicationResponse command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
<code>-id</code>	The identifier for the replication job or pending replication request. It can be a remote Core ID, host name, customer ID, email address, or pending replication request ID.
<code>-accept</code>	Accepts the replication request.
<code>-deny</code>	Denies the replication request.
<code>-ignore</code>	Ignores the replication request.
<code>-protectedserver</code>	When responding to a replication request, use this option to apply your response to list of protected servers with a repository name or ID. Use the parameter "all" to apply response to all requested machines.

Examples:

Accept a pending replication request for one protected machines:

```
>Set-ReplicationResponse -id customer@email.address -accepted -protectedserver 10.10.1.1 Repository1 10.10.1.2 Repository2 -responsecomment A response comment
```

Deny a pending replication request:

```
>Set-ReplicationResponse -id customer@email.address -deny
```

Start-Archive

Businesses often use long-term storage to archive both compliant and non-compliant data. The archive feature in Rapid Recovery is used to support the extended retention for compliant and non-compliant data. The administrator can save an archive on the local storage or network location by specifying the `/Path` command and credentials.

Usage

The usage for the command is as follows:

```
Start-Archive -path -startdate -enddate [-all] | -protectedserver [machine name] or [IP]] -core [host name] -user [user name] -password [password]
```

Command Options

The following table describes the options available for the `Start-Archive` command:

Table 160: Start-Archive command options

Option	Description
-?	Display this help message.
-path	Location path. Example path: 'D:\work\archive' or network path: '\\servername\sharename'.
-all	Archive recovery points for all machines on the Core.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-startdate	Start date of the date range for the created recovery points. Should be in the format specified by the OS on the current PC.
-enddate	End date of the date range. Defaults to the current time.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Archive recovery points for the specified machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-archiveusername	Optional. Required for network path only.
-archivepassword	Optional. Required for network path only.
-comment	Optional. Example: <code>-comment 'Before install new application'</code> .

Example:

Archive all recovery points for all machines on the Core:

```
>Start-Archive -path D:\work\archive -startdate 'Example 04/30/2012' -all
```

Start-AttachabilityCheck

The `Start-AttachabilityCheck` command forces an attachability check for all SQL Server databases protected by the Core.

Usage

The usage for the command is as follows:

```
Start-AttachabilityCheck -core [host name] -user [username] - password [password]
    - protectedserver [machine name | IP address] -rpn [number | numbers] | -time
[time string]
```

Command Options

The following table describes the options available for the `Start-AttachabilityCheck` command:

Table 161: Start-AttachabilityCheck command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	The protected machine on which to perform the SQL attachability check.
-rpn	Optional. The sequential number of a recovery point on which to perform the SQL attachability check. You can use the <code>-GetRecoveryPoints</code> command to obtain recovery point numbers. You can specify several space-separated numbers to perform the checks against multiple recovery points with a single command. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point is used for the attachability check.
-time	Optional. Determines recovery point to be selected for SQL attachability check. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.

Example:

Perform a SQL attachability check on the most recent recovery point for the specified protected SQL server:

```
>Start-AttachabilityCheck - protectedserver 10.10.9.120
```

Start-AzureDeploy

You can use the `Start-AzureDeploy` command to export a virtual machine (VM) to a Microsoft Azure cloud account.

Usage

The usage for the command is as follows:

```
Start-AzureDeploy -core [host name] -user [user name for Core]
                    -password [password for Core] -protectedserver [name | IP
address] -volumes
                    [volume names | all] -destinationcontainer [Azure destination
container]
                    -deploymentname [name of deployment] -subscriptionid [Azure
subscription ID]
                    -cloudservicename [cloud service name] -vmname [virtual machine
name] -vmsize
                    [virtual machine size] -endpointname [rdp | ssh] -protocol [tcp
| udp]
                    -publicremoteaccessport [public port number] -
privateremoteaccessport [private
port number]
```

Command Options

The following table describes the options available for the `Start-AzureDeploy` command:

Table 162: Start-AzureDeploy command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points that you want to export.
-volumes	Optional. List of additional volume names for the deploy. If you use the value <code>all</code> or use no value, then all volumes deploy.
-destinationcontainer	The name of the Azure destination container you want to use for the deploy.
-deploymentname	The name of the deployment.
-subscriptionid	The Azure subscription ID.
-cloudservicename	The name of the Azure cloud service.
-vmname	The name of the virtual machine.

Option	Description
-vmsize	The size of the virtual machine; for example, A0, Basic_A4, or Standard_G1.
-endpointname	The Azure endpoint protocol used only for remote access <code>rdp</code> or <code>ssh</code> . The default value is <code>rdp</code> .
-protocol	The protocol used only for remote access <code>tcp</code> or <code>udp</code> . The default value is <code>tcp</code> .
-publicremoteaccessport	The public port for using remote access. The default value is 3389.
-privateremoteaccessport	The private port for using remote access. The default value is 3389.
-privateagentport	Optional. The Agent port. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
-publicagentport	Optional. The external Agent port. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
-privatetransferport	Optional. The TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.
-publictransferport	Optional. The external TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. Note: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.

Examples:

Deploy data to Azure:

```
>Start-AzureDeploy -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1
-subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname
VirtualMachine -vmsize A0
```

Deploy data to Azure using a specified endpoint:

```
>Start-AzureDeploy -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1
-subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname
VirtualMachine -vmsize A0 -endpointname ssh -protocol udp -publicremoteaccessport
1555 -privateremoteaccessport 22
```

Deploy data to Azure with specified Agent and transfer endpoint when the `-privateagentport` option has a user-defined value of 8006. The parameter for `-publicagentport` uses the special value 0, which is copied from `-privateagentport`. The parameter for `-privatetransferport` uses the special value 0, which is taken from

the Agent configuration. The parameter for `-publictransferport` uses the special value 0, which is copied from `-privatetransferport`:

```
>Start-AzureDeploy -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1
-subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname
VirtualMachine -vmsize A0 -privateagentport 8006 -publicagentport 0 -
privatetransferport 0 -publictransferport 0
```

Deploy data to Azure using all available disks:

```
>Start-AzureDeploy -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -deploymentname Deploy1 -destinationcontainer container1
-subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname
VirtualMachine -vmsize A0 -privateagentport 8006 -publicagentport 0 -
privatetransferport 0 -publictransferport 0 -Volumes all
```

Start-AzureExport

You can use the `Start-AzureExport` command to force the export of data from a protected machine to a Microsoft Azure virtual server.

Usage

The usage for the command is as follows:

```
Start-AzureExport -core [host name] -user [user name for Core] -password
[password for Core] -protectedserver [name | IP address] -volumes [volume
names | all] -rpn [number | numbers] -time [time string] -cloudaccountid
[Azure account ID] -storageaccountname[ storage account name] -containername
[container name] -foldername [folder name] -deploymentname [deployment name] -
destinationcontainer [Azure destination container] -subscriptionid [Azure
subscription ID] -cloudservicename [cloud service name] -vmname [virtual
machine name] -vmsize [virtual machine size] -endpointname [rdp | ssh] -
protocol [tcp | udp] -publicremoteaccessport [public remote access port number]
-privateremoteaccessport [private port number]
```

Command Options

The following table describes the options available for the `Start-AzureExport` command:

Table 163: Start-AzureExport command options

Option	Description
<code>-?</code>	Display this help message.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the

Option	Description
	local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Protected machine with recovery points that you want to export.
-volumes	Optional. List of additional volume names for the deploy. If you use the value <code>all</code> or use no value, the all volumes deploy.
-rpn	Optional. The sequential number of a recovery point that you want to export (use the <code>/list rps</code> command to get the numbers). If neither <code>-time</code> nor <code>-rpn</code> is specified, then the most recent recovery point is exported.
-time	Optional. This option determines the recovery points to select for export. Specify the exact time in the format <code>mm/dd/yyyy hh:mm tt</code> ; for example, <code>2/24/2012 09:00 AM</code> . Keep in mind to specify the date time value of the time zone set on your PC. If neither <code>-time</code> nor <code>-rpn</code> is specified, then the most recent recovery point is exported.
-cloudaccountid	Optional, if the <code>-storageaccountname</code> is specified. Specify the Azure cloud account ID.
-storageaccountname	Optional, if the <code>-cloudaccountname</code> is specified. Specify the Azure storage account name.
-containername	The name of the Azure container.
-foldername	Optional. The name of the Azure folder.
-deploymentname	Use this option to specify the name of the deployment. It is required for a deploy after export only.
-destinationcontainer	The name of the Azure destination container you want to use for the deploy.
-subscriptionid	The Azure subscription ID. It is required for a deploy after export only.
-cloudservicename	The name of the Azure cloud service. It is required for a deploy after export only.
-vmname	The name of the virtual machine. It is required for a deploy after export only.
-vmsize	The size of the virtual machine; for example, <code>A0</code> , <code>Basic_A4</code> , or <code>Standard_G1</code> .
-endpointname	The Azure endpoint protocol used only for remote access <code>rdp</code> or <code>ssh</code> . The default value is <code>rdp</code> . It is required for a deploy after export only.
-protocol	The protocol used only for remote access <code>tcp</code> or <code>udp</code> . It is required for a deploy after export only. The default value is <code>tcp</code> .
-publicremoteaccessport	The public port for using remote access. The default value is 3389.
-privateremoteaccessport	The private port for using remote access. The default value is 3389.
-privateagentport	Optional. The Agent port. If the port value is 0, then the value is determined by the Agent configuration.

Option	Description
	i NOTE: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-publicagentport</code>	Optional. The external Agent port. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publicagentport</code> nor <code>-privateagentport</code> is specified, then no endpoint is added.
<code>-privatetransferport</code>	Optional. The TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.
<code>-publictransferport</code>	Optional. The external TCP port upon which to accept connections from the Core for the transfer of data from the Agent. If the port value is 0, then the value is determined by the Agent configuration. i NOTE: If neither the parameter <code>-publictransferport</code> nor <code>-privatetransferport</code> is specified, then no endpoint is added.
<code>-hypervgenerationtype</code>	Specifies virtual machine generation. Azure supports two generations of Hyper-V virtual machines: 1 and 2.

Examples:

Export data to Azure:

```
>Start-AzureExport -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -cloudaccountid "Cloud Account 1" -containername
"mycontainer" -foldername "folder" -deploymentname Deploy1 -destinationcontainer
container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename
Service1 -vmname VirtualMachine -vmsize A0
```

Export data to Azure using a specified endpoint:

```
>Start-AzureExport -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -cloudaccountid "Cloud Account 1" -containername
"mycontainer" -foldername "folder" -deploymentname Deploy1 -destinationcontainer
container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename
Service1 -vmname VirtualMachine -vmsize A0 -endpointname ssh -protocol udp -
publicremoteaccessport 1555 -privateremoteaccessport 22
```

Export data to Azure with a specified Agent endpoint when the `-privateagentport` option uses the special value 0, which is taken from the Agent configuration. The `-publicagentport` option has the user-defined value of 1888:

```
>Start-AzureExport -core 10.10.10.10 -user administrator -password 23WE@#sdd -
protectedserver 10.10.5.22 -cloudaccountid "Cloud Account 1" -containername
"mycontainer" -deploymentname Deploy1 -destinationcontainer container1 -
```

```
subscriptionid "111111-22222-33333-4444-555555" -cloudservicename Service1 -vmname  
VirtualMachine -vmsize A0 -privateagentport 0 -publicagentport 1888
```

Export data to Azure with specified Agent and transfer endpoints. The `-privateagentport` option has the user-defined value of 8006. The parameter for `-publicagentport` uses the special value of 0, which is copied from the `-privateagentport` option. The parameter for `-privatetransferport` uses the special value of 0, which is taken from the Agent configuration. The parameter for `-publictransferport` uses the special value 0, which is copied from the `-privatetransferport` option.:

```
>Start-AzureExport -core 10.10.10.10 -user administrator -password 23WE@#$sdd -  
protectedserver 10.10.5.22 -cloudaccountid "Cloud Account 1" -containername  
"mycontainer" -foldername "folder" -deploymentname Deploy1 -destinationcontainer  
container1 -subscriptionid "111111-22222-33333-4444-555555" -cloudservicename  
Service1 -vmname VirtualMachine -vmsize A0 -privateagentport 8006 -publicagentport 0  
-privatetransferport 0 -publictransferport 0
```

Start-ChecksumCheck

The `Start-ChecksumCheck` PowerShell command lets you force a checksum check of Exchange Server recovery points.

Usage

The usage for the command is as follows:

```
Start-ChecksumCheck -core [host name] -user [login] -password [password] -  
protectedserver [name | IP address] -rpn [number | numbers] | -time [time string]
```

Command Options

The following table describes the options available for the `Start-ChecksumCheck` command:

Table 164: Start-ChecksumCheck command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	The name of the protected machine.
-rpn	Optional. Only for chain deletion (base image with chain of incrementals or orphaned

Option	Description
	points). The sequential number of a recovery point to check (use the Get-RecoveryPoints command to obtain the numbers). You can specify several space-separated numbers to delete multiple recovery points with a single command.
-time	Optional. Select the recovery point to check by its creation time, instead of its sequential number. Specify the exact time in the format "mm/dd/yyyy hh:mm tt" (for example, "2/24/2012 09:00 AM"). Keep in mind to specify date and time values of the time zone set on your computer.

Example:

Start a checksum check on two recovery points.:

```
> Start-ChecksumCheck -core 10.10.10.10 -user administrator -password 23WE@#sdd -protectedserver 10.10.5.22 -rpn 5 7
```

Start-ConsumeSeedDrive

Use `Start-ConsumeSeedDrive` for the initial data transfer when you establish Rapid Recovery replication.

Usage

The usage for the command is as follows:

```
Start-ConsumeSeedDrive -path [local | network path] -seeddriveusername [user name] -seeddrivepassword [password] -remotecore [name] -protectedserver [name] | -all
```

Command Options

The following table describes the options available for the `Start-ConsumeSeedDrive` command:

Table 165: Start-ConsumeSeedDrive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-path	The local or network path of the seed drive.
-seeddriveusername	Optional. The user name for the network location of the seed drive.
-seeddrivepassword	Optional. The password for the network location of the seed drive.
-remotecore	Use only with the -consume option. It is the name of the remote Core from which the seed drive recovery points are created or consumed.
-protectedserver	The name or IP address of the protected machine you are using to create or consume the seed drive of recovery points. For example: -protectedserver "10.10.60.48" "10.10.12.101."
-all	This option specifies whether to consume or copy all of the available protected machines.

Examples:

Starting consuming a seed drive located on a network share:

```
>Start-ConsumeSeedDrive -path \\10.10.1.1\Share\Seed\ -seeddriveusername Adminsitrator -seeddrivepassword 12345 -remotecore RemoteCoreName -all
```

Start consuming the data from two protected machines from a seed drive located on the local system:

```
>Start-ConsumeSeedDrive -path C:\Seed\ -remotecore TargetCoreHostName -protectedserver "10.10.1.1","10.10.1.2"
```

Start-CopySeedDrive

You can use a seed drive for the initial data transfer when you establish Rapid Recovery replication.

Usage

The usage for the command is as follows:

```
Start-CopySeedDrive -path [local | network path] -seeddriveusername [user name] -seeddrivepassword [password] [-targetcore [name or IP] | -protectedserver [name] | -all] -usecompatibleformat
```

Command Options

The following table describes the options available for the `Start-CopySeedDrive` command:

Table 166: Start-CopySeedDrive command options

Option	Description
-?	Display this help message.

Option	Description
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-path	The local or network path of the seed drive.
-seeddriveusername	Optional. The user name for the network location of the seed drive.
-seeddrivepassword	Optional. The password for the network location of the seed drive.
-targetcore	Optional. Use only with the -copy option. It is the name or IP address of the remote Core. All protected machines replicating to this Core receive seed drive recovery points.
-protectedserver	The name or IP address of the protected machine you are using to create or consume the seed drive of recovery points. For example: -protectedserver "10.10.60.48" "10.10.12.101."
-all	This option specifies whether to consume or copy all of the available protected machines.
-usecompatibleformat	The new archiving format offers improved performance, however it is not compatible with older Cores. Use this option when working with a legacy AppAssure Core. Confirm with dev.

Examples:

Start copying data from protected machines to a seed drive located on the local system:

```
>Start-CopySeedDrive -path C:\Seed\ -usecompatibleformat -targetcore
TargetCoreHostName
```

Start copying two protected machines to the seed drive on the network share:

```
>Start-CopySeedDrive -path \\10.10.1.1\Share\Seed\ -seeddriveusername Administrator
-seeddrivepassword 12345 -usecompatibleformat -protectedserver
"10.10.60.48","10.10.12.101"
```

Start-EsxiExport

The `Start-EsxiExport` PowerShell command initiates the launch of a virtual export from the selected Rapid Recovery recovery point to an ESX(i) server virtual machine.

Required parameters include the name of the protected machine containing recovery points to export; the name of the virtual machine you are exporting to; the amount of RAM to be allocated on the virtual machine; the host name and port of the Linux server host, and the path to the local, network, or Linux folder where the resulting virtual machine files will be stored.

Usage

The usage for the command is as follows:

```
Start-EsxiExport -core [host name] -user [user name] -password [password] -
protectedserver [machine name | IP address] -volumes [volume names] -rpn [number |
numbers] | -time [time string] -vmname [virtual machine name] -hostname [virtual
host name] -hostport [virtual host port number] -hostusername [virtual host user
name] hostpassword [virtual host password] [-ram [total megabytes] | -usesourceram]
-diskprovisioning [thin | thick] -diskmapping [automatic | manual | withvm]
```

Command Options

The following table describes the options available for the `Start-EsxiExport` command:

Table 167: Start-EsxiExport command options

Option	Description
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Protected machine with recovery points to be exported.
-volumes	Optional. List of volume names to be exported. If not specified, all volumes in the specified recovery points will be exported. Values must be enclosed in double quotes, each separated by a space. do not use trailing slashes in volume names. For example, specify "C:" not "C:/"
-rpn	Optional. The sequential number of a recovery point to be exported. (You can use the <code>Get-RecoveryPoints</code> command to obtain recovery point numbers. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-time	Optional. Determines recovery point to be selected for export. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-vmname	Windows name of the virtual machine.
-hostname	The virtual server host name.
-hostport	The virtual server port number.
-hostusername	The user name to the virtual server host.
-hostpassword	The password to the virtual server host.
-ram	Allocate specific amount of RAM on the virtual server.

Option	Description
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server as the source protected machine.
-diskprovisioning	Optional. The amount of disk space that will be allocated on the virtual machine. Specify 'thick' to make the virtual disk as large as the original drive on the protected server, or 'thin' to allocate the amount of actual disk space occupied on the original drive, plus some extra space in megabytes. By default, 'thin' provisioning is selected.
-diskmapping	Optional. Select either 'auto,' 'manual,' or 'withvm'. By default, auto-mapping is enabled.
-resetup	Optional. Recreates virtual machine if it is already presented at the specified location.
-datacenter	Optional. Specifies which datacenter to use.
-resourcepool	Optional. Specifies which resource pool to use.
-datastore	Optional. Specifies which datastore to use.
-computeresource	Optional. Specifies which compute resource to use.
-version	Optional. Specifies which version of ESXi to use.

Start-HypervExport

The `Start-HypervExport` PowerShell command initiates the launch of a virtual export from the selected Rapid Recovery recovery point to a Hyper-V server virtual machine.

Usage

The usage for the command is as follows:

```
Start-HypervExport -core [host name] -user [user name] -password [password] -
protectedserver [[machine name] or [IP address]] -volumes [volume names] -rpn
[number | numbers] | -time [time string] [-vmname [uselocalmachine] | -hostname
[virtual host name] -hostport [virtual host port number] -hostusername [virtual host
user name] -hostpassword [virtual host password] -vmlocation [location]] [-ram
[total megabytes] | -usesourceram] -diskformat [VHD | VHDX] -exportvmconfigfiles
```

Command Options

The following table describes the options available for the `Start-HypervExport` command:

Table 168: Start-HypervExport command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.

Option	Description
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Protected machine with recovery points to be exported.
-volumes	Optional. List of volume names to be exported. If not specified, all volumes in the specified recovery points will be exported. Values must be enclosed in double quotes, each separated by a space. do not use trailing slashes in volume names. For example, specify "C:" not "C:/"
-rpn	Optional. The sequential number of a recovery point to be exported. (You can use the <code>Get-RecoveryPoints</code> command to obtain recovery point numbers. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-time	Optional. Determines recovery point to be selected for export. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-vmname	Windows name of the virtual machine.
-gen2	Optional. Specify to use the second VM generation. If not specified, generation 1 is used. Rapid Recovery supports generation 2 from Windows Server 2012 R2 through Windows 8.1.
-usevhdx	Optional. If you specify this option, Rapid Recovery uses the VHDX disk format to create the VM. If you do not, it uses the VHD disk format. Generation 2 uses only the VHDX format.
-uselocalmachine	Optional. Connect the local Hyper-V server. If this parameter is used, the following options are ignored: hostname, host port, host username, host password.
-hostname	The virtual server host name.
-hostport	The virtual server port number.
-hostusername	The user name to the virtual server host.
-hostpassword	The password to the virtual server host.
-vmlocation	Local or network path to the folder where you want to store the virtual machine files.
-ram	Allocate specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server as the source protected machine.
-exportvmconfigfiles	Optional. Specify whether to export virtual machine configuration files. This option is available only both when the source is a virtual protected agentlessly and when the target hypervisor is the same as the source hypervisor.

Example:

Create a Hyper-V machine file to be stored on a remote machine:

```
>Start-HypervExport -core 10.10.10.10 -user administrator -password 23WE@#$sdd -protectedserver 10.10.5.22 -vmlocation \\WIN7-Bobby\virtualmachines -hostname 10.10.10.23 -hostport 443 -hostusername root -hostpassword 12QWsdxc@# -ram 4096
```

Start-LogTruncation

The `Start-LogTruncation` command forces log truncation for the specified protected SQL Server or Microsoft Exchange server.

Usage

The usage for the command is as follows:

```
Start-LogTruncation -core [host name] -user [user name] -password [password] -protectedserver [[machine name] or [IP address]] -target [sql | exchange]
```

Command Options

The following table describes the options available for the `Start-LogTruncation` command:

Table 169: Start-LogTruncation command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Archive of recovery points for the specified machine.
-target	Specify the type of log truncation (either 'sql' or 'exchange'). If not specified, logs are truncated on all databases.

Example:

Truncate SQL logs:

```
>Start-LogTruncation -protectedserver SQL1 -target sql
```

Truncate Exchange server logs: all recovery points for all machines on the Core:

```
> start-LogTruncation -protectedserver ExServer2 -target exchange
```

Start-MountabilityCheck

The `Start-MountabilityCheck` command forces a mountability check for protected Microsoft Exchange mail stores.

Usage

The usage for the command is as follows:

```
Start-MountabilityCheck -core [host name] -user [user name] -password [password] -  
protectedserver [[machine name] or [IP address]] -rpn [number | numbers] | -time  
[time string]
```

Command Options

The following table describes the options available for the `Start-MountabilityCheck` command:

Table 170: Start-MountabilityCheck command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Archive of recovery points for the specified machine.
-rpn	Optional. The sequential number of a recovery point to be exported. (You can use the <code>GetRecoveryPoints</code> command to obtain recovery point numbers. Note: If neither 'time' nor 'rpn' option is specified in this command, then the most recent recovery point will be exported.
-time	Optional. Determines recovery point to be selected for export. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, then the most recent recovery point will be exported.

Example:

Start a mountability check for oall recovery points for all machines on the Core:

```
> Start-MountabilityCheck -protected EX01
```

Start-OptimizationJob

The `Start-OptimizationJob` command lets you perform optimize a repository on demand.

Usage

The usage for the command is as follows:

```
Start-OptimizationJob -core [host name] -user [user name] -password [password] -  
repository [repository name] | -all
```

Command Options

The following table describes the options available for the `Start-OptimizationJob` command:

Table 171: Start-OptimizationJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	The name of the repository that you want to optimize.
-all	Use this option to perform the optimization job on all repositories for this Core.

Example:

Start a repository optimization job:

```
>Start-OptimizationJob -repository "Repository 1" -core 10.10.10.10 -user  
administrator -password 23WE@#sdd
```

Start-OracleDBVerifyJob

Use the command `Start-OracleDBVerifyJob` to start the DBVerify job for one or more specified recovery points on a protected server.

Usage

The usage for the command is as follows:

```
Start-OracleDBVerifyJob -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -recoverypointnumber [number | numbers]
```

Command Options

The following table describes the options available for the `Start-OracleDBVerifyJob` command:

Table 172: Start-OracleDBVerifyJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable the Oracle DBVerify nightly job.
-recoverypointnumber	The sequential number of a recovery point that you want to export (use the <code>/list rps</code> command to get the numbers). To start the job on multiple recovery points with one command, separate each recovery point number with a space.

Example:

Start the Oracle DBVerify job for the recovery points on the specified protected server:

```
>Start-OracleDBVerifyJob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -recoverypointnumber 1 2
```

Start-OracleLogTruncationJob

The command `Start-OracleLogTruncationJob` lets you start a log truncation job for a specified Oracle instance on a protected server.

Usage

The usage for the command is as follows:

```
Start-OracleLogTruncationJob -core [host name] -user [user name] -password [password] -protectedserver [name | IP address] -instancename [instance SID] -deletionpolicy [automatic | keepnewest | keepspecificnumber] -retentionduration [duration value] -retentionunit [day | week | month | year] -numberoffiles [number of archive files to create]
```

Command Options

The following table describes the options available for the `Start-OracleLogTruncationJob` command:

Table 173: Start-OracleLogTruncationJob command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	Use this option to specify the protected machine for which you want to enable Oracle log truncation as a nightly job.
-instancename	The name of the Oracle instance for which you want to start log truncation.
-deletionpolicy	Optional. This option must be represented by one of the following values: <ul style="list-style-type: none">• "automatic"• "keepnewest"• "keepspecificnumber"
-retentionduration	Optional. This value determines the length of time to keep a log before truncating and is constrained to positive integer values. If using the "keepnewest" value of the <code>-deletionpolicy</code> option, a retention duration value is required.
-retentionunit	Optional. This option identifies the time unit for the <code>-retentionduration</code> option. It must be represented by one of the following values: <ul style="list-style-type: none">• "day"• "week"• "month"• "year"
-numberoffiles	Optional. This option sets the number of recent archive log files to keep. If using the "keepspecificnumber" value of the <code>-deletionpolicy</code> option, a number of files value is required.

Examples:

Start the Oracle log truncation job for the ORCL instance on a specified protected server:

```
>Start-OracleLogTruncationJob -core 10.10.127.42 -user admin -password 676df#df -protectedserver 10.10.34.88 -instancename ORCL
```

Start the Oracle log truncation job for the ORCL instance on a specified protected server and configure the deletion policy as "keepnewest" with the logs kept for 10 days:

```
>Start-OracleLogTruncationJob -protectedserver 10.10.34.88 -instancename ORCL -  
deletionpolicy keepnewest -retentionduration 10 -retentionunit day
```

Start-Protect

The `Start-Protect` command lets an administrator add a server under protection by a Core.

Usage

```
Start-Protect -core [host name] -user [user name] -password [password] -repository  
[repository name] -agent [name | IP address] -agentusername [user name] -  
agentpassword [password] -agentport [port] -volumes [volume names]
```

Command Options

The following table describes the options available for the `Start-Protect` command:

Table 174: Start-Protect command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-repository	Name of a repository on the Core where the protected machine's data is stored.
-agentname	Protected machine name or IP address.
-agentusername	Log on to the server to be protected.
-agentpassword	Password to the server to be protected.
-agentport	Protected server port number.
-volumes	List of volumes to protect. Values must be enclosed in double quotes and separated by a space. Do not use trailing slashes in volume names. For example, "c:" or "d:".

Example:

Put volumes of a server under protection:

```
>Start-Protect -repository "Repository 1" -agentname 10.10.9.120 -agentusername administrator -agentpassword 12345 -agentport 5002 -volumes "c:" "d:"
```

Start-ProtectCluster

The `Start-ProtectCluster` command lets an administrator add a server cluster under protection by a Core.

Usage

Usage for the command is as follows:

```
Start-ProtectCluster -core [host name] -user [user name] -password [password] -repository [repository name] -clustername [name | IP address] -clusterusername [user name for cluster] -clusterpassword [password for cluster] -clusterport [port] -clustervolumes [volume names] -clusternodes [cluster nodes names and volumes]
```

Command Options

The following table describes the options available for the `Start-ProtectCluster` command:

Table 175: Start-ProtectCluster command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-repository	Name of a repository on the Core where the protected machine's data is stored. The name must be enclosed in double quotes.
-clustername	The name of the cluster to protect.
-clusterusername	User name for the cluster to be protected.
-clusterpassword	Password to the cluster to be protected.
-clusterport	Port number for the cluster to be protected.
-clustervolumes	List of volumes to protect. Values must be in double quotes and separated by a space. Do not use trailing slashes in volume names. For example, "c:", "d".
-clusternodes	List of cluster nodes with volumes to protect. First specify label "nodename" and then type the name of the node. Then, specify label "volumes" and then type a list of volumes for the node. For example: "nodename", "10.10.10.10", "volumes", "c:", "e:", "nodename", "10.10.10.11", "volumes", "c:"

Example:

Put volumes of a server under protection:

```
>Start-ProtectCluster -repository "Repository 1" -clustername 10.10.9.120 -  
clusterusername administrator -clusterpassword 12345 -clusterport 5002 -  
clustervolumes "c:" "d:" -clusternodes nodename 10.10.10.10 volumes "c:" "e:"
```

Start-ProtectEsxServer

You can use the `Start-ProtectEsxServer` command whenever you want to add a VMware ESX(i) virtual machine to protection.

Usage

The usage for the command is as follows:

```
Start-ProtectEsxServer -core [host name] -user [user name] -password [password] -  
repository [repository name] -server [name | IP address] -serverusername [user name]  
-serverpassword [password for server login] -serverport [port] -virtualMachines  
[virtual machines collection | all] -autoProtect [object ID or name collection]
```

Command Options

The following table describes the options available for the `Start-ProtectEsxServer` command:

Table 176: Start-ProtectEsxServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. The user name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. The password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Required. The name of the repository that is associated with the Core that you want to use to protect the virtual machine. Note: You must enclose the name in double quotes.
-server	The name or IP address for the vCenter or ESXi server you want to protect.
-serverusername	The user name for logging in to the vCenter or ESXi server that you want to protect.
-serverpassword	The password for logging in to the vCenter or ESXi server that you want to protect.

Option	Description
-serverport	Optional. The port number for the vCenter or ESXi server that you want to protect.
-virtualmachines	Optional. This option lets you list the virtual machines that you want to protect.
-autoprotect	Optional. This option lets you list new virtual machines that you want to automatically protect.

Example:

Protect specific virtual machines from a vCenter or ESXi server with the Core:

```
>Start-ProtectEsxServer -core 10.10.10.10 -user admin -password password -repository
"Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root -
serverpassword password -virtualmachines "VM1" "VM2" -autoprotect "Folder1"
```

Start-ProtectHyperVCluster

The `Start-ProtectHyperVCluster` command adds a Hyper-V cluster under protection by a Core using agentless protection.

Usage

The usage for the command is as follows:

```
Start-ProtectHyperVCluster -core [host name] -user [user name] -password [password]
-repository [name] -server [name | IP address] -serverusername [user name] -
serverpassword [password] -serverport [port] -virtualmachines [virtual machines
collection | all] -isagentprotection
```

Command Options

The following table describes the options available for the `Start-ProtectHyperVCluster` command:

Table 177: Start-ProtectHyperVCluster command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.

Option	Description
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-server	Name or IP address of the Hyper-V server that you want to protect.
-serverusername	User name for the Hyper-V server to be protected.
-serverpassword	Password for the Hyper-V server to be protected.
-serverport	Optional. Protected Hyper-V server port number.
-virtualmachines	Optional. List of virtual machines to protect. Values must be enclosed in double quotes and separated by a space. If you exclude this parameter, only the Hyper-V cluster container is protected.
-isagentprotection	Optional. Use this option to protect a cluster with an Agent in each guest virtual machine, which is false by default.
-autoprotect	Optional. This option enables the autoprotect feature for the Hyper-V server. It is not compatible with the -isagentprotection option.

Example:

Protect specific virtual machines of a Hyper-V cluster:

```
>Start-ProtectHyperVCluster -core 10.10.10.10 -username admin -password password -
repository "Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root
clusterpassword password -virtualmachines "VM1" "VM2" -autoprotect
```

Start-ProtectHyperVServer

The `Start-ProtectHyperVServer` command adds a Hyper-V server under protection by a Core using agentless protection.

Usage

The usage for the command is as follows:

```
Start-ProtectHyperVServer -core [host name] -user [user name] -password [password] -
repository [name] -server [name | IP address] -serverusername [user name] -
serverpassword [password] -serverport [port] -virtualmachines [virtual machines
collection | all] -isagentprotection
```

Command Options

The following table describes the options available for the `Start-ProtectHyperVServer` command:

Table 178: Start-ProtectHyperVServer command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-repository	Name of a repository on the Core to which the protected machine data should be stored. The name must be enclosed in double quotes.
-server	Name or IP address of the Hyper-V server that you want to protect.
-serverusername	User name for the Hyper-V server to be protected.
-serverpassword	Password for the Hyper-V server to be protected.
-serverport	Optional. Protected Hyper-V server port number.
-virtualmachines	Optional. List of virtual machines to protect. Values must be enclosed in double quotes and separated by a space. If you exclude this parameter, only the Hyper-V cluster container is protected.

Example:

Protect specific virtual machines of a Hyper-V server:

```
>Start-ProtectHyperVServer -core 10.10.10.10 -username admin -password password -  
repository "Repository 1" -server 10.10.8.150 -serverport 443 -serverusername root  
clusterpassword password -virtualmachines "VM1" "VM2"
```

Start-RepositoryCheck

The `Start-RepositoryCheck` PowerShell command lets you check the integrity of a repository.

Usage

The usage for the command is as follows:

```
Start-RepositoryCheck -name [repository name] | -all [check all repositories] -  
password [password] -force
```

Command Options

The following table describes the options available for the `Start-RepositoryCheck` command:

Table 179: Start-RepositoryCheck command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-repository	Required. The name of the repository that you want to check.
-all	Optional. Check all repositories associated with this Core.
-force	Optional. Perform the repository check without confirmation.

Example:

Start checking a repository:

```
>Start-RepositoryCheck -repository newRepository1 -core 10.10.10.10:8006 -user administrator -password 23WE@#sdd
```

Start-RestoreAgent

The `Start-RestoreAgent` command lets you restore a protected machine or volume from a specific Rapid Recovery recovery point.

Usage

The usage for the command is as follows:

```
Start-RestoreAgent -protectedserver [name | IP address] -rpn [recovery point number] -volumes [IDs | names | all] -targetmachine [name] -targetvolume [volume name] -forcedismount -autorestart
```

Command Options

The following table describes the options available for the `Start-RestoreAgent` command:

Table 180: Start-RestoreAgent command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-protectedserver	The name or IP address of the server you want to restore.
-rpn	The identification number of the recovery point you want to use to restore the machine. To find the correct number, use the command <code>/list rps</code> .
-volumes	The IDs or names of the volumes you want to restore. To restore all protected volumes, use <code>-volumes all</code> .
-targetmachine	The name of the machine to which you want to restore the protected machine.
-targetvolume	The name or ID of the volume to which you want to restore the machine.
-forcedismount	Optional. Use this option to force the dismount of the database on demand.
-autorestart	Optional. Use this command if restarting an Exchange Server machine is necessary.

Example:

Restore a machine to a protected machine with the IP address 192.168.20.130, including the force database dismount option:

```
>Start-RestoreAgent -protectedserver 192.168.20.130 -rpn 259 -volumes "F:" "E:" "C:"
-targetmachine 192.168.20.174 -targetvolume "E:" "G:" "F:" -forcedismount
```

Start-RestoreArchive

Businesses often use long-term storage to archive both compliant and non-compliant data. The archive feature in Rapid Recovery is used to support the extended retention for compliant and non-compliant data. The administrator can save an archive on the local storage or network location by specifying the `-Path` command and credentials.

Usage

The usage for the command is as follows:

```
Start-RestoreArchive -core [host name] -user [login] -password [password] -all | -
protectedserver [name | IP address | "[name1 | IP address1]" "[name2 | IP
address2]"] -repository [name] -archiveusername [name] -archivepassword [password] -
path [location] -cloudaccountname [name] -cloudcontainer [name]
```

Command Options

The following table describes the options available for the `Start-RestoreArchive` command:

Table 181: Start-RestoreArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Archive recovery points for all protected machines.
-protectedserver	The protected machine with recovery points that you want to archive. You can specify multiple machine names enclosed in double quotes and separated by commas.
-repository	The name of the repository where you want to place restored recovery points. You must enclose the name in double quotes; for example, "Repository1."
-archiveusername	Optional. The user name for logging in to the remote machine. It is required for a network path only.
-archivepassword	Optional. The password for logging in to the remote machine. It is required for a network path only.
-path	The path to where to save the archived data. For example: <ul style="list-style-type: none">Local machine: "d:\work\archive"Network path: "\\servername\sharename"Folder in a cloud account: "Folder Name" Note: The number of symbols should not be greater than 100 for local and network locations, and should not be greater than 150 for a cloud location.
-cloudaccountname	Optional. Use only for cloud archiving. The name of the cloud account where you want to save the archive.
-cloudcontainer	Optional. Use only for cloud archiving. The name of the cloud container in the chosen cloud account, where the archive will be saved. When you use this option, you should also specify the "-cloudaccountname" parameter.
-manifestcore	Optional. Specify the Core that you want to use from the manifest of the restored archive.

Example:

Archive all recovery points for all machines on the Core and store them on the local machine:

```
>Start-RestoreArchive -path D:\work\archive -startdate 'Example 04/30/2012' -all
```

Start-ScheduledArchive

The `Start-ScheduledArchive` PowerShell command lets you force a Rapid Recovery scheduled archive to begin on demand, regardless of the pre-established schedule.

Usage

The usage for the command is as follows:

```
Start-ScheduledArchive -core [host name] -user [login] -password [password] -all -  
ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `Start-ScheduledArchive` command:

Table 182: Start-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Force all scheduled archives.
-id	The identification number or space-separated identifiers of the scheduled archives that you want to force.

Example:

Start multiple scheduled archive jobs:

```
>Start-ScheduledArchive -ids 799138c8-3dfc-4398-9711-1823733c2a31, 26c29bb7-b320-  
47f5-b5a8-dffc49f50e25
```

Start-VBExport

The `start-VBExport` command initiates the launch of a virtual export from the selected recovery point to an Oracle VirtualBox server virtual machine.

Required parameters include the name of the protected machine containing recovery points to export; the name of the virtual machine you are exporting to; the amount of RAM to be allocated on the virtual machine; the host name and port of the Linux server host, and the path to the local, network, or Linux folder where the resulting virtual machine files will be stored.

Usage

The usage for the command is as follows:

```
Start-VBExport -core -user [user name] -password [password] -protectedserver  
[machine name] or [IP address]] -volumes [volume names] -rpn [number | numbers] |  
-time [time string] -vmname [virtual machine name] [-ram [total megabytes] | -  
usesourceram] -linuxhostname [linux hostname] -hostport [linux port] -targetpath  
[location] pathusername [user name] - pathpassword [password]
```

Command Options

The following table describes the options available for the `Start-VBExport` command:

Table 183: Start-VBExport command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Protected machine with recovery points to be exported.
-volumes	Optional. List of volume names to be exported. If not specified, all volumes in the specified recovery points will be exported. Values must be enclosed in double quotes, each separated by a space. do not use trailing slashes in volume names. For example, specify "C:" not "C:/"
-rpn	Optional. The sequential number of a recovery point to be exported. (You can use the <code>Get-RecoveryPoints</code> command to obtain recovery point numbers.) Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-time	Optional. Determines recovery point to be selected for export. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, than the most recent recovery point will be exported.
-vmname	Windows name of the virtual machine.
-ram	Allocate specific amount of RAM on the virtual server.

Option	Description
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server as the source protected machine.
-linuxhostname	Linux VirtualBox server hostname.
-hostport	Linux VirtualBox server port.
-targetpath	Local or network or Linux path to the folder where the virtual machine files are to be stored.
-pathusername	User name for network machine. Only required when you specify network path in parameter -targetpath.
-pathpassword	Password for network machine. Only required when you specify network path in parameter -targetpath.
-accountusername	Optional. Use if you can specify a user account to register the exported virtual machine. For local or network machine only.
-accountpassword	Optional. Use only when you specify a user account to register the exported virtual machine using parameter -accountusername. For local or network machine only.

Example:

Export all volumes from the latest recovery point on machine 10.10.12.97 to a VM called NewVirtualBoxVM:

```
>Start-VBExport -protectedserver 10.10.12.97 -vmname NewVirtualBoxVM -ram
usesourceram -targetpath D:/exports
```

Start-VirtualStandby

The `Start-VirtualStandby` PowerShell command lets you force a Rapid Recovery a data export to a virtual standby machine. This on-demand export can occur outside of the regularly scheduled virtual standby exports.

Usage

The usage for the command is as follows:

```
Start-VirtualStandby -core [host name] -user [login] -password [password] -all | -
protectedserver [name(s) | IP address]
```

Command Options

The following table describes the options available for the `Start-VirtualStandby` command:

**Table 184: Start-VirtualStandby
command options**

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Force an export for all virtual standby

Option	Description
	machines.
-protectedserver	The name or names—separated by a comma and space—of the protected machines that you want to force to export.

Example:

Force a virtual standby export for a protected machine:

```
>Start-VirtualStandby -core 10.10.10.10:8006 -user administrator -password
23WE@#$sdd -protectedserver 10.10.5.22
```

Start-VMExport

The `Start-VMExport` command initiates the launch of a virtual export from the selected recovery point to a VMware Workstation server virtual machine.

Required parameters include the name of the protected machine containing recovery points to export; the name of the virtual machine you are exporting to; the amount of RAM to be allocated on the virtual machine; and the path to the local or network folder where the resulting virtual machine files will be stored.

Usage

The usage for the command is as follows:

```
Start-VMExport -core -user [user name] -password [password] -protectedserver
[machine name] or [IP address]] -volumes [volume names] -rpn [number | numbers] |
-time [time string] -vmname [virtual machine name] [-ram [total megabytes] | -
usesourceram] -linuxhostname [linux hostname] -hostport [linux port] -targetpath
[location] pathusername [user name] - pathpassword [password]
```

Command Options

The following table describes the options available for the `Start-VMExport` command:

Table 185: Start-VMExport command options

Option	Description
-?	Display this help message.

Option	Description
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Protected machine with recovery points to be exported.
-volumes	Optional. List of volume names to be exported. If not specified, all volumes in the specified recovery points will be exported. Values must be enclosed in double quotes, each separated by a space. do not use trailing slashes in volume names. For example, specify "C:" not "C:/"
-rpn	Optional. The sequential number of a recovery point to be exported. (You can use the <code>Get-RecoveryPoints</code> command to obtain recovery point numbers. Note: If neither 'time' nor 'rpn' option is specified in this command, then the most recent recovery point will be exported.
-time	Optional. Determines recovery point to be selected for export. You need to specify exact time in the format "MM/DD/YYYY hh:mm tt" (for example: "04/24/2015 09:00 AM"). Specify date time values of the time zone set on your local machine. Note: If neither 'time' nor 'rpn' option is specified in this command, then the most recent recovery point will be exported.
-vmname	Windows name of the virtual machine.
-ram	Allocate specific amount of RAM on the virtual server.
-usesourceram	Optional. Allocate the same amount of RAM on the virtual server as the source protected machine.
-targetpath	Local or network or Linux path to the folder where the virtual machine files are to be stored.
-pathusername	User name for network machine. Only required when you specify network path in parameter -targetpath.
-pathpassword	Password for network machine. Only required when you specify network path in parameter -targetpath.
-version	Version of VMware Tools to use. Valid versions are: 7, 8, 9, and 10.

Example:

Export all volumes from the latest recovery point on machine 10.10.12.97 to a VM called NewVMwareVM:

```
>Start-VBExport -protectedserver 10.10.12.97 -vmname NewVMWareVM -ram usesourceram -targetpath D:/exports
```

Stop-ActiveJobs

The `Stop-ActiveJobs` cancels active jobs for a specified protected machine.

Usage

The usage for the command is as follows:

```
Stop-ActiveJobs [-protectedserver [machine name | IP address]] [-core [host name]] -  
user [user name] -password [password] -jobtype [jobtype]
```

Command Options

The following table describes the options available for the `Stop-ActiveJobs` command:

Table 186: Stop-ActiveJobs command options

Option	Description
-?	Display this help message.
-all	Select and cancel events of the specified type for all protected machines.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-protectedserver	Determines protected machine on which jobs should be canceled.
-jobtype	Optional. Specifies job type filter. Available values are: 'transfer' (data transfer), 'repository' (repository maintenance), 'replication' (local and remote replications), 'backup' (backup and restore), 'bootcdbuilder' (create boot CDs), 'diagnostics' (upload logs), 'exchange' (Exchange Server files check), 'export' (recovery point export), 'pushinstall' (deploy Agent software to protected machines), 'rollback' (restore data from recovery point), 'rollup' (recovery point rollup's), 'sqlattach' (agent attachability checks), 'mount' (not repository). By default, all jobs of the specified type are canceled.

Example:

Stop transfer job in protected machine:

```
>Stop-ActiveJobs -protectedserver 10.10.1.76 -jobtype transfer
```

Stop all jobs for a specific protected machine:

```
>Stop-ActiveJobs -protectedserver 10.10.1.76 -all
```

Stop-CoreService

Use this command to stop the Core service on a Core machine.

Usage

The usage for the command is as follows:

```
Stop-CoreService -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false] -wait [time in seconds]
```

Command Options

The following table describes the options available for the Stop-CoreService command:

Table 187: Stop-CoreService command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."
-wait	Optional. This option indicates that the command should wait until the Core service is fully stopped for the specified period of time in seconds before canceling active jobs.

Example:

Stop the Core service:

```
>Stop-CoreService -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true -wait 600
```

Suspend-Replication

The Suspend-Replication command lets an administrator pause replication.

A user can pause replication in three ways:

- Pause replication on the source Core for all protected machines (`-outgoing` parameter)
The administrator must specify the remote machine name with outgoing replication pairing to pause outgoing replication on the source Core.

```
>Suspend-replication -outgoing 10.10.12.10
```

- Pause replication on the source Core for a single protected machine (`-protectedserver` parameter)

```
>Suspend-replication -protectedserver 10.10.12.97
```

- Pause replication on the target Core (`-incoming` parameter)
If the local Core is a target Core, the administrator can pause replication by specifying the source Core using the `-incoming` parameter.

Command Options

The following table describes the options available for the `Suspend-Replication` command:

Table 188: Suspend-Replication command options

Option	Description
<code>-?</code>	Display this help message.
<code>-all</code>	Pauses all protected machines on the selected Core.
<code>-core</code>	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
<code>-pause</code>	[<code>snapshots</code>], [<code>replication</code>] or [<code>vmexport</code>].
<code>-password</code>	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
<code>-protectedserver</code>	Pause the current protected server.
<code>-user</code>	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
<code>-incoming</code>	Host name of the remote Core that replicates to the Core machine. Replication is suspended for all protected machines on the remote Core.
<code>-outgoing</code>	Host name of the remote target core to which data is replicating. Replication is suspended for all protected machines on the remote core.

Example:

Pause outgoing replication on the remote Core with the IP address: 10.10.1.15, for the single protected machine with the IP address: 10.10.1.76:

```
>Suspend-replication -core 10.10.1.15 -protectedserver 10.10.1.76
```

Pause outgoing replication from the local Core to remote target with the IP address: 10.10.1.63 for all protected machines:

```
>Suspend-replication -outgoing 10.10.1.63
```

Pause incoming replication from 10.10.1.82 on the remote Core with the IP address: 10.10.1.15 (Administrator is able to pause incoming replication only for whole machine):

```
>Suspend-replication -core 10.10.1.15 -incoming 10.10.1.82
```

Suspend-ScheduledArchive

The `Suspend-ScheduledArchive` PowerShell command lets you pause a Rapid Recovery scheduled archive. This command prevents the archive from occurring as scheduled until you reactivate it.

If the topic is relevant, include and re-link:

For more information, see `Resume-ScheduledArchive`.

.

Usage

The usage for the command is as follows:

```
Suspend-ScheduledArchive -core [host name] -user [login] -password [password] -all -ids [id | id1 id2]
```

Command Options

The following table describes the options available for the `Suspend-ScheduledArchive` command:

Table 189: Suspend-ScheduledArchive command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-all	Pauses all scheduled archives.
-id	The identification number or space-separated numbers of scheduled archives to suspend.

Example:

Suspend multiple scheduled archives:

```
>Suspend-ScheduledArchive -ids 799138c8-3dfc-4398-9711-1823733c2a31, 26c29bb7-b320-47f5-b5a8-dffc49f50e25
```

Suspend-Scheduler

This command lets you suspend or pause the task scheduler it has been paused.

Usage

The usage for the command is as follows:

```
Suspend-Scheduler -core [host name] -user [user name] -password [password] -cancelactivejobs [true | false]
```

Command Options

The following table describes the options available for the `Suspend-Scheduler` command:

Table 190: Suspend-Scheduler command options

Option	Description
-?	Display this help message.
-restore	[snapshots], [replication] or [vmexport].
-core	Optional. Remote Core host machine IP address (with an optional port number). By default, the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you must also provide a password. If none is provided, then the credentials for the logged-on user are used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none is provided, then the credentials for the logged-on user are used.
-cancelactivejobs	Optional. Use this option to cancel all active jobs on the Core. The default setting is "false."

Example:

Pause the task scheduler:

```
>Suspend-Scheduler -core 10.10.127.42 -user admin -password 676df#df -cancelactivejobs true
```

Suspend-Snapshot

The `Suspend-Snapshot` command lets an administrator pause snapshots.

Usage

The usage for the command is as follows:

```
Suspend-Snapshot -core [host name] -user [user name] -password [password] -all | -  
protectedserver [name | IP address] -time [time string]
```

Command Options

The following table describes the options available for the `Suspend-Snapshot` command:

Table 191: Suspend-Snapshot command options

Option	Description
-?	Display this help message.
-all	Pauses all protected machines on the selected Core.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-time	The time in the format 'Day-Hours-Minutes' when the snapshots will be resumed (only for snapshots pause).

Example:

Pause snapshots for the protected machine with IP 10.10.10.4 for the local Core with a certain time to resume:

```
>Suspend-Snapshot -protectedserver 10.10.10.4 -time 3-20-50
```

Suspend-VirtualStandby

The `Suspend-VirtualStandby` PowerShell command lets you pause the export of data to a Rapid Recovery virtual standby machine.

Usage

The usage for the command is as follows:

```
Suspend-VirtualStandby -core [host name] -user [login] -password [password] -all | -  
protectedserver [name(s) | IP address]
```

Command Options

The following table describes the options available for the `Suspend-VirtualStandby` command:

Table 192: Suspend-VirtualStandby command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a log on. If none are provided, then the logged-on user's credentials will be used.
-all	Pause exports for all virtual standby machines.
-protectedserver	The name or names—separated by a comma and space—of the protected machines with virtual standby machines that you want to suspend.

Example:

Suspend virtual standby exports for a protected machine:

```
>Suspend-VirtualStandby -core 10.10.10.10:8006 -user administrator -password  
23WE@#$sdd -protectedserver 10.10.5.22
```

Suspend-VMExport

The `Suspend-VMExport` command lets an administrator pause exports to virtual machines.

Usage

```
Suspend-VMExport -core [host name] -user [user name] -password [password] -all | -  
protectedserver [name | IP address]
```

Command Options

The following table describes the options available for the `Suspend-VMExport` command:

Table 193: Suspend-VMExport command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name,

Option	Description
	you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.
-all	Pauses all protected machines on the selected Core.
-protectedserver	Pause the current protected server.

Example:

Suspend VM export for the protected machine with IP 10.10.10.4 for the local Core:

```
>Suspend-VMExport -protectedserver 10.10.12.25
```

Update-Repository

The `Update-Repository` command adds an extent to an existing DVM repository. The size specified must be between 250MB and 16TB.

Usage

```
Update-Repository -name [repository name] -size [size] [[[-datapath [datapath] -
metadatapath [metadata path]] | [-uncpath [UNC path] -shareusername [share user
name] -sharepassword [share password]]] -core [host name] -user [user name] -
password [password]
```

Command Options

The following table describes the options available for the `Update-Repository` command:

Table 194: Update-Repository command options

Option	Description
-?	Display this help message.
-core	Optional. Remote Core host machine IP address (with an optional port number). By default the connection is made to the Core installed on the local machine.
-user	Optional. User name for the remote Core host machine. If you specify a user name, you also have to provide a password. If none are provided, then the logged-on user's credentials will be used.
-password	Optional. Password to the remote Core host machine. If you specify a password, you also have to provide a user name. If none are provided, then the logged-on user's credentials will be used.

Option	Description
-name	DVM repository name.
-size	Size of DVM repository extent. Available units are: b, Kb, MB, GB, TB, PB.
-datapath	For local location only. Determines data path of DVM repository extent.
-metadatapath	For local location only. Determines metadata path of DVM repository extent.
-uncpath	For share location only. Determines data and metadata paths of DVM repository extent.
-shareusername	For share location only. Determines login to share location.
-sharepassword	For share location only. Determines password to share location.

Example:

Add an extent to the DVM repository of the minimum size:

```
>Update-Repository -name Repository1 -size 250Mb -datapath C:\Repository\Data -
metadatapath C:\repository\Metadata
```

Localization

When running on the same machine on which Rapid Recovery Core is installed, the Rapid Recovery PowerShell module bases its display language on the language set for the Core. Localized Rapid Recovery versions such as this one support English, Chinese (Simplified), French, Korean, German, Japanese, Portuguese (Brazil), and Spanish.

For Non-English releases, use: Rapid Recovery Core release 6.1.1 is an English-only release. As a result, English is the only language supported for the PowerShell Module. AppAssure release 6.0.2 is the most recent localized version of the Core software. In that release, supported languages include English, Chinese (Simplified), French, Korean, German, Japanese, Portuguese (Brazil), and Spanish.

If the Rapid Recovery PowerShell module is installed on a separate machine, English is the only language supported.

Qualifiers

The following table describes the qualifiers available for Rapid Recovery PowerShell Module.

Table 195: Rapid Recovery PowerShell module qualifiers

Qualifier	Usage
-core <Rapid Recovery Core Name>	Host name of the Core. Default: localhost
-ProtectedServer <Protected Server Name>	Host name/IP address of the Rapid Recovery Agent.

Qualifier	Usage
	Default: Localhost if multiple servers protected, otherwise the single server protected.
-Mode <READ, READWRITE, WRITE>	Recovery Point Mount mode. Default: Read.
-Volumes <Snapshot Volume Letter>	Snapshot volume letter from Rapid Recovery Agent. Default: All.
-User <User Name>	User name used to connect to the Rapid Recovery Core. This is typically the service user.
-Domain <Domain Name>	Domain to which the user defined in /User belongs.
-Password <Password>	Password of the user defined in /User.
-Path <Target path to mount, dismount recovery points or archive location>	For example: C:\RapidRecoveryMount.

Scripting

Rapid Recovery enables administrators to automate the administration and management of resources at certain occurrences through the execution of commands and scripts. The Rapid Recovery software supports the use of PowerShell scripting for Windows and Bourne shell and Bash scripting for Linux.

Core jobs are automatically created whenever you initiate operations on the Rapid Recovery Core such as replication, virtual export, or a backup transfer. You can extend these jobs by running a script before it or after it. These are known as pre and post scripts.

This section describes the scripts that can be used by administrators at designated occurrences in Rapid Recovery for Windows and Linux.

Caution: The sample PowerShell and shell scripts provided in this document will function when run as designed by qualified administrators. Take precautions when modifying functioning scripts to retain working versions. Any modifications to the script samples included here, or any scripts you create, are considered customization, which is not typically covered by Quest Support.

Using PowerShell scripting with Rapid Recovery

Windows PowerShell is a Microsoft .NET Framework-connected environment designed for administrative automation. Rapid Recovery includes comprehensive client software development kits (SDKs) for PowerShell scripting that lets administrative users run user-provided PowerShell scripts at designated occurrences; for example, before or after a snapshot, attachability and mountability checks, and so on. Administrators can run scripts from both the Rapid Recovery Core and the protected machine. Scripts can accept parameters, and the output of a script is written to Core and protected machine log files.

Note: For nightly jobs, preserve one script file and the JobType input parameter to distinguish between nightly jobs. Script files are located in the %ALLUSERSPROFILE%\AppRecovery\Scripts folder.

- In Windows 7, the path to locate the %ALLUSERSPROFILE% folder is: C:\ProgramData.
- In Windows 2003, the path to locate the folder is: Documents and Settings\All Users\Application Data.
Note: Windows PowerShell is required and must be installed and configured before running Rapid Recovery scripts.

For more information on how using PowerShell scripts see [Sample PowerShell scripts](#), [Input Parameters for PowerShell Scripting](#), [Input parameters for shell scripting](#), and [Sample shell scripts](#).

Prerequisites for PowerShell scripting

Before running PowerShell scripts for Rapid Recovery, you must have Windows PowerShell 2.0 or later installed. Due to new features introduced in PowerShell 3.0, including easier access to object properties, PowerShell Web access, and support for REST calls, Quest recommends using PowerShell 3.0 or later.

Note: Place the powershell.exe.config file in the PowerShell home directory. For example, C:\WindowsPowerShell\powershell.exe.config.

powershell.exe.config

```
<?xml version="1.0"?>
<configuration>
  <startup useLegacyV2RuntimeActivationPolicy="true">
    <supportedRuntime version="v4.0.30319"/>
    <supportedRuntime version="v2.0.50727"/>
  </startup>
</configuration>
```

Testing PowerShell Scripts

If you want to test the scripts you plan to run, you can do so by using the PowerShell graphical editor, *powershell_is*. You also need to add the configuration file *powershell_is.exe.config* to the same folder as the configuration file *powershell.exe.config*.

Note: The configuration file *powershell_is.exe.config* must have the same content as the *powershell.exe.config* file.

Caution: If the pre-PowerShell or post-PowerShell script fails, the job also fails.

Localization

When running on the same machine on which Rapid Recovery Core is installed, the Rapid Recovery PowerShell module bases its display language on the language set for the Core. Localized Rapid Recovery versions such as this one support English, Chinese (Simplified), French, Korean, German, Japanese, Portuguese (Brazil), and Spanish.

For Non-English releases, use: Rapid Recovery Core release 6.1.1 is an English-only release. As a result, English is the only language supported for the PowerShell Module. AppAssure release 6.0.2 is the most recent localized version of the Core software. In that release, supported languages include English, Chinese (Simplified), French, Korean, German, Japanese, Portuguese (Brazil), and Spanish.

If the Rapid Recovery PowerShell module is installed on a separate machine, English is the only language supported.

Qualifiers

The following table describes the qualifiers available for Rapid Recovery PowerShell Module.

Table 196: Rapid Recovery PowerShell module qualifiers

Qualifier	Usage
-core <Rapid Recovery Core Name>	Host name of the Core. Default: localhost
-ProtectedServer <Protected Server Name>	Host name/IP address of the Rapid Recovery Agent. Default: localhost if multiple servers

Qualifier	Usage
	protected, otherwise the single server protected.
-Mode <READ, READWRITE, WRITE>	Recovery Point Mount mode. Default: Read.
-Volumes <Snapshot Volume Letter>	Snapshot volume letter from Rapid Recovery Agent. Default: All.
-User <User Name>	User name used to connect to the Rapid Recovery Core. This is typically the service user.
-Domain <Domain Name>	Domain to which the user defined in /User belongs.
-Password <Password>	Password of the user defined in /User.
-Path <Target path to mount, dismount recovery points or archive location>	For example: C:\RapidRecoveryMount.

Input Parameters for PowerShell Scripting

All available input parameters are used in sample scripts. The parameters are described in the following tables.

Note: Script files must possess the same name as the sample script files.

AgentProtectionStorageConfiguration (namespace Replay.Common.Contracts.Agents)

The following table presents the available objects for the AgentProtectionStorageConfiguration parameter.

Table 197: Objects for the AgentProtectionStorageConfiguration parameter

Method	Description
public Guid RepositoryId { get; set; }	Gets or sets the ID of the repository where the agent recovery points are stored.
public string EncryptionKeyId { get; set; }	Gets or sets the ID of the encryption key for this agent's recovery points. An empty string means no encryption.

AgentTransferConfiguration (namespace Replay.Common.Contracts.Transfer)

The following table presents the available objects for the AgentTransferConfiguration parameter.

Table 198: Objects for the AgentTransferConfiguration parameter

Method	Description
public uint MaxConcurrentStreams { get; set; } }	Gets or sets the maximum number of concurrent TCP connections the Core establishes to the agent for transferring data.
public uint MaxTransferQueueDepth { get; set; } }	Gets or sets the maximum number of block extents which can be queued for writing. When a range of blocks are read from a transfer stream, that range is placed on a producer or consumer queue, where a consumer thread reads it and writes it to the epoch object. If the repository writes slower than the network reads, this queue fills up. The point at which the queue is full and reads stop is the maximum transfer queue depth.
public uint MaxConcurrentWrites { get; set; } }	Gets or sets the maximum number of block write operations to have outstanding on an epoch at any given time. If additional blocks are received beyond the maximum number of write operations specified in this parameter, those additional blocks are ignored until one of the outstanding writes finishes.
public ulong MaxSegmentSize { get; set; } }	Gets or sets the maximum number of contiguous blocks to transfer in a single request. Depending on testing, higher or lower values may be optimal.
public Priority Priority { get; set; } }	Gets or sets the priority for transfer request.
public uint GetChangedBlocksRetries { get; set; } }	Gets or sets the count of retries if initial retrieval of changed blocks from the agent failed.
public int MaxRetries { get; set; } }	Gets or sets the maximum number of times a failed transfer should be retried before it is presumed failed.
public bool UseDefaultMaxRetries { get; set; } }	If included, the default maximum number of retries (specified in transfer configuration) will be used.
public Guid ProviderId { get; set; } }	Gets or sets the GUID of the VSS provider to use for snapshots on this host. Administrators typically accept the default.
public Collection<ExcludedWriter> ExcludedWriterIds { get; set; } }	Gets or sets the collection of VSS writer IDs that should be excluded from this snapshot. The writer ID is determined by the name of the writer. This name is for documentation purposes only, and does not necessarily provide an exact match of the writer name.
public ushort TransferDataServerPort { get; set; } }	Gets or sets a value containing the TCP port upon which to accept connections from the Core for the actual transfer of data from the protected machine to the Core. The Agent attempts to listen on this port, but if the port is in use, the protected machine can use a different port instead. The Core should use the port number specified in the BlockHashesUri and BlockDataUri properties of the VolumeSnapshotInfo object for each snapped volume.
public TimeSpan CleanSnapshotTimeout { get; set; } }	Gets or sets the amount of time to wait for cleaning up the snapshot after transfer is finished.

Method	Description
}	
public TimeSpan SnapshotTimeout { get; set; }	Gets or sets the amount of time to wait for a VSS snapshot operation to complete before giving up and timing out.
public TimeSpan TransferTimeout { get; set; }	Gets or sets the amount of time to wait for further contact from the Core before abandoning the snapshot.
public TimeSpan NetworkReadTimeout { get; set; }	Gets or sets the timeout for network read operations related to this transfer.
public TimeSpan NetworkWriteTimeout { get; set; }	Gets or sets the timeout for network write operations related to this transfer.
public uint InitialQueueSize { get; set; }	Gets or sets a size of initial queue or requests.
public uint MinVolumeFreeSpacePercents { get; set; }	Gets or sets a minimal amount of free space on a volume, measured by percentage. If free space is lower than the amount specified in this parameter, then all change logs are deleted and a base image is forced.
public uint MaxChangeLogsSizePercents { get; set; }	Gets or sets a maximum size of driver change logs as part of volume capacity, measured by percentage. If part of change logs is bigger than this value, then all change logs are deleted and a base image is forced.
public bool EnableVerification { get; set; }	Gets or sets a value indicating whether diagnostic verification of each block sent to Core should be performed.

BackgroundJobRequest (namespace Replay.Core.Contracts.BackgroundJobs)

The following table presents the available objects for the BackgroundJobRequest parameter.

Table 199: Objects for the BackgroundJobRequest parameter

Method	Description
public AgentIdsCollection AgentIds { get; set; }	Gets or sets the IDs of the protected machines.
public bool IsNightlyJob { get; set; }	Gets or sets the value indicating whether the background job is a nightly job.
public Guid NightlyJobTransactionId { get; set; }	Gets or sets the ID of nightly job transaction.
public Guid JobId { get; set; }	Gets or sets the ID of background job.
public bool Force { get; set; }	Gets or sets the value indicating if a job was forced.
public uint JobStartsCount { get; set; }	Gets or sets the number of attempts to start a job.
public virtual bool InvolvesAgentId(Guid agentId)	Determines the value indicating whether the concrete agent is involved in job.

ChecksumCheckJobRequest (namespace Replay.Core.Contracts.Exchange.ChecksumChecks)

Inherits its values from the parameter, DatabaseCheckJobRequestBase.

DatabaseCheckJobRequestBase (namespace Replay.Core.Contracts.Exchange)

Inherits its values from the parameter, BackgroundJobRequest.

Table 200: Objects for the DatabaseCheckJobRequestBase parameter

Method	Description
public string RecoveryPointId { get; set; }	Gets or sets the ID of the recovery point for which databases will be checked.

ExportJobRequest (namespace Replay.Core.Contracts.Export)

Inherits its values from the parameter, BackgroundJobRequest.

The following table presents the available objects for the ExportJobRequest parameter.

Table 201: Objects for the ExportJobRequest parameter

Method	Description
public uint RamInMegabytes { get; set; }	Gets or sets the memory size for the exported VM. Set to zero (0) to use the memory size of the source machine.
public ushort CpuCount { get; set; }	Gets or sets the CPU count for the exported VM. Set to 0 to use the CPU count of the source machine.
public ushort CoresPerCpu { get; set; }	Gets or sets the Cores per CPU count for the exported VM. Set to 0 to use the Cores per CPU count of the source machine.
public VirtualMachineLocation Location { get; set; }	Gets or sets the target location for this export. This is an abstract base class.
public VolumeImageIdsCollection VolumeImageIds { get; private set; }	Gets or sets the volume images to include in the VM export.
public ExportJobPriority Priority { get; set; }	Gets or sets the priority for export request.

NightlyAttachabilityJobRequest (namespace Replay.Core.Contracts.Sql)

Inherits its values from the parameter, BackgroundJobRequest.

Table 202: Objects for the NightlyAttachabilityJobRequest parameter

Method	Description
public int SimultaneousJobsCount { get; set; }	Gets or sets count of jobs that can be run simultaneously.

RollupJobRequest (namespace Replay.Core.Contracts.Rollup)

Inherits its values from the parameter, BackgroundJobRequest.

TakeSnapshotResponse (namespace Replay.Agent.Contracts.Transfer)

The following table presents the available objects for the TakeSnapshotResponse parameter.

Table 203: Objects for the TakeSnapshotResponse parameter

Method	Description
public Guid SnapshotSetId { get; set; }	Gets or sets the GUID assigned by VSS to this snapshot.
public VolumeSnapshotInfoDictionary VolumeSnapshots { get; set; }	Gets or sets the collection of snapshot info for each volume included in the snap.

TransferJobRequest (namespace Replay.Core.Contracts.Transfer)

Inherits its values from the parameter, BackgroundJobRequest.

The following table presents the available objects for the TransferJobRequest parameter.

Table 204: Objects for the TransferJobRequest parameter

Method	Description
public VolumeNameCollection VolumeNames { get; set; }	Gets or sets the collection of names for transfer. VolumeNames is a data structure that contains the following data: <ul style="list-style-type: none"> GuidName. The Guid associated with the volume, used as the name if a DisplayName is not set. DisplayName. The displayed name of the volume.
public VolumeNameCollection TransferredVolumes { get; set; }	Gets or sets the collection of transferred volumes.
public VolumeNameCollection DependentVolumeNames { get; set; }	Gets or sets the collection of dependent volumes.
public QuotaSettingsCollection EnabledDiskQuotas { get; set; }	Gets or sets quotas that are enabled on a volume.

Method	Description
<pre>public ShadowCopyType ShadowCopyType { get }</pre>	<p>Gets the type of copying for transfer. The available values are:</p> <ul style="list-style-type: none"> • Copy • Full
<pre>public AgentTransferConfiguration TransferConfiguration { get; set; }</pre>	<p>Gets or sets the transfer configuration. AgentTransferConfiguration is an object which will have the following data:</p> <ul style="list-style-type: none"> • MaxConcurrentStreams. The maximum number of concurrent TCP connections the core will establish to the agent for transferring data • MaxTransferQueueDepth. The maximum number of block extents which can be queued up for writing • MaxConcurrentWrites. The maximum number of block write operations to have outstanding on an epoch at any given time. If additional blocks are received when this many block writes are outstanding, those additional blocks will be ignored until one of the outstanding blocks gets written. • MaxSegmentSize. The maximum number of contiguous blocks to transfer in a single request • Priority. An object which will have the following data: <ul style="list-style-type: none"> • Undefined • One • Two • Three • Four • Five • Six • Seven • Eight • Nine • Ten • Highest (which is equal to One) • Lowest (which is equal to Ten) • Default (which is equal to Five) • MaxRetries. The maximum number of times a failed transfer should be retried before it is presumed failed • UseDefaultMaxRetries. A value indicating that the maximum number of retries is the default value

Method	Description
	<ul style="list-style-type: none"> ProviderId. The GUID of the VSS provider to use for snapshots on this host. Users typically use the default setting.
public AgentProtectionStorageConfiguration StorageConfiguration { get; set; }	Gets or sets the storage configuration.
public string Key { get; set; }	Generates a pseudorandom (but not cryptographically secure) key, which can be used as a one-time password to authenticate transfer requests.
public bool IsBaseImage { get; set; }	Gets or sets value indicating whether base image will be taken.
public bool IsForced { get; set; }	Gets or sets value indicating whether transfer has been forced.
public Guid ProtectionGroupId { get; set; }	Gets or sets the ID of the protection group.
public TargetComponentTypes LogTruncationTargets { get; set; }	Gets or sets value that indicates for which databases log truncation will be performed (SQL or Exchange).
public bool ForceBaseImage { get; }	Gets the value indicating whether the base image was forced or not.
public bool IsLogTruncation { get; }	Gets the value indicating whether the log truncation job is performing or not.

TransferPrescriptParameter (namespace Replay.Common.Contracts.PowerShellExecution)

Inherits its values from the TransferScriptParameterBase parameter.

TransferPostscriptParameter (namespace Replay.Common.Contracts.PowerShellExecution)

The following table presents the available objects for the TransferPostscript parameter. Inherits its value from the TransferScriptParameterBase parameter.

Table 205: Objects for the TransferPostscript parameter

Method	Description
public VolumeNameCollection VolumeNames { get; set; }	<p>Gets or sets the collection of volume names for transfer. VolumeNames is a data structure that contains the following data:</p> <ul style="list-style-type: none"> GuidName. The Guid associated with the volume, used as the name if a DisplayName is not set. DisplayName. The displayed name of the volume.
public ShadowCopyType ShadowCopyType { get; set; }	Gets or sets the type of copying for transfer.ShadowCopyType is an enumeration with values. The available values are:

Method	Description
	<ul style="list-style-type: none"> • Unknown • Copy • Full
public AgentProtectionStorageConfigurationCommon StorageConfiguration { get; set; }	Gets or sets the storage configuration.
public AgentTransferConfiguration TransferConfiguration { get; set; }	<p>Gets or sets the transfer configuration. AgentTransferConfiguration is an object which will have the following data:</p> <ul style="list-style-type: none"> • MaxConcurrentStreams. The maximum number of concurrent TCP connections the core will establish to the agent for transferring data • MaxTransferQueueDepth. The maximum number of block extents which can be queued up for writing • MaxConcurrentWrites. The maximum number of block write operations to have outstanding on an epoch at any given time. If additional blocks are received when this many block writes are outstanding, those additional blocks will be ignored until one of the outstanding blocks gets written. • MaxSegmentSize. The maximum number of contiguous blocks to transfer in a single request • Priority. An object which has the following data: <ul style="list-style-type: none"> • "Undefined • "One • "Two • "Three • "Four • "Five • "Six • "Seven • "Eight • "Nine • "Ten • "Highest (which is equal to One) • "Lowest (which is equal to Ten) • "Default (which is equal to Five) • MaxRetries. The maximum number of times a failed transfer should be retried before it is presumed failed

Method	Description
	<ul style="list-style-type: none"> • UseDefaultMaxRetries. A value indicating that the maximum number of retries is the default value • ProviderId. The GUID of the VSS provider to use for snapshots on this host. Administrators typically accept the default.
public AgentTransferConfiguration TransferConfiguration { get; set; } (cont.)	<ul style="list-style-type: none"> • ExcludedWriterIds. Collection of VSS writer IDs which should be excluded from this snapshot. The writer ID is keyed by the name of the writer. This name is for documentation purposes only and does not have to exactly match the actual name of the writer. • TransferDataServerPort. A value containing the TCP port upon which to accept connections from the core for the actual transfer of data from the agent to the core. • SnapshotTimeout. The amount of time to wait for a VSS snapshot operation to complete before giving up and timing out. • TransferTimeout. The amount of time to wait for further contact from the core before abandoning the snapshot. • NetworkReadTimeout. The timeout for network read operations related to this transfer. • NetworkWriteTimeout. The timeout for network write operations related to this transfer. • InitialQueueSize. A size of initial queue of requests. • MinVolumeFreeSpacePercents. A minimal amount of free space on a volume in percent. • MaxChangeLogsSizePercents. A maximum size of driver change logs as part of volume capacity measured in percent. • EnableVerification. A value indicating whether diagnostic verification of each block sent to Core should be performed.
public AgentProtectionStorageConfiguration StorageConfiguration { get; set; }	<p>Gets or sets the storage configuration The AgentProtectionStorageConfiguration object contains the following data:</p> <ul style="list-style-type: none"> • RepositoryId. The name of the repository where this agent's recovery points will be stored • EncryptionKeyId. The ID of the encryption key for this agent's recovery points. An empty string means no encryption
public string Key { get; set; }	The Key method generates a pseudorandom (but not

Method	Description
	cryptographically secure) key, which can be used as a one-time password to authenticate transfer requests.
public bool ForceBaseImage { get; set; }	Gets or sets the value indicating whether the transfer was a forced base image capture.
public bool IsLogTruncation { get; set; }	Gets or sets the value indicating whether logging is being truncated.
public uint LatestEpochSeenByCore { get; set; }	Gets or sets latest epoch value. The LatestEpochSeenByCore method is the ordinal number of the most recent snapshot taken by the Core. This is the 'epoch number' assigned by the filter driver to this particular snapshot at the moment it was taken with VSS.
public Guid SnapshotSetId { get; set; }	Gets or sets the GUID assigned by VSS to this snapshot.
public VolumeSnapshotInfoDictionary VolumeSnapshots { get; set; }	Gets or sets the collection of snapshot info for each volume included in the snapshot.

TransferScriptParameterBase (namespace Replay.Common.Contracts.PowerShellExecution)

The following table presents the available objects for the TransferScriptParameterBase parameter.

Table 206: Objects for the TransferScriptParameterBase parameter

Method	Description
public AgentTransferConfiguration TransferConfiguration { get; set; }	Gets or sets the transfer configuration.
public AgentProtectionStorageConfigurationCommon StorageConfiguration { get; set; }	Gets or sets the storage configuration.

VirtualMachineLocation (namespace Replay.Common.Contracts.Virtualization)

The following table presents the available objects for the VirtualMachineLocation parameter.

Table 207: Objects for the VirtualMachineLocation parameter

Method	Description
public string Description { get; set; }	Gets or sets a human-readable description of this location.
public string Name { get; set; }	Gets or sets the name of the VM.

VolumelimageldsCollection (namespace Replay.Core.Contracts.RecoveryPoints)

Inherits its values from the parameter, System.Collections.ObjectModel.Collection<string>.

VolumeName (namespace Replay.Common.Contracts.Metadata.Storage)

The following table presents the available objects for the VolumeName parameter.

Table 208: Objects for the VolumeName parameter

Method	Description
public string GuidName { get; set; }	Gets or sets the ID of the volume.
public string DisplayName { get; set; }	Gets or sets the name of the volume.
public string UriEncode()	Gets a URL-encoded version of the name which can be passed cleanly on a URL. Note: A known issue exists in .NET 4.0 WCF (https://connect.microsoft.com/VisualStudio/feedback/ViewFeedback.aspx?FeedbackID=413312), which prevents path escape characters from working correctly in a URI template. Because a volume name contains both '\' and '?', you must replace the special characters '\' and '?' with other special characters.
public string GetMountName()	Returns a name for this volume that is valid for mounting volume image to some folder.

VolumeNameCollection (namespace Replay.Common.Contracts.Metadata.Storage)

Inherits its values from the parameter, System.Collections.ObjectModel.Collection<VolumeName>.

The following table presents the available objects for the VolumeNameCollection parameter.

Table 209: Objects for the VolumeNameCollection parameter

Method	Description
public override bool Equals(object obj)	Determines whether this instance and a specified object, which must also be a VolumeNameCollection object, have the same value. (Overrides Object.Equals(Object).)
public override int GetHashCode()	Returns the hash code for this VolumeNameCollection. (Overrides Object.GetHashCode().)

VolumeSnapshotInfo (namespace Replay.Common.Contracts.Transfer)

The following table presents the available objects for the VolumeSnapshotInfo parameter.

Table 210: Objects for the VolumeSnapshotInfo parameter

Method	Description
public Uri BlockHashesUri { get; set;}	Gets or sets the URI at which the MD5 hashes of volume blocks can be read.
public Uri BlockDataUri { get; set;}	Gets or sets the URI at which the volume data blocks can be read.

VolumeSnapshotInfoDictionary (namespace Replay.Common.Contracts.Transfer)

Inherits its values from the parameter, System.Collections.Generic.Dictionary<VolumeName, VolumeSnapshotInfo>.

Sample PowerShell scripts

The following sample scripts are provided to assist administrative users in executing PowerShell scripts.

- [PreTransferScript.ps1](#)
- [PostTransferScript.ps1](#)
- [PreExportScript.ps1](#)
- [PostExportScript.ps1](#)
- [PreNightlyJobScript.ps1](#)
- [PostNightlyJobScript.ps1](#)

PreTransferScript.ps1

The PreTransferScript is run on the protected machine before transferring a snapshot.

Sample PreTransferScript

```
# receiving parameter from transfer job
param([object]$TransferPrescriptParameter)
# building path to Agent's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Agent 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
# Converting input parameter into specific object
```

```

$TransferPrescriptParameterObject = $TransferPrescriptParameter -as
[Replay.Common.Contracts.PowerShellExecution.TransferPrescriptParameter];
# Working with input object. All echo's are logged
if($TransferPrescriptParameterObject -eq $null) {
    echo 'TransferPrescriptParameterObject parameter is null'
}
else {
    echo
'TransferConfiguration:'$TransferPrescriptParameterObject.TransferConfiguration
    echo 'StorageConfiguration:'
$TransferPrescriptParameterObject.StorageConfiguration
}

```

PostTransferScript.ps1

The PostTransferScript is run on the protected machine after transferring a snapshot.

Sample PostTransferScript

```

# receiving parameter from transfer job
param([object] $TransferPostscriptParameter)
# building path to Agent's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Agent 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
# Converting input parameter into specific object
$TransferPostscriptParameterObject = $TransferPostscriptParameter -as
[Replay.Common.Contracts.PowerShellExecution.TransferPostscriptParameter];
# Working with input object. All echo's are logged
if($TransferPostscriptParameterObject -eq $null) {
    echo 'TransferPostscriptParameterObject parameter is null'
}
else {
echo 'VolumeNames:' $TransferPostscriptParameterObject.VolumeNames
    echo 'ShadowCopyType:'
$TransferPostscriptParameterObject.ShadowCopyType
    echo 'ForceBaseImage:'
$TransferPostscriptParameterObject.ForceBaseImage
    echo 'IsLogTruncation:'
$TransferPostscriptParameterObject.IsLogTruncation
}

```

PreExportScript.ps1

The PreExportScript is run on the Core before any export job.

Sample PreExportScript

```
# receiving parameter from export job
param([object]$ExportJobRequest)
# building path to Core's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Core 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'CoreService\Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
# Converting input parameter into specific object
$ExportJobRequestObject = $ExportJobRequest -as
[Replay.Core.Contracts.Export.ExportJobRequest]
# Working with input object. All echo's are logged
if($ExportJobRequestObject -eq $null) {
    echo 'ExportJobRequestObject parameter is null'
}
else {
    echo 'Location:' $ExportJobRequestObject.Location
    echo 'Priority:' $ExportJobRequestObject.Priority
}
```

PostExportScript.ps1

The PostExportScript is run on the Core after any export job.

Note: There are no input parameters for the PostExportScript when used to run once on the exported protected machine after initial startup. The regular protected machine should contain this script in the PowerShell script folder as PostExportScript.ps1.

Sample PostExportScript

```
# receiving parameter from export job
param([object]$ExportJobRequest)
# building path to Core's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Core 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'CoreService\Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
$regVal2 = $regLM.GetValue('InstallLocation')
$regVal2 = $regVal2 + 'CoreService\Common.Contracts.dll'
# Converting input parameter into specific object
$ExportJobRequestObject = $ExportJobRequest -as
[Replay.Core.Contracts.Export.ExportJobRequest]
# Working with input object. All echo's are logged
if($ExportJobRequestObject -eq $null) {
    echo 'ExportJobRequestObject parameter is null'
}
else {
```

```

        echo 'VolumeImageIds:' $ExportJobRequestObject.VolumeImageIds
        echo 'RamInMegabytes:' $ExportJobRequestObject.RamInMegabytes
    }

```

PreNightlyJobScript.ps1

The PreNightlyJobScript is run before every nightly job on Core side. It contains the parameter \$JobClassName, which helps to handle those child jobs separately.

Sample PreNightlyJobScript

```

# receiving parameters from Nightlyjob
param([System.String]$JobClassMethod , [object]$NightlyAttachabilityJobRequest,
[object]$RollupJobRequest, [object]$Agents, [object]$ChecksumCheckJobRequest,
[object]$TransferJobRequest, [int]$LatestEpochSeenByCore)
# building path to Core's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Core 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'CoreService\Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
# Nightlyjob has four child jobs: NightlyAttachability Job, Rollup Job, Checksum
Check Job and Log Truncation Job. All of them are triggering the script, and
$JobClassMethod (contain job name that calls the script) helps to handle those child
jobs separately
switch ($JobClassMethod) {
# working with NightlyAttachability Job
    NightlyAttachabilityJob {
        $NightlyAttachabilityJobRequestObject = $NightlyAttachabilityJobRequest -as
[Replay.Core.Contracts.Sql.NightlyAttachabilityJobRequest];
        echo 'Nightly Attachability job results:';
        if($NightlyAttachabilityJobRequestObject -eq $null) {
            echo 'NightlyAttachabilityJobRequestObject parameter is null';
        }
        else {
            echo 'AgentIds:' $NightlyAttachabilityJobRequestObject.AgentIds;
            echo 'IsNightlyJob:' $NightlyAttachabilityJobRequestObject.IsNight
        }
        break;
    }
# working with Rollup Job
    RollupJob {
        $RollupJobRequestObject = $RollupJobRequest -as
[Replay.Core.Contracts.Rollup.RollupJobRequest];
        echo 'Rollup job results:';
        if($RollupJobRequestObject -eq $null) {
            echo 'RollupJobRequestObject parameter is null';
        }
        else {
            echo 'SimultaneousJobsCount:' $RollupJobRequestObject.Simultaneous

```

```

        echo 'AgentIds:' $RollupJobRequestObject.AgentIds;
        echo 'IsNightlyJob:' $RollupJobRequestObject.IsNightlyJob;
    }
    $AgentsCollection = $Agents -as "System.Collections.Generic.List`1[System
    if($AgentsCollection -eq $null) {
        echo 'AgentsCollection parameter is null';
    }
    else {
        echo 'Agents GUIDs:'
        foreach ($a in $AgentsCollection) {
            echo $a
        }
    }
    break;
}

# working with Checksum Check Job
ChecksumCheckJob {
    $ChecksumCheckJobRequestObject = $ChecksumCheckJobRequest -as
[Replay.Core.Contracts.Exchange.ChecksumChecks.ChecksumCheckJobRequest];
    echo 'Exchange checksumcheck job results:';
    if($ChecksumCheckJobRequestObject -eq $null) {
        echo 'ChecksumCheckJobRequestObject parameter is null';
    }
    else {
        echo 'RecoveryPointId:' $ChecksumCheckJobRequestObject.RecoveryPoi
        echo 'AgentIds:' $ChecksumCheckJobRequestObject.AgentIds;
        echo 'IsNightlyJob:' $ChecksumCheckJobRequestObject.IsNightlyJob;
    }
    break;
}

# working with Log Truncation Job
TransferJob {
    $TransferJobRequestObject = $TransferJobRequest -as
[Replay.Core.Contracts.Transfer.TransferJobRequest];
    echo 'Transfer job results:';
    if($TransferJobRequestObject -eq $null) {
        echo 'TransferJobRequestObject parameter is null';
    }
    else {
        echo 'TransferConfiguration:' $TransferJobRequestObject.TransferCo
        echo 'StorageConfiguration:' $TransferJobRequestObject.StorageConf
    }
    echo 'LatestEpochSeenByCore:' $LatestEpochSeenByCore;
    break;
}
}

```

PostNightlyJobScript.ps1

The PostNightlyJobScript is run after every nightly job on the Core. It contains the parameter \$JobClassName, which helps to handle those child jobs separately.

Sample PostNightlyJobScript

```
# receiving parameters from Nightlyjob
param([System.String]$JobClassMethod , [object]$NightlyAttachabilityJobRequest,
[object]$RollupJobRequest, [object]$Agents, [object]$ChecksumCheckJobRequest,
[object]$TransferJobRequest, [int]$LatestEpochSeenByCore,
[object]$TakeSnapshotResponse)
# building path to Core's Common.Contracts.dll and loading this assembly
$regLM = [Microsoft.Win32.Registry]::LocalMachine
$regLM = $regLM.OpenSubKey
('SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\AppRecovery Core 5')
$regVal = $regLM.GetValue('InstallLocation')
$regVal = $regVal + 'CoreService\Common.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal) | out-null
$regVal2 = $regLM.GetValue('InstallLocation')
$regVal2= $regVal2 + 'CoreService\Core.Contracts.dll'
[System.Reflection.Assembly]::LoadFrom($regVal2) | out-null
# Nightlyjob has four child jobs: NightlyAttachability Job, Rollup Job, Checksum
Check Job and Log Truncation Job. All of them are triggering the script, and
$JobClassMethod (contain job name that calls the script) helps to handle those child
jobs separately
switch ($JobClassMethod) {
# working with NightlyAttachability Job
    NightlyAttachabilityJob {
        $NightlyAttachabilityJobRequestObject = $NightlyAttachabilityJobRequest -as
[Replay.Core.Contracts.Sql.NightlyAttachabilityJobRequest];
        echo 'Nightly Attachability job results: ';
        if($NightlyAttachabilityJobRequestObject -eq $null) {
            echo 'NightlyAttachabilityJobRequestObject parameter is null';
        }
        else {
            echo 'AgentIds:' $NightlyAttachabilityJobRequestObject.AgentIds;
            echo 'IsNightlyJob:' $NightlyAttachabilityJobRequestObject.IsNightlyJob;
        }
        break;
    }
# working with Rollup Job
    RollupJob {
        $RollupJobRequestObject = $RollupJobRequest -as
[Replay.Core.Contracts.Rollup.RollupJobRequest];
        echo 'Rollup job results: ';
        if($RollupJobRequestObject -eq $null) {
            echo 'RollupJobRequestObject parameter is null';
        }
        else {
            echo 'AgentIds:' $RollupJobRequestObject.AgentIds;
            echo 'IsNightlyJob:' $RollupJobRequestObject.IsNightlyJob;
        }
        $AgentsCollection = $Agents -as "System.Collections.Generic.List`1[System.Guid]"
        if($AgentsCollection -eq $null) {
            echo 'AgentsCollection parameter is null';
        }
    }
}
```

```

    }
    else {
    echo 'Agents GUIDs:'
        foreach ($a in $AgentsCollection) {
            echo $a
        }
    }
    break;
}

# working with Checksum Check Job
ChecksumCheckJob {
    $ChecksumCheckJobRequestObject = $ChecksumCheckJobRequest -as
[Replay.Core.Contracts.Exchange.ChecksumChecks.ChecksumCheckJobRequest];
    echo 'Exchange checksumcheck job results:';
    if($ChecksumCheckJobRequestObject -eq $null) {
        echo 'ChecksumCheckJobRequestObject parameter is null';
    }
    else {
        echo 'RecoveryPointId:' $ChecksumCheckJobRequestObject.RecoveryPointId;
        echo 'AgentIds:' $ChecksumCheckJobRequestObject.AgentIds;
        echo 'IsNightlyJob:' $ChecksumCheckJobRequestObject.IsNightlyJob;
    }
    break;
}

# working with Log Truncation Job
TransferJob {
    $TransferJobRequestObject = $TransferJobRequest -as
[Replay.Core.Contracts.Transfer.TransferJobRequest];
    echo 'Transfer job results:';
    if($TransferJobRequestObject -eq $null) {
        echo 'TransferJobRequestObject parameter is null';
    }
    else {
        echo 'TransferConfiguration:' $TransferJobRequestObject.TransferConfigura
        echo 'StorageConfiguration:' $TransferJobRequestObject.StorageConfiguratio
    }
    echo 'LatestEpochSeenByCore:' $LatestEpochSeenByCore;
    $TakeSnapshotResponseObject = $TakeSnapshotResponse -as
[Replay.Agent.Contracts.Transfer.TakeSnapshotResponse];
    if($TakeSnapshotResponseObject -eq $null) {
        echo 'TakeSnapshotResponseObject parameter is null';
    }
    else {
        echo 'ID of this transfer session:' $TakeSnapshotResponseObject.SnapshotSe
        echo 'Volumes:' $TakeSnapshotResponseObject.VolumeSnapshots;
    }
    break;
}
}

```

Using Bourne shell and Bash scripting with Rapid Recovery

Bourne shell (sh) is a shell language or command-line interpreter for Unix-based operating systems. Bourne shell is used in Rapid Recovery with Linux to customize environments and specify certain operations to occur in a predetermined sequence. The .sh is the file extension and naming convention for Bourne shell files.

Bourne Again Shell (Bash) is a similar shell language that implements the same grammar, parameter, and variable expansion, redirection and quoting. Bash also uses the same .sh file extension. The information here applies equally to Bash.

Using pre and post transfer, pre and post snapshot, and post export script hooks, you can perform system operations before and after a transfer or snapshot, or after virtual export. For example, you may want to disable a certain cronjob while a transfer is occurring and enable it once the transfer has finished. As another example, you may need to run commands to flush application-specific data to disk. The contents are written to a temporary file and run using exec. The script then runs using the interpreter defined in the first line of the script, for example, `(#!/usr/bin/env bash)`. If the specified interpreter is not available, the script uses the default shell defined in the \$SHELL environment variable.

You can substitute and use any interpreter. For example, on the `#!` line of the script, you can replace “bash” with “zsh” (Z shell), “tcsh” (tee shell), and so on, based on your preference.

You can add available objects from the TransferPrescript parameter or add your own commands to the PreTransferScript.sh and PostTransfer.sh scripts to customize them.

Only PreTransferScript and PostTransferScript receive parameters. The snapshot and export scripts do not.

This section describes the scripts that administrators can use at designated occurrences in Rapid Recovery for Windows and Linux. It includes the following topics:

- [Input parameters for shell scripting](#)
- [Sample shell scripts](#)

Prerequisites for shell scripting

Rapid Recovery provides the ability to run Bourne shell, Bash, and other shell scripts on a protected Linux machine before and after a transfer. The following scripts are supported for Linux machines protected with the Rapid Recovery Agent software.

Note: If a script is not executable, the transfer job fails.


- PreTransferScript.sh
- PostTransferScript.sh
- PreSnapshotScript.sh
- PostSnapshotScript.sh
- PostExportScript.sh

To use these scripts, ensure that they reside in the `/opt/apprecovery/scripts/` directory.

Execution timing for pre and post scripts

For context, the following diagram shows the difference in timing for running pre and post transfer and snapshot scripts.

When pre and post scripts execute



Supported transfer and post-transfer script parameters

The following parameters are supported on Linux for transfer scripts. For more information, see [Sample shell scripts](#).

- `TransferPrescriptParameter_VolumeNames=$TransferPrescriptParameter_VolumeNames`
- `TransferPrescriptParameter_ShadowCopyType=$TransferPrescriptParameter_ShadowCopyType`
- `TransferPrescriptParameter_TransferConfiguration=$TransferPrescriptParameter_TransferConfiguration`
- `TransferPrescriptParameter_StorageConfiguration=$TransferPrescriptParameter_StorageConfiguration`
- `TransferPrescriptParameter_Key=$TransferPrescriptParameter_Key`
- `TransferPrescriptParameter_ForceBaseImage=$TransferPrescriptParameter_ForceBaseImage`
- `TransferPrescriptParameter_IsLogTruncation=$TransferPrescriptParameter_IsLogTruncation`
- `TransferPrescriptParameter_LatestEpochSeenByCore=$TransferPrescriptParameter_LatestEpochSeenByCore`

The following parameters are supported on Linux for post transfer scripts.

- `TransferPostscriptParameter_VolumeNames=$TransferPostscriptParameter_VolumeNames`
- `TransferPostscriptParameter_ShadowCopyType=$TransferPostscriptParameter_ShadowCopyType`
- `TransferPostscriptParameter_TransferConfiguration=$TransferPostscriptParameter_TransferConfiguration`
- `TransferPostscriptParameter_StorageConfiguration=$TransferPostscriptParameter_StorageConfiguration`

- `TransferPostscriptParameter_Key=$TransferPostscriptParameter_Key`
- `TransferPostscriptParameter_ForceBaseImage=$TransferPostscriptParameter_ForceBaseImage`
- `TransferPostscriptParameter_IsLogTruncation=$TransferPostscriptParameter_IsLogTruncation`
- `TransferPostscriptParameter_LatestEpochSeenByCore=$TransferPostscriptParameter_LatestEpochSeenByCore`

Testing shell scripting

You can test the scripts you want to run by using the editor for the script (.sh) files.

Note: If the pre or post script fails, the job also fails. Information about the job is available in the `/var/log/apprecovery/apprecovery.log` file. Successful scripts return the exit code 0.

Input parameters for shell scripting

The parameters for shell scripting in Rapid Recovery are described in the following tables.

TransferPrescriptParameters_VolumeNames

The following table presents the available objects for the TransferPrescript parameter.

Table 211: TransferPrescript objects

Method	Description
public VolumeNameCollection VolumeNames (get; set;)	<p>Gets or sets the collection of volume names for transfer.</p> <p>VolumeNames is a data structure that contains the following data:</p> <ul style="list-style-type: none"> • GuidName. The Guid associated with the volume, used as the name if a DisplayName is not set. • DisplayName. The displayed name of the volume.
public ShadowCopyType ShadowCopyType { get; set; }	<p>Gets or sets the type of copying for transfer. ShadowCopyType is an enumeration with values. The available values are:</p> <ul style="list-style-type: none"> • Unknown • Copy • Full

Method	Description
public string Key { get; set; }	The Key method generates a pseudorandom (but not cryptographically secure) key, which can be used as a one-time password to authenticate transfer requests.
public bool ForceBaseImage { get; set; }	Gets or sets the value indicating whether the transfer was a forced base image capture.
public bool IsLogTruncation { get; set; }	Gets or sets the value indicating whether logging is being truncated.
public uint LatestEpochSeenByCore { get; set; }	Gets or sets latest epoch value. The LatestEpochSeenByCore method is the ordinal number of the most recent snapshot taken by the Core. This is the 'epoch number' assigned by the filter driver to this particular snapshot at the moment it was taken with VSS.

TransferPostscriptParameter

The following table presents the available objects for the TransferPostscript parameter.

Table 212: TransferPostscript objects

Method	Description
public VolumeNameCollection VolumeNames { get; set; }	Gets or sets the collection of volume names for transfer. VolumeNames is a data structure that contains the following data: <ul style="list-style-type: none"> • GuidName. The Guid associated with the volume, used as the name if a DisplayName is not set. • DisplayName. The displayed name of the volume.
public ShadowCopyType	Gets or sets the type of

Method	Description
ShadowCopyType { get; set; }	<p>copying for transfer. ShadowCopyType is an enumeration with values. The available values are:</p> <ul style="list-style-type: none"> • Unknown • Copy • Full
public string Key { get; set; }	<p>The Key method generates a pseudorandom (but not cryptographically secure) key, which can be used as a one-time password to authenticate transfer requests.</p>
public bool ForceBaseImage { get; set; }	<p>Gets or sets the value indicating whether the transfer was a forced base image capture.</p>
public bool IsLogTruncation { get; set; }	<p>Gets or sets the value indicating whether logging is being truncated.</p>
public uint LatestEpochSeenByCore { get; set; }	<p>Gets or sets latest epoch value.</p> <p>The LatestEpochSeenByCore method is the ordinal number of the most recent snapshot taken by the Core. This is the 'epoch number' assigned by the filter driver to this particular snapshot at the moment it was taken with VSS.</p>

Sample shell scripts

This section describes the sample shell scripts available for administrative users to run on protected machines.

Caution: The sample scripts provided in this document function as they exist when run by qualified administrators. Take precautions when modifying functioning scripts to retain working versions. Any modifications to the script samples included here, or any scripts you create, are considered customization, which is not typically covered by Quest Support.

Note: Protected machines use the 'exec' shell command to launch the script. You can indicate which interpreter should run the script by defining that information in the first line of the script. If you do not specify the interpreter, the default shell interprets the script. If you choose something other than the default shell, you must ensure that the specified interpreter is available on all protected machines. All sample shell scripts in this document are tested and run successfully as Bourne shell or Bash scripts.

The sample scripts for protected machines include:

PreTransferScript.sh

The PreTransferScript is run on the protected Linux machine immediately before the backup snapshot transfer begins.

Note: For clarification on when pre and post scripts are run, see [Using Bourne shell and Bash scripting with Rapid Recovery](#).

The following script stores the values from input parameters in PreTransferScriptResult.txt, which is stored in the root home directory.

Sample PreTransferScript

```
#!/bin/bash
echo "TransferPrescriptParameter_VolumeNames=$TransferPrescriptParameter_
VolumeNames
TransferPrescriptParameter_ShadowCopyType=$TransferPrescriptParameter_
ShadowCopyType
TransferPrescriptParameter_Key=$TransferPrescriptParameter_Key
TransferPrescriptParameter_ForceBaseImage=$TransferPrescriptParameter_
ForceBaseImage
TransferPrescriptParameter_IsLogTruncation=$TransferPrescriptParameter_
IsLogTruncation
TransferPrescriptParameter_LatestEpochSeenByCore=$TransferPrescriptParameter_
LatestEpochSeenByCore" > ~/PreTransferScriptResult.txt
exit 0
```

PostTransferScript.sh

The PostTransferScript is run on the protected Linux machine after the backup snapshot process has fully completed.

Note: For clarification on when pre and post scripts are run, see [Using Bourne shell and Bash scripting with Rapid Recovery](#).

The following script stores the values from input parameters in PostTransferScriptResult.txt, which is stored in the root home directory.

Sample PostTransferScript

```
#!/bin/bash
echo "TransferPostscriptParameter_VolumeNames=$TransferPostscriptParameter_
VolumeNames
TransferPostscriptParameter_ShadowCopyType=$TransferPostscriptParameter_
ShadowCopyType
TransferPostscriptParameter_Key=$TransferPostscriptParameter_Key
TransferPostscriptParameter_ForceBaseImage=$TransferPostscriptParameter_
ForceBaseImage
TransferPostscriptParameter_IsLogTruncation=$TransferPostscriptParameter_
IsLogTruncation
TransferPostscriptParameter_LatestEpochSeenByCore=$TransferPostscriptParameter_
LatestEpochSeenByCore" > ~/PostTransferScriptResult.txt
exit 0
```

PreSnapshotScript.sh

The PreSnapshotScript is run on the protected Linux machine after preparation but before data is read from the original device when capturing a snapshot. This script does not receive parameters from the protected machine.

Note: For clarification on when pre and post scripts are run, see [Using Bourne shell and Bash scripting with Rapid Recovery](#).

The following script returns the time that the script completed on the machine in hours, minutes, and seconds, based on the system time of the Core. This information is logged in PreSnapshotScriptResult.txt, which is stored in the root home directory.

Sample PreSnapshotScript

```
#!/bin/bash
echo "`date +%H:%M:%S` PreSnapshot script has been executed." >
~/PreSnapshotScriptResult.txt
exit 0
```

PostSnapshotScript.sh

The PostSnapshotScript is run on the protected Linux machine after data is read from the original device when capturing a snapshot, but before data is read from the copied device. This script does not receive parameters from the protected machine.

Note: For clarification on when pre and post scripts are run, see [Using Bourne shell and Bash scripting with Rapid Recovery](#).

The following script returns the time that the script completed on the machine in hours, minutes, and seconds, based on the system time of the Core. This information is logged in PostSnapshotScriptResult.txt, which is stored in the root home directory.

Sample PostSnapshotScript

```
#!/bin/bash
echo "`date +%H:%M:%S` PostSnapshot script has been executed." >
~/PostSnapshotScriptResult.txt
exit 0
```

PostExportScript.sh

The PostExportScript is run on the exported Linux machine after the virtual export is complete. This script does not receive parameters from the protected machine.

Note: The original machine from which the VM was cloned should be powered off before starting the VM.

The following script returns the start time of the exported virtual machine in hours, minutes, and seconds, based on the system time of the Core. This information is logged in PostExportScriptResult.txt, which is stored in the root home directory.

Sample PostExportScript

```
#!/bin/bash
echo
"`date +%H:%M:%S` Start time of the machine. This indicates that virtual export has
```

```
been completed and machine is active." > ~/PostExportScriptResult.txt  
exit 0
```

Quest creates software solutions that make the benefits of new technology real in an increasingly complex IT landscape. From database and systems management, to Active Directory and Office 365 management, and cyber security resilience, Quest helps customers solve their next IT challenge now. Around the globe, more than 130,000 companies and 95% of the Fortune 500 count on Quest to deliver proactive management and monitoring for the next enterprise initiative, find the next solution for complex Microsoft challenges and stay ahead of the next threat. Quest Software. Where next meets now. For more information, visit www.quest.com.

Technical support resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product