



Quest Recovery Manager for Active Directory  
Disaster Recovery Edition 10.2.1

## **Management Shell Guide**



**© 2021 Quest Software Inc.**

**ALL RIGHTS RESERVED.**

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.

Attn: LEGAL Dept

4 Polaris Way

Aliso Viejo, CA 92656

Refer to our Web site (<https://www.quest.com>) for regional and international office information.

**Patents**

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

**Trademarks**

Quest, the Quest logo, and Join the Innovation are trademarks and registered trademarks of Quest Software Inc. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Updated – December 2021

# Contents

|  |          |
|--|----------|
| <b>Overview .....</b>                        | <b>6</b> |
| About Management Shell.....                  | 6        |
| Installing and opening Management Shell..... | 6        |
| Installation requirements .....              | 6        |
| Installing Management Shell .....            | 7        |
| Opening Management Shell.....                | 7        |
| Getting Help .....                           | 7        |
| Descriptions of PowerShell commands .....    | 8        |
| Add-RMADBackup .....                         | 14       |
| Add-RMADCollectionItem.....                  | 17       |
| Add-RMADFECloudStorage.....                  | 23       |
| Add-RMADReplicationConsole .....             | 26       |
| Add-RMADStorageServer .....                  | 28       |
| Backup-RMADCollection .....                  | 31       |
| Close-RMADFEProject.....                     | 33       |
| Compare-RMADObject.....                      | 34       |
| Convert-RMADBackup .....                     | 44       |
| ConvertTo-RMADRecycledObject.....            | 46       |
| Copy-RMADFEBackup .....                      | 49       |
| Create-RMADStorageAgentSetup .....           | 52       |
| Expand-RMADBackup.....                       | 53       |
| Export-RMADBackup .....                      | 57       |
| Export-RMADFECloudStorageBackup.....         | 59       |
| Export-RMADFERecoveryCertificate .....       | 62       |
| Export-RMADFEResult.....                     | 63       |
| Export-RMADSecureStorageBackup .....         | 65       |
| Get-RMADBackup .....                         | 68       |
| Get-RMADBackupAgent.....                     | 76       |
| Get-RMADBackupInfo .....                     | 78       |
| Get-RMADBackupObject.....                    | 81       |
| Get-RMADBackupSecurityStatus.....            | 86       |
| Get-RMADCollection .....                     | 88       |
| Get-RMADCollectionItem .....                 | 90       |
| Get-RMADDeletedObject .....                  | 93       |
| Get-RMADFEAvailableSubnet .....              | 100      |
| Get-RMADFECloudStorage .....                 | 101      |
| Get-RMADFECloudStorageCollection .....       | 103      |
| Get-RMADFECloudStorageUploadSession .....    | 105      |
| Get-RMADFEComputer.....                      | 107      |

|  |     |
|--|-----|
| Get-RMADFEConsole .....                      | 109 |
| Get-RMADFEDnsCache.....                      | 110 |
| Get-RMADFEDomain .....                       | 111 |
| Get-RMADFEEvent .....                        | 112 |
| Get-RMADFEGlobalOptions.....                 | 114 |
| Get-RMADFEOperation.....                     | 115 |
| Get-RMADFEPersistenceConnection .....        | 116 |
| Get-RMADFEProject .....                      | 117 |
| Get-RMADFERecoveryAgent.....                 | 119 |
| Get-RMADFESchedule .....                     | 121 |
| Get-RMADGlobalOptions .....                  | 122 |
| Get-RMADLicenseInfo.....                     | 124 |
| Get-RMADObject.....                          | 125 |
| Get-RMADReplicationConsole .....             | 132 |
| Get-RMADReplicationSchedule .....            | 133 |
| Get-RMADReplicationSession .....             | 134 |
| Get-RMADReplicationSessionItem .....         | 136 |
| Get-RMADReportObject.....                    | 137 |
| Get-RMADReportObjectAttributes.....          | 139 |
| Get-RMADReportObjectChildren .....           | 140 |
| Get-RMADReportSession .....                  | 142 |
| Get-RMADSession .....                        | 143 |
| Get-RMADSessionItem .....                    | 147 |
| Get-RMADSessionItemEvent.....                | 149 |
| Get-RMADStorageServer.....                   | 151 |
| Get-RMADStorageServerAllowedVolumes .....    | 152 |
| Get-RMADStorageServerHardeningStatus .....   | 153 |
| Get-RMADStorageServerRetentionPolicy.....    | 155 |
| Import-RMADBackup.....                       | 156 |
| Import-RMADFERecoveryCertificate .....       | 158 |
| Install-RMADBackupAgent .....                | 159 |
| Install-RMADFERecoveryAgent .....            | 162 |
| New-RMADCollection .....                     | 164 |
| New-RMADFEProject .....                      | 166 |
| New-RMADFERecoveryMedia .....                | 168 |
| New-RMADSchedule.....                        | 172 |
| Open-RMADFEProject .....                     | 178 |
| Protect-RMADSecureStorageServer.....         | 180 |
| Protect-RMADStorageServer .....              | 182 |
| Publish-RMADBackupSecurityStatus.....        | 184 |
| Refresh-RMADStorageServer .....              | 186 |
| Register-RMADSecureStorageBackups .....      | 188 |
| Remove-RMADBackup .....                      | 190 |
| Remove-RMADBackupAgent .....                 | 193 |
| Remove-RMADCollection.....                   | 195 |
| Remove-RMADCollectionItem.....               | 198 |
| Remove-RMADFECLOUDStorage .....              | 199 |
| Remove-RMADFECLOUDStorageUploadSession ..... | 202 |

|   |            |
|---|------------|
| Remove-RMADFERecoveryAgent .....              | 205        |
| Remove-RMADFESchedule .....                   | 207        |
| Remove-RMADReplicationConsole .....           | 209        |
| Remove-RMADReplicationSchedule .....          | 211        |
| Remove-RMADReplicationSession .....           | 212        |
| Remove-RMADStorageServer .....                | 213        |
| Remove-RMADUnpackedComponent .....            | 216        |
| Rename-RMADCollection .....                   | 218        |
| Restart-RMADFECloudStorageUploadSession ..... | 222        |
| Restore-RMADDeletedObject .....               | 224        |
| Restore-RMADDomainController .....            | 234        |
| Restore-RMADObject .....                      | 239        |
| Resume-RMADFERecovery .....                   | 247        |
| Save-RMADFEProject .....                      | 249        |
| Set-RMADCollection .....                      | 251        |
| Set-RMADFECloudStorage .....                  | 262        |
| Set-RMADFECloudStorageCollection .....        | 265        |
| Set-RMADFEComputer .....                      | 268        |
| Set-RMADFEDnsCache .....                      | 287        |
| Set-RMADFEDomain .....                        | 289        |
| Set-RMADFEGlobalOptions .....                 | 293        |
| Set-RMADFEPersistenceConnection .....         | 297        |
| Set-RMADFERecoveryMode .....                  | 300        |
| Set-RMADFESchedule .....                      | 301        |
| Set-RMADGlobalOptions .....                   | 303        |
| Set-RMADReplicationConsole .....              | 306        |
| Set-RMADReplicationSchedule .....             | 310        |
| Set-RMADStorageServerAllowedVolumes .....     | 312        |
| Set-RMADStorageServerRetentionPolicy .....    | 314        |
| Start-RMADFERecovery .....                    | 316        |
| Start-RMADFERecoveryAgentOperation .....      | 319        |
| Start-RMADFEVerification .....                | 322        |
| Start-RMADReplication .....                   | 323        |
| Start-RMADReportViewer .....                  | 325        |
| Stop-RMADFECloudStorageUploadSession .....    | 326        |
| Stop-RMADFEWorkflow .....                     | 328        |
| Test-RMADSecureStorageBackup .....            | 330        |
| Unprotect-RMADStorageServer .....             | 332        |
| Update-RMADBackupAgent .....                  | 334        |
| Update-RMADFEProject .....                    | 336        |
| Update-RMADLicense .....                      | 338        |
| <b>About us .....</b>                         | <b>340</b> |

# Overview

- [Installing and Opening Management Shell](#)
- [Getting Help](#)
- [Descriptions of PowerShell Commands](#)

## About Management Shell

The Recovery Manager for Active Directory Management Shell, built on Microsoft Windows PowerShell technology, provides a command-line interface that enables automation of backup/recovery-related administrative tasks. With this Management Shell, administrators can manage Computer Collections, backup/recovery sessions, compare and start backup/recovery jobs.

The Management Shell command-line tools (cmdlets), like all the Windows PowerShell cmdlets, are designed to deal with objects—structured information that is more than just a string of characters appearing on the screen. The cmdlets do not use text as the basis for interaction with the system, but use an object model that is based on the Microsoft .NET platform. In contrast to traditional, text-based commands, the cmdlets do not require the use of text-processing tools to extract specific information. Rather, you can access portions of the data directly by using standard Windows PowerShell object manipulation commands.

## Installing and opening Management Shell

This section covers:

- [Installation requirements](#)
- [Installing Management Shell](#)
- [Opening Management Shell](#)

## Installation requirements

Before you install the Recovery Manager for Active Directory Management Shell, ensure that your system meets the system requirements provided.

### Requirements

Microsoft Windows PowerShell version 5.0 or later

# Installing Management Shell

## **To install Management Shell**

1. Run the **Setup.exe** file included with the Recovery Manager for Active Directory installation package, and follow the instructions in the Setup Wizard.
2. To install Recovery Manager for Active Directory with default parameters (this includes installing the Management Shell component), click **Express**, and then follow the provided instructions to complete the Setup Wizard.

# Opening Management Shell

You can open the Management Shell by using either of the following procedures. Each procedure loads the Recovery Manager for Active Directory Management Shell snap-in into Windows PowerShell. If you do not load the Recovery Manager for Active Directory Management Shell snap-in before you run a command (cmdlet) provided by that snap-in, you will receive an error.

**NOTE**

Verify that the user account under which you run Recovery Manager for Active Directory Management Shell console has the **Write** permission to the **%ProgramData%\Quest\Recovery Manager for Active Directory** folder. Otherwise, you will get warning messages when you run the snap-in cmdlets.

## **To open the Management Shell**

1. Start Windows PowerShell.

You can do so by running the **powershell** command at a command prompt (Cmd.exe).

2. At the Windows PowerShell prompt, enter the following command: `Add-PSSnapin Quest.RecoveryManager.AD.*`

Alternatively, you can complete the following steps related to your version of Windows:

On the **Start** screen, click the **Management Shell** tile.

Upon the shell start, the console may present you with a message stating that a certain file published by Quest is not trusted on your system. This security message indicates that the certificate the file is digitally signed with is not trusted on your computer, so the console requires you to enable trust for the certificate issuer before the file can be run. Press either R (Run once) or A (Always run). To prevent this message from appearing in the future, it is advisable to choose the second option (A).

# Getting Help

The Recovery Manager for Active Directory Management Shell uses the Windows PowerShell help cmdlets to assist you in finding the appropriate information to accomplish your task. The following table provides some examples of how to use the **Get-Help** and **Get-Command** cmdlets to access the help information that is available for each cmdlet in the Recovery Manager for Active Directory Management Shell.

## **Get-Help**

When you use **Get-Help** without any parameters, you are presented with basic instructions on how to use the help system in Windows PowerShell, including Help for the Recovery Manager for Active Directory Management Shell.

## **Get-Help**

When you use **Get-Help** with the name of a cmdlet as an argument, you are presented with the help information for that cmdlet. For example, to retrieve the help information for the **Get-RMADCollection** cmdlet, use the following command:

```
Get-Help Get-RMADCollection
```

## **Get-Command**

**Get-Command** without any parameters lists all the cmdlets that are available to the shell. You can use the **Get-Command** cmdlet with the **Format-List** or **Format-Table** cmdlet to provide a more readable display. For example, use **Get-Command | Format-List** to display the output in a list format. To display a list of all the Recovery Manager for Active Directory Management Shell cmdlets that are available to the shell, use the following syntax:

```
Get-Command *RMAD*
```

## **Get-Command**

When you use **Get-Command** with the name of a cmdlet as an argument, you are presented with information about the parameters and other components of that cmdlet. The <Cmdlet> entry allows for wildcard character expansion. For example, to retrieve information about the cmdlets with the names ending in **Member**, you can use the following command:

```
Get-Command *Member
```

# Descriptions of PowerShell commands

## PowerShell cmdlets for Recovery Manager for Active Directory

| Cmdlet                     | Description  |
|----------------------------|--|
| Add-RMADBackup             | Registers a backup in the Recovery Manager database.   |
| Add-RMADCollectionItem     | Adds a new item to a Computer Collection.  |
| Add-RMADReplicationConsole | Adds a RMAD console as a replication source.   |
| Add-RMADStorageServer      | Adds a secure storage server, optionally remotely installs a storage server agent.   |
| Backup-RMADCollection      | Backs up an existing computer collection.  |
| Compare-RMADObject         | Compares Active Directory objects. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA). |
| Convert-RMADBackup         | Converts Windows Server backups into RMAD Bare Metal Recovery backups.   |

| Cmdlet                         | Description   |
|--------------------------------|---|
| ConvertTo-RMADRecycledObject   | Recycles specific deleted Active Directory objects.   |
| Create-RMADStorageAgentSetup   | Creates storage server agent setup.   |
| Expand-RMADBackup              | Extracts the contents of a specified backup file.   |
| Export-RMADBackup              | Exports registration information for a backup into an .xml file.  |
| Export-RMADSecureStorageBackup | Exports a backup on a Secure Storage server to a remote network share.  |
| Get-RMADBackup                 | Gets backups registered with Recovery Manager.  |
| Get-RMADBackupAgent            | Retrieves objects that represent Recovery Manager Backup Agents, or discovers manually preinstalled Recovery Manager Backup Agents. |
| Get-RMADBackupInfo             | Gets the content of the backups held at a specified location.   |
| Get-RMADBackupObject           | Get objects from backups  |
| Get-RMADBackupSecurityStatus   | Gets security check information for a specified backup.   |
| Get-RMADCollection             | Retrieves Recovery Manager computer collection objects or default computer collection settings.                                     |
| Get-RMADCollectionItem         | Retrieves information about items added to specified Recovery Manager for Active Directory computer collections.                    |
| Get-RMADDeletedObject          | Retrieves deleted Active Directory objects.   |
| Get-RMADGlobalOptions          | Sets global settings for the application.   |
| Get-RMADLicenseInfo            | Retrieves information about the installed license key file.   |
| Get-RMADObject                 | Retrieves specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory.          |
| Get-RMADReplicationConsole     | Gets all the RMAD consoles in the replication console list.   |
| Get-RMADReplicationSchedule    | Allows you to get the replication schedule from a specified computer.   |
| Get-RMADReplicationSession     | Retrieves information about replication sessions.   |
| Get-RMADReplicationSessionItem | Retrieves a list of remote consoles that are involved in the specified replication session.   |
| Get-RMADReportObject           | Retrieves an object representing the online comparison or restore operation item.   |
| Get-RMADReportObjectAttributes | Retrieves an object representing the online comparison or restore operation item attributes.  |
| Get-RMADReportObjectChildren   | Retrieves an object representing the online comparison or restore operation item child items.                                       |
| Get-RMADReportSession          | Retrieves an object representing the online comparison or restore operation report.   |

| Cmdlet                            | Description   |
|-----------------------------------|---|
| Get-RMADSession                   | Retrieves an object representing Recovery Manager backup sessions.  |
| Get-RMADSessionItem               | Gets items from a specified backup creation session.  |
| Get-RMADSessionItemEvent          | Gets events from a specified backup creation session item.  |
| Get-RMADStorageServer             | Returns a list of registered secure storage servers.  |
| Import-RMADBackup                 | Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects.             |
| Install-RMADBackupAgent           | Installs Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.             |
| New-RMADCollection                | Creates a new computer collection.  |
| New-RMADSchedule                  | Creates a schedule for the backup creation operation you want to perform on a particular computer collection.                       |
| Protect-RMADSecureStorageServer   | Enables storage server hardening.   |
| Publish-RMADBackupSecurityStatus  | Publishes security check information for a specified backup.  |
| Refresh-RMADStorageServer         | Refreshes current information of the secure storage server.   |
| Register-RMADSecureStorageBackups | Registers backups on an existing secure storage server in a Recovery Manager database.  |
| Remove-RMADBackup                 | Allows you to selectively unregister backups from the Recovery Manager backup registration database.                                |
| Remove-RMADBackupAgent            | Removes Recovery Manager Backup Agent from a specified computer, or its registration information from the Recovery Manager Console. |
| Remove-RMADCollection             | Deletes specified Computer Collections.   |
| Remove-RMADCollectionItem         | Removes items from a specified Computer Collection.   |
| Remove-RMADReplicationConsole     | Removes an RMAD console from the replication console list.  |
| Remove-RMADReplicationSchedule    | Allows you to remove the replication schedule from a specified computer.  |
| Remove-RMADReplicationSession     | Deletes replication sessions from the replication history.  |
| Remove-RMADStorageServer          | Removes the secure storage server.  |
| Remove-RMADUnpackedComponent      | Allows you to delete components (data) unpacked from specified backups.   |
| Rename-RMADCollection             | Renames a computer collection.  |

| Cmdlet                       | Description  |
|------------------------------|--|
| Restore-RMADDeletedObject    | Restores deleted Active Directory objects. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).       |
| Restore-RMADDomainController | Restores a domain controller from backup.  |
| Restore-RMADObject           | Restores Active Directory objects from a backup. This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA). |
| Set-RMADCollection           | Sets properties for a computer collection.   |
| Set-RMADGlobalOptions        | Sets global application settings   |
| Set-RMADReplicationConsole   | Sets replication properties of consoles in the replication console list.   |
| Set-RMADReplicationSchedule  | Sets replication schedules for a computer.   |
| Start-RMADReplication        | Performs replication from other computers in the replication console list.   |
| Start-RMADReportViewer       | Displays a report about the results of the online comparison or restore operation.   |
| Test-RMADSecureStorageBackup | Checks the integrity of a backup on the secure storage server.   |
| Update-RMADBackupAgent       | Upgrades Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.                        |
| Update-RMADLicense           | Updates license key file.  |

## PowerShell cmdlets for Recovery Manager for Active Directory Forest Edition (Disaster Recovery Edition)

| Cmdlet                           | Description  |
|----------------------------------|--|
| Add-RMADFECloudStorage           | Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage. |
| Close-RMADFEProject              | Closes currently opened recovery project.  |
| Copy-RMADFEBackup                | Copies a backup from a network share to the secure storage server.   |
| Export-RMADFECloudStorageBackup  | Download a backup file from cloud storage and save it locally.   |
| Export-RMADFERecoveryCertificate | Exports Forest Recovery certificates.  |
| Export-RMADFEResult              | Export the verification result of an RMADFE project.   |
| Get-RMADFEAvailableSubnet        | For internal use only.   |
| Get-RMADFECloudStorage           | Returns cloud storage registered in Recovery Manager for Active Directory.   |

| Cmdlet                                 | Description   |
|--|---|
| Get-RMADFECloudStorageCollection       | Returns computer collections for the cloud storage registered in Recovery Manager for Active Directory.                         |
| Get-RMADFECloudStorageUploadSession    | Retrieves the cloud storage upload session details.   |
| Get-RMADFEComputer                     | Retrieves a list of computer settings from the current RMADFE project.  |
| Get-RMADFEConsole                      | Gets all registered RMAD FE consoles.   |
| Get-RMADFEDnsCache                     | Returns cached DNS records in the Forest Recovery project.  |
| Get-RMADFEDomain                       | Retrieves the domain settings.  |
| Get-RMADFEEvent                        | Returns recovery events related to the entire Active Directory forest or a specific domain controller.                          |
| Get-RMADFEGlobalOptions                | Gets global application settings.   |
| Get-RMADFEOperation                    | Returns information about the progress of the recovery operations.  |
| Get-RMADFEPersistenceConnection        | Gets persistence connection settings.   |
| Get-RMADFEProject                      | Gets the current status of the RMADFE project.  |
| Get-RMADFERecoveryAgent                | Returns information about Forest Recovery Agents that are installed and registered in Forest Recovery Console.                  |
| Get-RMADFESchedule                     | Gets a schedule for the RMADFE project verification.  |
| Import-RMADFERecoveryCertificate       | Imports Forest Recovery certificates.   |
| Install-RMADFERecoveryAgent            | Installs Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.                     |
| New-RMADFEProject                      | Creates a new RMADFE project in the file system.  |
| New-RMADFERecoveryMedia                | Creates a new Recovery Media ISO in the file system.  |
| Open-RMADFEProject                     | Opens the RMADFE project.   |
| Remove-RMADFECloudStorage              | Removes a registered cloud storage from Recovery Manager for Active Directory.  |
| Remove-RMADFECloudStorageUploadSession | Removes an existing cloud storage upload session.   |
| Remove-RMADFERecoveryAgent             | Removes Forest Recovery Agent from a specified domain controller, or its registration information from Forest Recovery Console. |
| Remove-RMADFESchedule                  | Removes an existing verification schedule for the RMADFE project.   |

| Cmdlet                                  | Description   |
|---|---|
| Restart-RMADFECloudStorageUploadSession | Restart a failed or canceled cloud storage upload session.  |
| Resume-RMADFERecovery                   | Resumes recovery process.   |
| Save-RMADFEProject                      | Saves the RMADFE project.   |
| Set-RMADFECloudStorage                  | Updates cloud storage in the Recovery Manager.  |
| Set-RMADFECloudStorageCollection        | Configure a computer collection to use a registered cloud storage.                                  |
| Set-RMADFEComputer                      | Applies computer settings to the RMADFE project.  |
| Set-RMADFEDnsCache                      | Updates cached DNS records in the Forest Recovery project.  |
| Set-RMADFEDomain                        | Sets the domain settings for the current RMADFE project.  |
| Set-RMADFEGlobalOptions                 | Sets global settings for recovery projects.   |
| Set-RMADFEPersistenceConnection         | Sets persistence connection settings.   |
| Set-RMADFERecoveryMode                  | Sets recovery mode for the current recovery project   |
| Set-RMADFESchedule                      | Applies settings to the verification schedule for the RMADFE project.                               |
| Start-RMADFERecovery                    | Performs the restore operation for the RMADFE project.  |
| Start-RMADFERecoveryAgentOperation      | Starts so-called agent operation on the remote machine where Forest Recovery agent is installed.    |
| Start-RMADFEVerification                | Performs verification of the RMADFE project.  |
| Stop-RMADFECloudStorageUploadSession    | Cancel queued or running cloud storage upload session.  |
| Stop-RMADFEWorkflow                     | Stops the verification or recovery workflow of the recovery project.                                |
| Update-RMADFEProject                    | Shows the difference between the current project and live Active Directory and updates the project. |

## PowerShell cmdlets for Recovery Manager for Active Directory Disaster Recovery Edition Secure Storage Server

| Cmdlet                               | Description  |
|--------------------------------------|--|
| Get-RMADStorageServerAllowedVolumes  |  |
| Get-RMADStorageServerHardeningStatus | Retrieves the hardening status of the current server.        |
| Get-RMADStorageServerRetentionPolicy | Retrieves the retention policy status of the current server. |

| Cmdlet                               | Description   |
|--------------------------------------|---|
| Protect-RMADStorageServer            | Enable storage server hardening.                        |
| Set-RMADStorageServerAllowedVolumes  |   |
| Set-RMADStorageServerRetentionPolicy | Sets the retention policy status of the current server. |
| Unprotect-RMADStorageServer          | Disables hardening on the storage server.               |

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
 Module Name: Quest.RecoveryManager.AD.PowerShell  
 online version:

## schema: 2.0.0

# Add-RMADBackup

## SYNOPSIS

Registers a backup in the Recovery Manager database.

## SYNTAX

### BackupInfo

```
Add-RMADBackup [-InputObject] <BackupInfo[]> [-SkipAlreadyRegistered] [-  

  BackupPassword <SecureString>]  

  [-UseLegacyEncryption] [-IgnoreReadOnly] [<CommonParameters>]
```

### Bkf

```
Add-RMADBackup [-Path] <String[]> [-BackupPassword <SecureString>] [-  

  UseLegacyEncryption] [-IgnoreReadOnly]  

  [<CommonParameters>]
```

### OfflineDit

```
Add-RMADBackup [-Path] <String[]> [-SysvolPath <String[]>] [-ResolveIndexes  

<Boolean>] [-OfflineDit]  

  [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Registers specified backup in the Recovery Manager database.  
 Use the -InputObject parameter to specify the backup to register.

# EXAMPLES

## Example

```
PS C:\> $b = Get-ChildItem "C:\Backups" -Filter *.bkf -Recurse | Get-RMADBackupInfo
```

```
C:\PS>Add-RMADBackup $b
```

The first line of this example gets the backups held in the C:\Backups folder and its subfolders, and saves the backup objects in the \$b variable.

The second line of this example registers the backup objects in the Recovery Manager database.

# PARAMETERS

## -BackupPassword

Specifies the password to access a password-protected backup.

This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString

Parameter Sets: BackupInfo, Bkf

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -InputObject

Accepts a backup object as input to the cmdlet.

Enter a variable that contains the objects or type a command or expression that gets the objects.

Type: BackupInfo[]

Parameter Sets: BackupInfo

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-OfflineDit**

Specifies that the application registers the DIT file as a backup.

Type: SwitchParameter  
Parameter Sets: OfflineDit  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Path**

Path to the backup file.

Type: String[]  
Parameter Sets: Bkf, OfflineDit  
Aliases: FullName

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## **-ResolveIndexes**

Resolve the DIT file index.

Type: Boolean  
Parameter Sets: OfflineDit  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SkipAlreadyRegistered**

Do not display the error message if the backup is registered.

Type: SwitchParameter  
Parameter Sets: BackupInfo  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SysvolPath**

Path to the SYSVOL folder.

Type: String[]  
Parameter Sets: OfflineDit  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-UseLegacyEncryption**

Allows you to work with backups encrypted by the RC4 algorithm from RSA, Inc. (Microsoft RSA Base Provider). This algorithm is used to back up Windows Server 2003/2003 R2 domain controllers in Recovery Manager for Active Directory 8.2.x and 8.5.x.

Type: SwitchParameter  
Parameter Sets: BackupInfo, Bkf  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Add-RMADCollectionItem**

## **SYNOPSIS**

Adds a new item to a Computer Collection.

# SYNTAX

## InputObject

```
Add-RMADCollectionItem [-InputObject] <ComputerCollection> [-  
DomainController <String>] [-Domain <String>]  
[-OU <String>] [-Container <String>] [-ADSite <String>] [-AdamSite  
<String>] [-AdamServer <String>]  
[-AdamHost <String>] [-Exclusions <String[]>] [-Credentials  
<PSCredential>] [-IgnoreReadOnly]  
[<CommonParameters>]
```

## Name

```
Add-RMADCollectionItem -Name <String> [-DomainController <String>] [-Domain  
<String>] [-OU <String>]  
[-Container <String>] [-ADSite <String>] [-AdamSite <String>] [-AdamServer  
<String>] [-AdamHost <String>]  
[-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly]  
[<CommonParameters>]
```

## Id

```
Add-RMADCollectionItem -Id <Int32> [-DomainController <String>] [-Domain  
<String>] [-OU <String>]  
[-Container <String>] [-ADSite <String>] [-AdamSite <String>] [-AdamServer  
<String>] [-AdamHost <String>]  
[-Exclusions <String[]>] [-Credentials <PSCredential>] [-IgnoreReadOnly]  
[<CommonParameters>]
```

## Domain

```
Add-RMADCollectionItem [-Domain <String>] [-Exclusions <String[]>] [-  
IgnoreReadOnly] [<CommonParameters>]
```

## OU

```
Add-RMADCollectionItem [-OU <String>] [-Exclusions <String[]>] [-  
Credentials <PSCredential>] [-IgnoreReadOnly]  
[<CommonParameters>]
```

## Container

```
Add-RMADCollectionItem [-Container <String>] [-Exclusions <String[]>] [-  
Credentials <PSCredential>]  
[-IgnoreReadOnly] [<CommonParameters>]
```

## ADSite

```
Add-RMADCollectionItem [-ADSite <String>] [-Exclusions <String[]>] [-  
Credentials <PSCredential>]  
[-IgnoreReadOnly] [<CommonParameters>]
```

## AdamServer

```
Add-RMADCollectionItem [-AdamSite <String>] [-AdamServer <String>] [-  
Credentials <PSCredential>]  
[-IgnoreReadOnly] [<CommonParameters>]
```

## **AdamSite**

```
Add-RMADCollectionItem [-AdamSite <String>] [-Exclusions <String[]>] [-  
Credentials <PSCredential>]  
[-IgnoreReadOnly] [<CommonParameters>]
```

## **DESCRIPTION**

Adds a new item to the Computer Collection that has the specified name or is represented by the specified objects.

## **EXAMPLES**

### **Example 1**

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -DomainController  
dc1.dom1.local
```

Adds the dc1.dom1.local domain controller to the computer collection named Collection1.

### **Example 2**

```
PS C:\> $c = Get-RMADCollection Collection1  
  
C:\PS>Add-RMADCollectionItem -InputObject $c -Domain dom1.local
```

In the first line of this example, the Get-RMADCollection cmdlet gets the computer collection object named Collection1 and saves it in the \$c variable.

In the second line, the Add-RMADCollection cmdlet adds the dom1.local domain to the Computer Collection object saved in the \$c variable.

### **Example 3**

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -OU  
"OU=Tokens,OU=Defender,DC=prod,DC=quest,DC=corp"
```

Adds an OU to the Computer Collection.

### **Example 4**

```
PS C:\> Add-RMADCollectionItem -Name Collection1 -Container  
"CN=Computers,DC=prod,DC=quest,DC=corp"
```

Adds a container to the Computer Collection.

### **Example 5**

```
PS C:\> $dn = "CN=Default-First-Site-  
Name,CN=Sites,CN=Configuration,DC=prod,DC=quest,DC=corp"  
Add-RMADCollectionItem -Name Collection1 -ADSite $dn -Exclusions  
@("ws1.prod.quest.corp:0")
```

Create an ADSite exclude from the domain controller (ws1.prod.quest.corp:0") and add it to the Computer Collection.

### **Example 6**

```
PS C:\> $dn = "CN=Default-First-Site-  
Name,CN=Sites,CN=Configuration,CN={7B1308BE-06B9-4925-BEF5-C323292279F5}"  
Add-RMADCollectionItem -Name Collection1 -AdamServer  
ws1.prod.quest.corp:389 -AdamSite dn
```

Create an AdamSite and add it to the Computer Collection.

## PARAMETERS

### -AdamHost

Specifies the name of the server for the AD LDS instance installation.

Type: String  
Parameter Sets: InputObject, Name, Id  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -AdamServer

Name of the AD LDS instance.

Type: String  
Parameter Sets: InputObject, Name, Id, AdamServer  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -AdamSite

Specifies the distinguished name of the ADAM/AD LDS site to be added to the Computer Collection.  
Use it in conjunction with AdamServer.

Type: String  
Parameter Sets: InputObject, Name, Id, AdamServer, AdamSite  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -ADSite

Specifies the distinguished name of the Active Directory site to be added to the Computer Collection.

Type: String  
Parameter Sets: InputObject, Name, Id, ADSite  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Container**

Specifies the distinguished name of the container to be added to the Computer Collection.

Type: String

Parameter Sets: InputObject, Name, Id, Container

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Credentials**

Specifies the credentials for the account with which you want to connect.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential

Parameter Sets: InputObject, Name, Id, OU, Container, ADSite, AdamServer,

AdamSite

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Domain**

Specifies the DNS name of the domain to be added to the Computer Collection.

Type: String

Parameter Sets: InputObject, Name, Id, Domain

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-DomainController**

Specifies the DNS name of the domain controller to be added to the Computer Collection.

Type: String

Parameter Sets: InputObject, Name, Id

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Exclusions**

Excludes a specified domain controller from the collection items to be added.

The parameter must be used in conjunction with other parameters.

Type: String[]

Parameter Sets: InputObject, Name, Id, Domain, OU, Container, ADSite, AdamSite  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Id**

Specifies the identifier of the Computer Collection to which you want to add items.

Type: Int32  
Parameter Sets: Id  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-InputObject**

Specifies the object representing the Computer Collections to which you want to add items.  
Enter a variable that contains the objects or type a command or expression that gets the objects.

Type: ComputerCollection  
Parameter Sets: InputObject  
Aliases: Collection

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **-Name**

Specifies the name of the Computer Collection to which you want to add items.

Type: String  
Parameter Sets: Name  
Aliases:

Required: True  
Position: Named

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -OU

Specifies the distinguished name of the organizational unit to be added to the Computer Collection.

```
Type: String  
Parameter Sets: InputObject, Name, Id, OU  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Add-RMADFECloudStorage

## SYNOPSIS

Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage.

## SYNTAX

```
Add-RMADFECloudStorage -Name <String> -Container <String> -ConnectionString <String> -Type <CLOUD_STORAGE_TYPE>
```

```
[-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Registers a cloud storage in the Recovery Manager for Active Directory database, allowing backups to be copied to cloud storage.

Use the Connection String parameter to securely connect to the cloud storage and specify the type of storage using the Type parameter.

## EXAMPLES

### Example 1

```
PS C:\> Add-RMADFECloudStorage -Name "MyStorage" -ConnectionString "..." -Container "MyContainer" -Type CloudStorageAzure
```

Registers the Azure Blob Storage container named MyContainer in Recovery Manager for Active Directory.

## PARAMETERS

### -ConnectionString

Full connection string for the cloud storage to be registered in Recovery Manager for Active Directory.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -Container

Name of container in storage account. Backups will be copied to this location.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Name**

Cloud storage display name for the registered storage in Recovery Manager for Active Directory.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Type**

Storage type - Azure Blob Storage or Amazon S3 Storage.

```
Type: CLOUD_STORAGE_TYPE  
Parameter Sets: (All)  
Aliases:  
Accepted values: CloudStorageAzure, CloudStorageAmazon
```

```
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**None**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Add-RMADReplicationConsole

## SYNOPSIS

Adds a RMAD console as a replication source.

## SYNTAX

```
Add-RMADReplicationConsole [-ComputerName] <String> [-Mode]
<ReplicationMode>
[-AccessCredential <PSCredential>] [-FallbackCredential <PSCredential>]
[<CommonParameters>]
```

## DESCRIPTION

RMAD console can synchronize the backups, collections, global options, schedules, Secure Storage servers and backups stored on Secure Storage servers from the consoles in the replication console list manually or on schedule.

## EXAMPLES

### Example 1

```
PS C:\> C:\>$credential = Get-Credential
C:\>Add-RMADReplicationConsole Hostname1 -AccessCredential $credential -Mode Backups
```

This command adds the RMAD console on Hostname1 to the replication console list with the Backups mode enabled.

### Example 2

```
PS C:\> C:\>Add-RMADReplicationConsole -ComputerName Hostname1 -Mode Full
```

This command adds the RMAD console on Hostname1 to the replication console list with the Full mode enabled.

### Example 3

```
PS C:\> C:\>$fallbackAccount = Get-Credential
C:\>Add-RMADReplicationConsole -ComputerName Hostname1 -Mode Full -FallbackCredential $fallbackAccount
```

This command adds the RMAD console on Hostname1 to the replication console list with the Full mode enabled and with the specified fallback account.

## PARAMETERS

### -AccessCredential

Specifies the user credentials to read data from the target computer.  
The user must be a local Administrator on the target computer.

To obtain the user credentials, create a PSCredential object using the Get-Credential cmdlet provided by Windows PowerShell.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ComputerName**

Specifies the hostname of the computer on which the RMAD console you want to add is installed.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-FallbackCredential**

Supplies a fallback account for replacing the account that is used by the backup schedule task.

The account must have administrator privileges on the system(s) to be backed up.

You can use this parameter only when Full mode is specified for the console.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Mode**

Specifies the console mode: Full (to replicate backups, collections, global options and schedule) or Backups (to replicate backups only).

Type: ReplicationMode  
Parameter Sets: (All)  
Aliases:  
Accepted values: Full, Backups

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Add-RMADStorageServer

## SYNOPSIS

Adds a secure storage server, optionally remotely installs a storage server agent.

## SYNTAX

```
Add-RMADStorageServer [-Name] <String> [-Port <Int32>] [-Credential <PSCredential>] [-RegisterBackups] [-InstallAgent] [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Registers a secure storage server in Recovery Manager for Active Directory.

## EXAMPLES

### Example 1

```
PS C:\> Add-RMADStorageServer -Name "backupsrv01.acme.test" -Port 48001
```

Registers the secure storage server with given name and connection port.

# PARAMETERS

## -Credential

Server credentials used for remote agent installation. Ignored if the '-InstallAgent' switch is not set.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -InstallAgent

If set, automatically installs storage server agent.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Name

DNS name or IP address of the server.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -Port

Port used to connect to the secure storage agent.

Type: Int32

Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-RegisterBackups**

If set, backups on an existing storage server will be registered.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.String**

## **OUTPUTS**

**IStorageServer**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Backup-RMADCollection

## SYNOPSIS

Backs up an existing computer collection.

## SYNTAX

### InputObject

```
Backup-RMADCollection [-InputObject] <ComputerCollection> [-AsJob] [-IgnoreReadOnly] [<CommonParameters>]
```

### Name

```
Backup-RMADCollection [-Name] <String> [-AsJob] [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Backs up the existing computer collection that has the specified name or is represented by the specified objects.

## EXAMPLES

### Example 1

```
PS C:\> Backup-RMADCollection -Name "Collection1"
```

Backs up the Computer Collection named Collection1.

### Example 2

```
PS C:\> Get-RMADCollection -Id 1 | Backup-RMADCollection
```

Gets the Computer Collection whose identifier is 1, and then backs up that Computer Collection.

### Example 3

```
PS C:\> $c = Get-RMADCollection -Name col
```

```
C:\PS>Backup-RMADCollection -InputObject $c -AsJob
```

In the first line of this command, the Get-RMADCollection cmdlet gets the computer collection named col. The computer collection object is then stored in the \$c variable.

## PARAMETERS

### -AsJob

Runs the command as a background job.

You can use this parameter to run commands that take a significant time to complete.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-InputObject**

Backs up the existing Computer Collection represented by the specified collection object.  
Enter a variable that contains the object or type a command or expression that gets the object.

```
Type: ComputerCollection
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **-Name**

Specifies the name of the existing Computer Collection to be backed up.

```
Type: String
Parameter Sets: Name
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Close-RMADFEProject

## SYNOPSIS

Closes currently opened recovery project.

## SYNTAX

```
Close-RMADFEProject [<CommonParameters>]
```

## DESCRIPTION

This cmdlet allows you to close previously opened recovery project in the current PowerShell session.

## EXAMPLES

### Example 1

```
PS C:\> Close-RMADFEProject
```

Closes currently opened by Open-RMADFEProject recovery project.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Compare-RMADObject

## SYNOPSIS

Compares Active Directory objects.

This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

## SYNTAX

### Default (Default)

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
    [-Credential <PSCredential>] [-Backup <Guid>] [-Backup1 <Guid>] [-Backup2 <Guid>]
    [-Backup1Password <SecureString>] [-Backup2Password <SecureString>] [-KeepBackupUnpacked] [-Id <String[]>]
    [-ProcessChildren] [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-ReportUnchangedObjects]
    [-SQLCredential <PSCredential>] [-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor]
    [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly]
    [<CommonParameters>]
```

### ADAndBackup

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
    [-Credential <PSCredential>] -Backup <Guid> [-BackupPassword <SecureString>] [-KeepBackupUnpacked]
    [-Id <String[]>] [-ProcessChildren] [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes]
    [-ReportUnchangedObjects] [-SQLCredential <PSCredential>] [-ChangeAuditorDbName <String>]
```

```
[-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## ADLds

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword <SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes]
[-ReportUnchangedObjects] [-SQLCredential <PSCredential>] [-AdLds] [-AdLdsInstance <String>
[-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>]
[-IgnoreReadOnly] [<CommonParameters>]
```

## Firewall

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword <SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-ReportUnchangedAttributes]
[-ReportUnchangedObjects] [-SQLCredential <PSCredential>] [-AdLds] [-ChangeAuditorDbName <String>]
[-ConfigureFirewall] [-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]
```

## Agentless

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
[-Credential <PSCredential>] [-Backup <Guid>] [-BackupPassword <SecureString>] [-KeepBackupUnpacked]
[-Id] <String[]> [-UseAgentlessMethod] [-ProcessChildren] [-ChildObjectClass <String[]>]
[-ReportUnchangedAttributes] [-ReportUnchangedObjects] [-SQLCredential <PSCredential>] [-AdLds]
[-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor] [-Partition <String>] [-Port <Int32>]
[-IgnoreReadOnly] [<CommonParameters>]
```

## TwoBackups

```
Compare-RMADObject [-ProcessRecycledObjects] [-Attribute <String[]>] [-Server <String>]
[-Credential <PSCredential>] -Backup1 <Guid> -Backup2 <Guid> [-Backup1Password <SecureString>]
[-Backup2Password <SecureString>] [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor]
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to compare the following:<sup>\*</sup> Live Active Directory objects against their versions in a backup.

- Active Directory objects held in two backups. To fill in the 'ModifyBy' field for a report, use the ChangeAuditorDbName parameter. To view a report about the compare operation performed by this cmdlet, use the Start-RMADReportViewer cmdlet.  
You can only use this cmdlet when Windows PowerShell is started using MTA.  
To start Windows PowerShell using MTA, run this command: PowerShell -mta

## EXAMPLES

### Example

```
PS C:\> $b = (Get-RMADBackup -Domain dom1.local | Sort-Object -Property Date) [-1]
C:\PS>Compare-RMADObject -Backup $b.Path -Id "ou=ou1,dc=dom1,dc=local" -ProcessChildren -ChangeAuditorDbName ".\ChangeAuditor"
```

In this example, the Get-RMADBackup cmdlet gets all backups existing for the dom1.local domain.

## PARAMETERS

### -AdLds

Specifies that the AD LDS instance is used as a data storage.

Type: SwitchParameter

Parameter Sets: ADLds

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: Firewall, Agentless

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -AdLdsInstance

If you compare the object changes in AD LDS (ADAM), you should specify the AD LDS (ADAM) instance whose backup you want to use.

Type: String

Parameter Sets: ADLds

Aliases: AdamInstance

Required: True

Position: Named

Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Attribute

Specifies the display names of the object attributes to compare.  
When specifying multiple display names, use a comma as a separator.

```
Type: String[]  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Backup

Specifies the backup that contains the AD objects to be compared.  
Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory.

```
Type: Guid  
Parameter Sets: Default, ADLds, Firewall, Agentless  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: Guid  
Parameter Sets: ADAndBackup  
Aliases:
```

```
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Backup1

Specifies the first backup that contains the AD objects to be compared.  
Use this parameter if you want to compare AD objects held in backups.  
The backup specified in this parameter must be registered in the Recovery Manager database.

```
Type: Guid  
Parameter Sets: Default  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: Guid  
Parameter Sets: TwoBackups  
Aliases:
```

```
Required: True
```

```
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Backup1Password**

Specifies the password to access the first backup, if the backup is password-protected.  
This is the same password that is set for the backup in the Recovery Manager console.

```
Type: SecureString
Parameter Sets: Default, TwoBackups
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Backup2**

Specifies the second backup that contains the AD objects to be compared.  
Use this parameter if you want to compare AD objects held in backups.  
The backup specified in this parameter must be registered in the Recovery Manager database.

```
Type: Guid
Parameter Sets: Default
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
Type: Guid
Parameter Sets: TwoBackups
Aliases:
```

```
Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Backup2Password**

Specifies the password to access the second backup, if the backup is password-protected.  
This is the same password that is set for the backup in the Recovery Manager console.

```
Type: SecureString
Parameter Sets: Default, TwoBackups
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-BackupPassword**

Specifies the password to access a password-protected backup.

This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString

Parameter Sets: ADAndBackup, ADLds, Firewall, Agentless

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ChangeAuditorDbName**

Specifies a location of the ChangeAuditor SQL database.

If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ChildObjectClass**

Specifies the child object classes to process.

When specifying multiple classes, use a comma as a separator.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ConfigureFirewall**

Specifies whether Recovery Manager automatically configures Windows Firewall on the target Windows Server 2008-based or Windows Server 2012-based DCs to allow compare and restore operations.

Type: SwitchParameter

Parameter Sets: Firewall

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Credential**

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter. Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory.

If this parameter is omitted, the credentials of current user account are used.

This parameter is ignored if you compare AD objects in a backup with their counterparts in another backup.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Id**

Specifies the objects to compare.

To specify an object, you can use object GUID, distinguished name (DN), sAMAccountName, or user principal name (UPN).

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-KeepBackupUnpacked**

Determines whether to save the unpacked backup after the search operation.

If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Partition**

Specifies the AD LDS (ADAM) partition where you want to compare objects.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Port**

Specifies the port on which to access the AD LDS (ADAM) instance that hosts the objects you want to compare.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ProcessChildren**

When present, specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ProcessRecycledObjects**

When present, specifies to process recycled objects.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ReportUnchangedAttributes**

Includes the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ReportUnchangedObjects**

Includes the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-RestoreUsingChangeAuditor**

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Server**

Specifies the domain controller or ADAM instance host from which objects are to be retrieved.

The domain controller can be specified by its computer name, IP address, or domain name.

If you specify a domain name, deleted objects are retrieved from any available domain controller in the specified domain.

The ADAM instance host can be specified by its computer name or IP address.

If this parameter is omitted, objects are retrieved from any available domain controller in the current domain.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SQLCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report about the compare operation.

The user name and password must be in the form of a PSCredential object.

When this parameter is omitted, the cmdlet uses the credentials of the account under which Management Shell is running.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-UseAgentlessMethod**

Specifies to use the agentless method to access a domain controller.  
Use this parameter if you want to compare AD objects in a backup with their counterparts in Active Directory.  
If this parameter is omitted, the domain controller is accessed by using Restore Agent.  
This parameter is ignored if you compare AD objects in a backup with their counterparts in another backup.

Type: SwitchParameter  
Parameter Sets: Agentless  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

The Backup 1 and Backup 2 parameters must specify backups for the same domain controller. In the DomainController parameter, you must specify the same domain controller whose backup you specified in the Backup parameter.

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Convert-RMADBackup

## SYNOPSIS

Converts Windows Server backups into RMAD Bare Metal Recovery backups.

## SYNTAX

```
Convert-RMADBackup [-WindowsServerBackupLocation] <String> [-  
BareMetalRecoveryPath] <String> [-AsJob]  
[<CommonParameters>]
```

## DESCRIPTION

Converts Windows Server Backups into RMAD Bare Metal Recovery backups.

## EXAMPLES

### Example 1

```
PS C:\> Convert-RMADBackup \\backup_srv01\wsb\WindowsImageBackup  
\\backup_srv01\rmad\bmr.vhdx
```

Synchronously starts the conversion of the Windows Server backup to the bmr.vhdx file located on the network share.

### Example 2

```
PS C:\> Convert-RMADBackup \\backup_srv01\wsb\WindowsImageBackup  
\\backup_srv01\rmad\bmr.vhdx | Add-RMADBackup
```

Synchronously starts the conversion of the Windows Server backup located at the remote network share, puts the result into the bmr.vhdx file, and then registers the resulting backup.

### Example 3

```
PS C:\> $job = Convert-RMADBackup D:\WindowsImageBackup D:\bmr.vhdx -AsJob  
$job.StatusMessage
```

Runs conversion as a background job and shows the current status message.

## PARAMETERS

### -AsJob

Runs the conversion process as a background job.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

```
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-BareMetalRecoveryPath**

Specifies the full path to the RMAD Bare Metal Recovery backup file.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-WindowsServerBackupLocation**

Specifies the full path to the Windows Server backup.

You must specify the path including the WindowsImageBackup folder.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

### **String**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# ConvertTo-RMADRecycledObject

## SYNOPSIS

Recycles specific deleted Active Directory objects.

## SYNTAX

```
ConvertTo-RMADRecycledObject -Name <String[]> [-Force] [-Server <String>]
[-Credential <PSCredential>]
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

## DESCRIPTION

Allows you to manually recycle specific deleted Active Directory objects held in Microsoft's Active Directory Recycle Bin in the forest where Recovery Manager is installed.

This cmdlet overrides the deleted object lifetime setting that applies to the deleted objects being recycled. You can only use this cmdlet if Microsoft's Active Directory Recycle Bin feature is enabled in the forest where Recovery Manager is installed.

## EXAMPLES

### Example 1

```
PS C:\> (Get-RMADDeletedObject dc1.dom1.lab.local) |
Where-Object { $_.objectclass -contains "user" } |
Foreach-Object { ConvertTo-RMADRecycledObject -Name $_.Name -Server
dc1.dom1.lab.local }
```

This example shows how to recycle all user objects held in Microsoft's Active Directory Recycle Bin. The Get-RMADDeletedObject cmdlet gets all deleted objects from Microsoft's Active Directory Recycle Bin by connecting to the dc1.dom1.lab.local domain controller.

Then the Get-RMADDeletedObject cmdlet pipes the objects to the Where-Object cmdlet that filters out user objects.

Then, the Foreach-Object cmdlet uses the ConvertTo-RMADRecycledObject cmdlet to transfer each user object to the recycled state.

### Example 2

```
PS C:\> ConvertTo-RMADRecycledObject -Name "User 1\0ADEL:7dbac5c7-f38d-
4270-8ac2-7a0674bc246b"
```

Converts the deleted object "User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b" to recycled state.

# PARAMETERS

## -Credential

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Force

Suppresses the cmdlet prompt for confirmation.

When this parameter is omitted, the cmdlet prompts you for confirmation before recycling objects.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -Name

Allows you to specify the deleted object you want to recycle.

To specify a deleted object, enter the value of the object's Name attribute in this parameter.

The Name attribute provides the object's relative distinguished name (RDN) that looks similar to the following:

User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b To view the value of the Name attribute for a deleted object, you can use the Get-RMADDeletedObject cmdlet.

Type: String[]  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: Named  
Default value: None

```
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **-Partition**

Specifies the distinguished name of the Active Directory partition from which deleted objects are to be retrieved.  
If this parameter is omitted, the default naming context is used.

This parameter is required if you specify an ADAM instance host in the DirectoryHost parameter.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Port**

Specifies the port number to be used for connection.

If this parameter is set to 0 or not specified, the default LDAP port (389) is used.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Server**

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects.

If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain.

To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address.

If you specify an Active Directory domain name in this parameter, the cmdlet retrieves objects from any available domain controller in the specified domain.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Confirm**

Prompts for a confirmation before executing the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

```
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

### **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## **schema: 2.0.0**

# **Copy-RMADFEBackup**

## **SYNOPSIS**

Copies a backup from a network share to the secure storage server.

## **SYNTAX**

```
Copy-RMADFEBackup -BackupPath <String> [-BackupAccessCredentials
<PSCredential>] -StorageServer <String>
```

```
[ -AgentPort <UInt32> ] [-AsJob] [<CommonParameters>]
```

## DESCRIPTION

Copies a backup from a network share to the secure storage server.  
Backup is pulled from a network share by an agent running on the secure storage server.

## EXAMPLES

### Example 1

```
$credentials = New-Object PSCredential("user", (ConvertTo-SecureString "password" -asPlainText -Force) )  
Copy-RMADFEBackup -StorageServer 'storage' -StorageServerBackupPath 'E:\Backups\DC1.rmad.local\2020-09-10 14-54-49.bkf' -BackupPath '\\fr\backupsnew\DC1.rmad.local\2020-09-10 14-54-49.bkf' -  
BackupAccessCredentials $credentials
```

## PARAMETERS

### -AgentPort

Secure storage agent port

Type: UInt32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -AsJob

Runs the command as a background job.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -BackupAccessCredentials

Network credentials to access the backup stored on BackupPath.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-BackupPath**

Network path to the backup.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-StorageServer**

Secure storage name or IP address.

Assumimg that the Foreset Recovery agent is already installed on secure storage server.

```
Type: String  
Parameter Sets: (All)  
Aliases:
```

```
Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**None**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Create-RMADStorageAgentSetup

## SYNOPSIS

Creates storage server agent setup.

## SYNTAX

```
Create-RMADStorageAgentSetup [-Path] <String> [-Port <Int32>]  
[<CommonParameters>]
```

## DESCRIPTION

Create storage server agent setup bundle packed to the ZIP archive that contains required components to deploy the storage server agent.

## EXAMPLES

### Example 1

```
PS C:\> Create-RMADStorageAgentSetup -Path "C:\Setup.zip" -StorageAgentPort  
48001
```

Creates a setup bundle and puts it in the specified file.

## PARAMETERS

### -Path

Path to the result file in which the setup will be created.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

### -Port

Port that will be used to run storage agent on.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.String**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Expand-RMADBackup

## SYNOPSIS

Extracts the contents of a specified backup file.

## SYNTAX

### BackupInfo (Default)

```
Expand-RMADBackup [-InputObject] <BackupInfo[]> [-BackupPassword  
<SecureString>] [-UseLegacyEncryption]  
[-TargetFolder] <String> [ [-Components] <BackupComponentBits>] [-AsJob]  
[<CommonParameters>]
```

### Bkf

```
Expand-RMADBackup [-Path] <String[]> [-BackupPassword <SecureString>] [-  
UseLegacyEncryption]
```

```
[-TargetFolder] <String> [[-Components] <BackupComponentBits>] [-AsJob]
[<CommonParameters>]
```

## Id

```
Expand-RMADBackup [-Id] <Int32[]> [-BackupPassword <SecureString>] [-
UseLegacyEncryption]
[-TargetFolder] <String> [[-Components] <BackupComponentBits>] [-AsJob]
[<CommonParameters>]
```

# DESCRIPTION

Allows you to selectively extract the contents of a backup file created with Recovery Manager for Active Directory to the location you want.

## EXAMPLES

### Example 1

```
PS C:\> Expand-RMADBackup -InputObject (Get-RMADBackup | where {$_.Date -gt
(Get-Date).AddDays(-2)}) -TargetFolder 'C:\UnpackedBackups'
```

This command extracts the contents of all backups created within last two days to the local folder C:\UnpackedBackups.

## PARAMETERS

### -AsJob

Runs the command as a background job.

You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

### -BackupPassword

If the backup is password-protected, specifies the password to open the backup.

The parameter value must be a SecureString object.

Type: SecureString  
Parameter Sets: (All)  
Aliases: Password

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Components**

Specifies the backup components you want to extract.

When specifying multiple backup components in this parameter, use a comma as a separator.

This parameter accepts the following values for backup components:<sup>\*</sup> Sam - Specifies to extract the SAM registry hive.

- Security - Specifies to extract the Security registry hive.
- Software - Specifies to extract the Software registry hive.
- System - Specifies to extract the System registry hive.
- Default - Specifies to extract the Default registry hive.
- NTUserDat - Specifies to extract the NTUser.dat registry hive.
- Components - Specifies to extract the Components registry hive.
- SchemaDat - Specifies to extract the Schema.dat
- ActiveDirectoryDatabase - Specifies to extract the DIT database.
- Sysvol - Specifies to extract SYSVOL.
- EnterpriseServices - Specifies to extract the COM+ Class Registration database.
- BootFiles - Specifies to extract the boot files.
- IISMetabase - Specifies to extract IIS metabase.
- PerformanceCounters - Specifies to extract performance counters.
- CertificateServer - Specifies to extract certificate server.
- ClusterQuorum - Specifies to extract the cluster quorum.
- Adam - Specifies to extract all instances of AD LDS (ADAM).
- GroupMembership - Specifies to extract cross-domain group membership information.
- ActiveDirectory - Specifies to extract the components represented by the following parameters: ActiveDirectoryDatabase and SYSVOL.
- Registry - Specifies to extract the components represented by the following parameters: Sam, Security, Software, System, Default, NTUserDat, Components, and SchemaDat.

Type: BackupComponentBits

Parameter Sets: (All)

Aliases:

Accepted values: Sam, Security, Software, System, Default, NTUserDat, ActiveDirectoryDatabase, Sysvol, ActiveDirectory, EnterpriseServices, BootFiles, SystemProtectedFiles, BootIni, CertificateServer, IisMetabase, PerformanceCounters, ClusterQuorum, Adam, GroupMembership, BootFilesExt, CryptoKeys, ForestRecoveryMetadata, Components, SchemaDat, Registry, VirtualImage, HardLinks

Required: False

Position: 2

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Id**

Specifies the identifier of the backup you want to extract.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

```
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## -InputObject

Accepts a backup object as input to the cmdlet.  
Enter a variable that contains the object or type a command or expression that gets the object.

```
Type: BackupInfo[]
Parameter Sets: BackupInfo
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## -Path

Path to the backup file.

```
Type: String[]
Parameter Sets: Bkf
Aliases: FullName
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

## -TargetFolder

Specifies the target folder to which you want to extract the backup.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -UseLegacyEncryption

Allows you to work with backups encrypted by the RC4 algorithm from RSA, Inc.  
(Microsoft RSA Base Provider).

This algorithm is used to back up Windows Server 2003/2003 R2 domain controllers in Recovery Manager for Active Directory 8.2.x and 8.5.x.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
```

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Export-RMADBackup

## SYNOPSIS

Exports registration information for a backup into an .xml file.

## SYNTAX

### InputObject

```
Export-RMADBackup [-InputObject] <BackupInfo[]> [-Path] <String> [-PassThru] [<CommonParameters>]
```

### Id

```
Export-RMADBackup [-Id] <Int32[]> [-Path] <String> [-PassThru] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet exports the registration information for the specified backup into an .xml file. You can then use the Import-RMADBackup cmdlet to transform the registration information saved in the .xml file into an object.

# EXAMPLES

## Example 1

```
PS C:\> $b = Get-RMADBackup  
Export-RMADBackup -Path Backups.xml -InputObject $b
```

Exports registration information for all backups registered in the Recovery Manager for Active Directory backup registration database located on the computer where you are using this cmdlet.  
The backup registration information is saved in the Backups.xml file.

## Example 2

```
PS C:\> Export-RMADBackup -Id 1 -Path C:\ExportedBackups
```

Exports the registration information of the backup whose ID 1 to an XML file in the folder C:\ExportedBackups.

# PARAMETERS

## -Id

Specifies the identifiers of one or more backups to export.  
This parameter accepts an array of integers.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -InputObject

Accepts a backup object as input to the cmdlet.  
Enter a variable that contains the object or type a command or expression that gets the object.

Type: BackupInfo[]  
Parameter Sets: InputObject  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -PassThru

Passes the registration information for the specified backup along the pipeline.  
If this parameter is omitted, the registration information is not passed along the pipeline.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Path**

Specifies the path to the .xml file where you want to save registration information for the backup.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## **schema: 2.0.0**

# **Export-RMADFECloudStorageBackup**

## **SYNOPSIS**

Download a backup file from cloud storage and save it locally.

## **SYNTAX**

### **UploadSessionId**

```
Export-RMADFECloudStorageBackup [-UploadSessionId] <Int32> [-Path] <String>  
[<CommonParameters>]
```

## **InputObject**

```
Export-RMADFECloudStorageBackup [-InputObject] <UploadSession> [-Path]
<String> [<CommonParameters>]
```

## **DESCRIPTION**

This cmdlet allows you to download an Active Directory or BMR backup from cloud storage. Use the Path parameter to specify a local path for the download.  
Specify the upload session Id for the UploadSession parameter. The upload session Id can be found in the list of upload sessions for each backup file.

## **EXAMPLES**

### **Example 1**

```
PS C:\> Get-RMADFECloudStorageUploadSession
```

```
Id          : 2
StorageId   : 1
BackupId    : 7143538
SourceBackupPath : \\mycomputer.company.ca\Backups\MyBackup_123456.bkf
TargetBackupPath  : mycomputer.company.ca\Backups\MyBackup_123456.bkf
ErrorMessage   :
CreationTimestamp : 10/28/2021 4:23:47 PM
ModificationTimestamp : 10/28/2021 4:24:17 PM
Status        : UploadStatusCompleted

Id          : 1
StorageId   : 1
BackupId    : 5439573
SourceBackupPath : \\mycomputer.company.ca\Backups\MyBackup_123456.bkf
TargetBackupPath  : mycomputer.company.ca\Backups\MyBackup_123456.bkf
ErrorMessage   :
CreationTimestamp : 10/28/2021 4:14:10 PM
ModificationTimestamp : 10/28/2021 4:14:17 PM
Status        : UploadStatusCompleted
```

```
PS C:\> Export-RMADFECloudStorageBackup -UploadSessionId 2 -Path
C:\Backups\MyBackup_123456.bkf
```

Download the backup file uploaded by the session with Id 2 to the local path specified.

## **PARAMETERS**

### **-InputObject**

Specifies the UploadSession object representing the cloud storage upload session.

Type: UploadSession  
Parameter Sets: InputObject  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## -Path

The full local path for the downloaded backup file.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -UploadSessionId

The Upload session Id for the backup to be downloaded.

Type: Int32

Parameter Sets: UploadSessionId

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Export-RMADFERecoveryCertificate

## SYNOPSIS

Exports Forest Recovery certificates.

## SYNTAX

```
Export-RMADFERecoveryCertificate [-Path] <String> [-Password]
<SecureString> [<CommonParameters>]
```

## DESCRIPTION

This cmdlet exports Forest Recovery certificates to the specified location. You must also supply the password that is used to protect the certificates.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Export-RMADFERecoveryCertificate -Path
C:\Certificates\RMADFeCertificates.pfx" -Password (ConvertTo-SecureString
"protection password" -AsPlainText -Force)
```

This command exports Forest Recovery certificates to the specified location.

## PARAMETERS

### -Password

Specifies the password that is used to protect the Forest Recovery certificates.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Path

Specifies the full path to the Forest Recovery certificate file.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Export-RMADFEResult

## SYNOPSIS

Export the verification result of an RMADFE project.

## SYNTAX

```
Export-RMADFEResult [-Results] <ProjectSummary> [-Path] <String> [ [-  
FileType] <ExportFileType>]  
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet exports results after verifying all the domain controllers in a recovery project. To export the verification result, get the current status of the RMADFE project first, and then specify the file path and format to save the results of export file.

# EXAMPLES

## Example 1

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)  
Start-RMADFEVerification  
$results = Get-RMADFEProject
```

```
Export-RMADFEResult -Results $results -Path "C:\result.xml"
```

```
Export-RMADFEResult -Results $results -Path "C:\result.html" -FileType Html
```

This example illustrates how to export verification results to an XML file and an HTML file.  
The first line of this example gets the current status of the RMADFE project.  
The second line of this example exports the verification results to an XML and the file path is c:\result.xml.  
The third line of this example exports the verification results to an HTML file and the file path is c:\result.html.

## Example 2

```
PS C:\> Open-RMADFEProject -Path C:\RMADFeProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)  
Start-RMADFEVerification
```

```
Get-RMADFEProject | Export-RMADFEResult -Path "c:\result.xml"
```

```
Get-RMADFEProject | Export-RMADFEResult -Path "c:\result.htm" -FileType  
Html
```

This example illustrates how to export verification results with the pipeline.  
The first line of this example exports verification results to an XML file and saves it to c:\result.xml with the pipeline.  
The second line of this example exports verification results to an HTML file and saves it to c:\result.html with the pipeline.

# PARAMETERS

## -FileType

Specifies the format of the exported file.  
Default format is XML.

Type: ExportFileType  
Parameter Sets: (All)  
Aliases:  
Accepted values: Xml, Html, Txt, Csv

Required: False  
Position: 2  
Default value: Xml  
Accept pipeline input: False  
Accept wildcard characters: False

## -Path

Specifies the path to save the results.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Results

Specifies the current status of the RMADFE project.

```
Type: ProjectSummary
Parameter Sets: (All)
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Export-RMADSecureStorageBackup

## SYNOPSIS

Exports a backup on a Secure Storage server to a remote network share.

# SYNTAX

## **InputObject**

```
Export-RMADSecureStorageBackup [-InputObject] <BackupInfo[]> [-TargetRemoteFolder] <String> [-TargetCredentials] <PSCredential> [-PassThru] [<CommonParameters>]
```

## **Id**

```
Export-RMADSecureStorageBackup [-Id] <Int32[]> [-TargetRemoteFolder] <String> [-TargetCredentials] <PSCredential> [-PassThru] [<CommonParameters>]
```

# DESCRIPTION

Exports a backup on a Secure Storage server to a remote network share.

# EXAMPLES

## **Example 1**

```
$credential = Get-Credential  
$backup = Get-RMADBackup -OnlySecureStorage -ComputerName 'dc1.rmad.local'  
| Select-Object -First 1  
Export-RMADSecureStorageBackup -InputObject $backup -TargetRemoteFolder  
'\\192.168.0.1\BackupsNew\Temp' -TargetCredentials $credential
```

## **Example 2**

```
$credential = Get-Credential  
Export-RMADSecureStorageBackup -Id @(2, 4, 6) -TargetRemoteFolder  
'\\192.168.0.1\BackupsNew\Temp' -TargetCredentials $credential
```

# PARAMETERS

## **-Id**

Specifies the identifiers of one or more backups to export.  
This parameter accepts an array of integers.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **-InputObject**

Accepts a backup object as input to the cmdlet.  
Enter a variable that contains the object or type a command or expression that gets the object.

Type: BackupInfo[]  
Parameter Sets: InputObject

Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

### **-PassThru**

Passes the registration information for the specified backup along the pipeline.  
If this parameter is omitted, the registration information is not passed along the pipeline.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

### **-TargetCredentials**

Credentials to access the target network location.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: True
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

### **-TargetRemoteFolder**

Remote network share where backup should be exported.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: True
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**QuestSoftware.RecoveryManager.AD.PowerShell.BackupInfo[]**

**System.Int32[]**

**System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

**schema: 2.0.0**

## Get-RMADBackup

### SYNOPSIS

Gets backups registered with Recovery Manager.

### SYNTAX

#### **Id (Default)**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [[-Id]
<Int32[]>] [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
AfterModifiedDate <DateTime>] [-First <Int32>]
[-Skip <Int32>] [-SourceConsole <String>] [<CommonParameters>]
```

## **Id\_IncludeSecureStorage**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Id]
<Int32[]> [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
IncludeSecureStorage]
[-AfterModifiedDate <DateTime>] [-First <Int32>] [-Skip <Int32>] [-
SourceConsole <String>]
[<CommonParameters>]
```

## **Id\_OnlySecureStorage**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Id]
<Int32[]> [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
OnlySecureStorage] [-AfterModifiedDate <DateTime>]
[-First <Int32>] [-Skip <Int32>] [-SourceConsole <String>]
[<CommonParameters>]
```

## **Guid**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [[-Guid]
<Guid[]>] [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
AfterModifiedDate <DateTime>] [-First <Int32>]
[-Skip <Int32>] [-SourceConsole <String>] [<CommonParameters>]
```

## **Guid\_IncludeSecureStorage**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Guid]
<Guid[]> [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
IncludeSecureStorage]
[-AfterModifiedDate <DateTime>] [-First <Int32>] [-Skip <Int32>] [-
SourceConsole <String>]
[<CommonParameters>]
```

## **Guid\_OnlySecureStorage**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-Guid]
<Guid[]> [-ComputerName <String>]
[-MaxDate <DateTime>] [-MinDate <DateTime>] [-Site <String>] [-
CollectionId <Int32>]
[-BackupComponents <BackupComponents>] [-IncludeDeleted] [-
OnlySecureStorage] [-AfterModifiedDate <DateTime>]
[-First <Int32>] [-Skip <Int32>] [-SourceConsole <String>]
[<CommonParameters>]
```

## **IncludeSecureStorage**

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-
ComputerName <String>] [-MaxDate <DateTime>]
```

```
[-MinDate <DateTime>] [-Site <String>] [-CollectionId <Int32>] [-  
BackupComponents <BackupComponents>]  
[-IncludeDeleted] [-IncludeSecureStorage] [-AfterModifiedDate <DateTime>]  
[-First <Int32>] [-Skip <Int32>]  
[-SourceConsole <String>] [<CommonParameters>]
```

## OnlySecureStorage

```
Get-RMADBackup [-MinimumId <Int32>] [-Domain <String>] [-All] [-  
ComputerName <String>] [-MaxDate <DateTime>]  
[-MinDate <DateTime>] [-Site <String>] [-CollectionId <Int32>] [-  
BackupComponents <BackupComponents>]  
[-IncludeDeleted] [-OnlySecureStorage] [-AfterModifiedDate <DateTime>] [-  
First <Int32>] [-Skip <Int32>]  
[-SourceConsole <String>] [<CommonParameters>]
```

## DESCRIPTION

Retrieves the backup object for the backups registered in the Recovery Manager backup registration database.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADBackup | Where-Object {$_ .ComputerName -eq  
"dc1.dom1.local"}
```

This command retrieves all backup objects and passes them to the Where-Object cmdlet.  
The Where-Object cmdlet outputs the backup objects whose ComputerName property value is dc1.dom1.local.

### Example 2

```
PS C:\> Get-RMADBackup -Id 12345
```

Retrieves the backup whose identifier is 12345.

### Example 3

```
PS C:\> Get-RMADBackup | Where-Object {($_ .Date -gt (Get-Date) .AddDays(-5))  
-and ($_.Path -like "*Toronto*")}
```

This command retrieves objects that represent backups created by Recovery Manager for Active Directory in the last 5 days.  
The command retrieves only those backups whose file path includes the word "Toronto".

### Example 4

```
PS C:\> Get-RMADBackup -Skip 10 -First 100
```

This command skips the first 10 backups and starts retrieving 100 backups from the 11th one.

## PARAMETERS

### -AfterModifiedDate

Retrieves the backup objects that were last modified after this date.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-All**

When this parameter is present, the cmdlet gets all backup objects registered in the Recovery Manager backup registration database, including those whose file is physically missing.

When this parameter is omitted, the cmdlet gets only those backup objects registered in the Recovery Manager backup registration database whose file is physically present.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupComponents**

Retrieves the backup objects with the specified components only.

If this parameter is not specified, all backup objects are retrieved from the Recovery Manager backup registration database.

Type: BackupComponents  
Parameter Sets: (All)  
Aliases:  
Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, All

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-CollectionId**

Retrieves the backup objects for the specified collection only.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ComputerName**

Retrieves the backup objects from the specified computer only.

Type: String  
Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Domain

Retrieves the backup objects for the specified domain only.

If this parameter is not specified, all backup objects are retrieved from the Recovery Manager backup registration database.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName)  
Accept wildcard characters: False

## -Guid

Specifies the GUID of the backup to get.

Type: Guid[]  
Parameter Sets: Guid  
Aliases:

Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: Guid[]  
Parameter Sets: Guid\_IncludeSecureStorage, Guid\_OnlySecureStorage  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Id

Specifies the identifier of the backup to get.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: Int32[]  
Parameter Sets: Id\_IncludeSecureStorage, Id\_OnlySecureStorage

Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-IncludeDeleted**

When this parameter is present, the cmdlet gets all backup objects from the Recovery Manager backup registration database, including those objects whose status has been marked as Deleted or Unregistered.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-IncludeSecureStorage**

When this parameter is present, the cmdlet gets all backup objects from the Recovery Manager backup registration database, including backups stored on Secure Storage servers.

Type: SwitchParameter  
Parameter Sets: Id\_IncludeSecureStorage, Guid\_IncludeSecureStorage  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: SwitchParameter  
Parameter Sets: IncludeSecureStorage  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MaxDate**

Retrieves the backup objects after the specified date.

Type: DateTime  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MinDate**

Retrieves the backup objects before the specified date.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-MinimumId**

Retrieves backups with identifier greater than a specified number.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-OnlySecureStorage**

Return backups stored on a Secure Storage servers.

Type: SwitchParameter

Parameter Sets: Id\_OnlySecureStorage, Guid\_OnlySecureStorage

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: OnlySecureStorage

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Site**

Retrieves the backup objects from the specified AD site

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -SourceConsole

Retrieves backups replicated from a specified console.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -Skip

Specifies the number of backups to skip before starting retrieving.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -First

Specifies the number of backups to retrieve.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADBackupAgent

## SYNOPSIS

Retrieves objects that represent Recovery Manager Backup Agents, or discovers manually preinstalled Recovery Manager Backup Agents.

## SYNTAX

```
Get-RMADBackupAgent [-Discover] [-UpdateInfo] [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve a list of installed and registered in the Recovery Management Console Backup Agents. It also allows you to discover all Backup Agent instances that were manually preinstalled on computers.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADBackupAgent
```

This code returns a list of installed and registered in the Recovery Management Console Backup Agents.

### Example 2

```
PS C:\> Get-RMADBackupAgent -Discover
```

This code discovers all Backup Agent instances that were manually preinstalled on computers.

Note that after the discover operation completes, you can view and manage the discovered Backup Agent instances using the corresponding cmdlets or from the Backup Agent Management node in the Recovery Manager Console.

# PARAMETERS

## -Discover

Specifies whether Backup Agent instances that were manually preinstalled on computers should be discovered.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -UpdateInfo

Specifies whether Backup Agents information should be re-requested.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

**schema: 2.0.0**

## Get-RMADBackupInfo

### SYNOPSIS

Gets the content of the backups held at a specified location.

### SYNTAX

#### Bkf

```
Get-RMADBackupInfo [-Path] <String[]> [-BackupPassword <SecureString>] [-UseLegacyEncryption] [-IgnoreReadOnly] [<CommonParameters>]
```

#### OfflineDit

```
Get-RMADBackupInfo [-Path] <String[]> [-SysvolPath <String[]>] [-ResolveIndexes <Boolean>] [-OfflineDit] [-IgnoreReadOnly] [<CommonParameters>]
```

#### BackupInfo

```
Get-RMADBackupInfo [-BackupPassword <SecureString>] [-UseLegacyEncryption] [-IgnoreReadOnly] [<CommonParameters>]
```

### DESCRIPTION

The Get-RMADBackupInfo cmdlet gets the content of the backups created with Recovery Manager and held at the location specified by the path.

### EXAMPLES

#### Example 1

```
PS C:\> $b = Get-ChildItem C:\Backups -Filter *.bkf -Recurse | Get-RMADBackupInfo  
C:\PS>Where-Object -InputObject $b { $_.Contents -band 64 } | Add-RMADBackup
```

This command gets the content of all backups held in the C:\Backups folder and its subfolders, and saves the content in the \$b variable.

The Where-Object cmdlet then passes the Active Directory backups from the \$b variable to the Add-Backup cmdlet (the number 64 stands for the Active Directory component.) Add-RMADBackup then registers the passed Active Directory backups in the Recovery Manager database.

#### Example 2

```
PS C:\> $p = Read-Host "Backup Password" -AsSecureString
```

```
C:\PS>Get-RMADBackupInfo C:\Backups\password-protected_backup1.bkf -  
BackupPassword $p
```

In this example, the Read-Host cmdlet provided by Windows PowerShell gets the backup password as a SecureString object and saves it in the \$p variable.

The Get-RMADBackupInfo then uses the password saved in the \$p variable to access the password-protected backup C:\Backups\password-protected\_backup1.bkf.

## PARAMETERS

### **-BackupPassword**

Specifies the password to access a password-protected backup.

This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString

Parameter Sets: Bkf, BackupInfo

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### **-OfflineDit**

Specifies that the application registers the DIT file as a backup.

Type: SwitchParameter

Parameter Sets: OfflineDit

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### **-Path**

Specifies the path to the backups whose content is to be retrieved.

Type: String[]

Parameter Sets: Bkf, OfflineDit

Aliases: FullName

Required: True

```
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

## **-ResolveIndexes**

Reindexes the DIT file in case of invalid index data.

```
Type: Boolean
Parameter Sets: OfflineDit
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-SysvolPath**

Path to the SYSVOL folder.

```
Type: String[]
Parameter Sets: OfflineDit
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-UseLegacyEncryption**

Allows you to work with backups encrypted by the RC4 algorithm from RSA, Inc.  
(Microsoft RSA Base Provider).

This algorithm is used to back up Windows Server 2003/2003 R2 domain controllers in Recovery Manager for Active Directory 8.2.x and 8.5.x.

```
Type: SwitchParameter
Parameter Sets: Bkf, BackupInfo
Aliases:
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADBackupObject

## SYNOPSIS

Get objects from backups

## SYNTAX

### **InputObject+Name (Default)**

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Name <String[]>] [-  
BackupPassword <SecureString>]  
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-  
KeepBackupUnpacked]  
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

### **InputObject+Id**

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Id <String[]>] [-  
BackupPassword <SecureString>]  
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-  
KeepBackupUnpacked]  
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

### **InputObject+Filter**

```
Get-RMADBackupObject -InputObject <BackupInfo[]> [-Filter <String>] [-  
BackupPassword <SecureString>]  
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-  
KeepBackupUnpacked]  
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

## **BackupGuid+Id**

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Id <String[]>] [-BackupPassword <SecureString>]
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked]
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

## **BackupGuid+Name**

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Name <String[]>] [-BackupPassword <SecureString>]
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked]
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

## **BackupGuid+Filter**

```
Get-RMADBackupObject -BackupGuid <Guid[]> [-Filter <String>] [-BackupPassword <SecureString>]
[-Attribute <String[]>] [-SearchBase <String>] [-Count <Int32>] [-KeepBackupUnpacked]
[-AdLdsInstance <String[]>] [<CommonParameters>]
```

# **DESCRIPTION**

Retrieves specific objects from certain backups registered with Recovery Manager for Active Directory.

# **EXAMPLES**

### **Example 1**

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -Name "Adm" -Attribute *
```

Retrieves a list of all backups that are registered in Recovery Manager for Active Directory and then search for the object using ambiguous name resolution.

In this example, you will get a list of all objects that have 'Adm' in the beginning of any naming attribute from the 'ANR attribute Set'.

### **Example 2**

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -SearchBase
'CN=Partitions,CN=Configuration,DC=CONTOSO,DC=COM' -Filter
"objectClass='crossRef'"
```

Retrieves a list of objects from the container that is specified in the 'SearchBase' parameter. The objects are filtered by the 'objectClass' attribute.

### **Example 3**

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -Filter "givenName=Name
1|Name 2,cn=Smith"
```

Retrieves a list of all registered backups and all objects that have 'Name 1' or 'Name 2' value for the 'givenName' attribute and 'Smith' for the 'CN' attribute.

### **Example 4**

```
PS C:\> Get-RMADObject -Filter
"distinguishedName='CN=name1,DC=mydomain,DC=com'"
```

Retrieves a list of all registered backups and all objects that have the following distinguished name: CN=name1,DC=mydomain,DC=com.

## Example 5

```
PS C:\> Get-RMADBackup | Get-RMADBackupObject -AdLdsInstance  
'ContosoApplication' -Filter  
"distinguishedName='CN=Users,CN=Roles,CN=App1,DC=contoso,DC=com'"
```

Retrieves the object with the specified distinguished name from the backup of the 'ContosoApplication' AD LDS instance.

# PARAMETERS

## -AdLdsInstance

If you search in the AD LDS instance backup, you should specify a list of AD LDS instances in which you want to search.

Type: String[]  
Parameter Sets: (All)  
Aliases: AdamInstance

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Attribute

Specifies the object attributes to retrieve in addition to the attributes the cmdlet retrieves by default.  
If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes: - distinguishedName - name - objectClass - objectguid

Type: String[]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -BackupGuid

GUID of the registered backup.

Type: Guid[]  
Parameter Sets: BackupGuid+Id, BackupGuid+Name, BackupGuid+Filter  
Aliases: Guid

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access a password-protected backup.

This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Count**

Limits the maximum number of objects to retrieve.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Filter**

Allows you to filter objects by attribute names and attribute values.

For details, see the examples provided for this cmdlet.

Type: String

Parameter Sets: InputObject+Filter, BackupGuid+Filter

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Id**

Specifies the identifier of the object to retrieve.

This parameter accepts one of the following: - GUID - Distinguished name (DN) - samAccountName - userLogonName

Type: String[]

Parameter Sets: InputObject+Id, BackupGuid+Id

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-InputObject**

Specifies backups that contain the retrieved object.  
To get the backup, use the Get-RMADBackup cmdlet.

Type: BackupInfo []  
Parameter Sets: InputObject+Name, InputObject+Id, InputObject+Filter  
Aliases: Backup, Backups

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **-KeepBackupUnpacked**

Determines whether to save the unpacked backup after the search operation.  
If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Name**

Retrieves objects whose Name attribute value is equal to the value specified in this parameter.

Type: String []  
Parameter Sets: InputObject+Name, BackupGuid+Name  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SearchBase**

Specifies an Active Directory container in which to search for objects.  
The search is performed in the specified container and all its subcontainers.  
Specify the distinguished name (DN) of the container in which you want to search.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADBackupSecurityStatus

## SYNOPSIS

Gets security check information for a specified backup.

## SYNTAX

```
Get-RMADBackupSecurityStatus [-BackupGuid <Guid[]>] [-From <DateTime>]  
[<CommonParameters>]
```

## DESCRIPTION

Retrieves security check information for a specified backup registered with Recovery Manager for Active Directory.

## EXAMPLES

### Example 1

```
PS C:\> $bkf = (Get-RMADBackup -ComputerName dc.DomainName.local)[-1]  
$status = New-Object -TypeName  
QuestSoftware.RecoveryManager.AD.PowerShell.BackupSecurityStatus  
$status.Summary = "Passed"  
$status.Details = "all successful"  
$status.CheckDate = Get-Date
```

```
Publish-RMADBackupSecurityStatus -BackupGuid $bkf.backupGuid -  
    SecurityStatus $status  
Get-RMADBackup -ComputerName dc.DomainName.local | %{  
    Get-RMADBackupSecurityStatus -BackupGuid $_.BackupGuid  
}
```

For troubleshooting only.

This command retrieves information related to antimalware scan results for all backups registered with Recovery Manager for Active Directory.

## PARAMETERS

### **-BackupGuid**

This is the GUID of the backup for which a user wants to get the antimalware scan results.

Type: Guid[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-From**

Specifies the time point to get statuses.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADCollection

## SYNOPSIS

Retrieves Recovery Manager computer collection objects or default computer collection settings.

## SYNTAX

### Name (Default)

```
Get-RMADCollection [-Name] <String[]> [<CommonParameters>]
```

### Id

```
Get-RMADCollection [-Id] <Int32[]> [<CommonParameters>]
```

### Default

```
Get-RMADCollection [-Default] [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve an existing Recovery Manager computer collection by its name or ID. This cmdlet retrieves all existing computer collections if no collection name or ID is specified. You can also use this cmdlet to retrieve the default computer collection settings that apply to each new computer collection.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADCollection
```

This command retrieves all Recovery Manager computer collections.

### Example 2

```
PS C:\> (Get-RMADCollection Coll1).Schedule
```

This command retrieves the line containing the schedule for the collection named Coll1.

# PARAMETERS

## -Default

Allows you to retrieve the default computer collection settings that apply to each new computer collection.  
Do not use the Name or ID parameter along with this parameter.

Type: SwitchParameter  
Parameter Sets: Default  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -Id

Specifies the identifier of the Computer Collection to retrieve.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## -Name

Specifies the name of the computer collection you want to retrieve.

In the computer collection name that you type in this parameter, you can use an asterisk as a wildcard symbol for any number of any characters.

Do not use the Default parameter along with this parameter.

Type: String[]  
Parameter Sets: Name  
Aliases:

Required: False  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADCollectionItem

## SYNOPSIS

Retrieves information about items added to specified Recovery Manager for Active Directory computer collections.

## SYNTAX

### **InputObject**

```
Get-RMADCollectionItem [-InputObject] <ComputerCollection[]> [-UseCache] [-ComputerInfo] [<CommonParameters>]
```

### **Name**

```
Get-RMADCollectionItem [-UseCache] [-Name] <String[]> [-ComputerInfo] [<CommonParameters>]
```

### **Id**

```
Get-RMADCollectionItem [-UseCache] [-Id] <Int32[]> [-ComputerInfo] [<CommonParameters>]
```

## DESCRIPTION

Retrieves information about items added to specified Recovery Manager for Active Directory computer collections.

You can use this cmdlet to retrieve information about one of the following:<sup>\*</sup> Items that are explicitly added to computer collections (such as domain controllers, Active Directory domains, Active Directory sites, organizational units, AD LDS (ADAM) hosts, AD LDS (ADAM) instances, and AD LDS (ADAM) sites).

- Domain controllers and AD LDS (ADAM) hosts that are explicitly or implicitly added to computer collections.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADCollectionItem -Collection NewCollection
```

Retrieves information about items that are explicitly added to the Computer Collection named NewCollection. These items can include domain controllers, Active Directory domains, Active Directory sites, organizational units, AD LDS (ADAM) hosts, AD LDS (ADAM) instances, and AD LDS (ADAM) sites.

## Example 2

```
PS C:\> Get-RMADCollectionItem -Collection NewCollection -ComputerInfo
```

Retrieves information about domain controllers and AD LDS (ADAM) hosts explicitly or implicitly added to the Computer Collection named NewCollection.

# PARAMETERS

## -ComputerInfo

When present, specifies to retrieve information about the domain controllers and AD LDS (ADAM) hosts that are explicitly or implicitly added to the computer collections you specified in the Collection parameter.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -Id

Specifies the identifier of the computer collection that includes the items you want to retrieve.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## -InputObject

Specifies the object representing the computer collections that include the items you want to retrieve.

Type: ComputerCollection[]

Parameter Sets: InputObject

Aliases: Collection

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-Name**

Specifies the name of the computer collection that includes the items you want to retrieve.

Type: String[]

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-UseCache**

Specifies to return the data from cache

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADDeletedObject

## SYNOPSIS

Retrieves deleted Active Directory objects.

## SYNTAX

### Name (Default)

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups]
[-ForceBackupRetrieving] [-Name <String[]>] [-Count <Int32>] [-Attribute <String[]>]
[-SearchBase <String>]
[-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>]
[-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

### Identity

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups]
[-ForceBackupRetrieving] [-Id <String[]>] [-Attribute <String[]>] [-UseSsl]
[-Server <String>]
[-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

### Filter

```
Get-RMADDeletedObject [-All] [-Restorable] [-Computer <String>] [-RetrieveOnlyUnpackedBackups]
[-ForceBackupRetrieving] [-Filter <String>] [-Count <Int32>] [-Attribute <String[]>]
[-SearchBase <String>]
[-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>]
[-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve specific deleted or recycled Active Directory objects.

The cmdlet retrieves objects from the default naming context or the Active Directory partition you specify.

You can only retrieve recycled objects when Microsoft's Active Directory Recycle Bin is enabled in your environment. By default, for each deleted object, this cmdlet retrieves the following attributes: - GUID

- Distinguished name (DN)
- Name
- objectClass

You can also specify additional attributes you want to retrieve.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADDeletedObject
```

This command retrieves all deleted Active Directory objects in the current domain.

## Example 2

```
PS C:\> Get-RMADDeletedObject -Name "User 1"
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the deleted objects whose Name attribute value is User 1.

## Example 3

```
PS C:\> Get-RMADDeletedObject -Name "User 1" -Attribute usnChanged,  
usnCreated
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the deleted objects whose Name attribute value is User 1.

In addition to the default set of object attributes (that is, GUID, Distinguished name (DN), Name, and objectClass), this command also retrieves the attributes usnChanged and usnCreated.

## Example 4

```
PS C:\> Get-RMADDeletedObject -Filter "whenCreated>=20130601123000.0Z"
```

This command retrieves all deleted objects that were created on 1 June 2013 at 12:30:00 or after this date.

## Example 5

```
PS C:\> Get-RMADDeletedObject -Filter "whenCreated=20130601000000.0Z"
```

This command retrieves all deleted objects that were created on 1 June 2013 between 00:00:00 and 23:59:59.

## Example 6

```
PS C:\> Get-RMADDeletedObject -Filter  
"distinguishedName='CN=user1\0ADEL:b0806312-d320-41fb-9e4d-  
ebad82706a74,CN=Deleted Objects,DC=mydomain,DC=com'"
```

Retrieves the deleted object whose distinguished name (DN) is CN=user1\0ADEL:b0806312-d320-41fb-9e4d-ebad82706a74,CN=Deleted Objects,DC=mydomain,DC=com.

## Example 7

```
PS C:\> Get-RMADDeletedObject -Name user1 -SearchBase  
'OU=Users,DC=domain,DC=com'
```

Gets the deleted object whose Name attribute value is user1 and that was deleted from the container with DN OU=Users,DC=domain,DC=com or from any of its subcontainers.

# PARAMETERS

## -All

Specifies to retrieve all deleted and recycled Active Directory objects.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: ShowRecycled

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -Attribute

Specifies the object attributes to retrieve in addition to the attributes retrieved by default.  
If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes: - GUID

- Distinguished name (DN)
- Name
- objectClassTo specify all available object attributes, type an asterisk (\*) in this parameter.

```
Type: String[]
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Computer

Specifies the computer whose backups contain the deleted object to retrieve.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Count

Limits the maximum number of objects to retrieve.

```
Type: Int32
Parameter Sets: Name, Filter
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Credential

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

```
Type: PSCredential
```

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Filter**

Allows you to filter objects by attribute names and attribute values.

For the syntax this parameter accepts, see the examples provided for this cmdlet.

Type: String

Parameter Sets: Filter

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ForceBackupRetrieving**

Retrieves the ID of the backup that contains the deleted object even if this object can be restored using the Active Directory Recycle Bin.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Id**

Specifies the identifier of the object to retrieve.

This parameter accepts one of the following: - GUID

- Distinguished name (DN)
- samAccountName
- userLogonName

Type: String[]

Parameter Sets: Identity

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Name**

Retrieves objects whose Name attribute value is equal to the value specified in this parameter.

The Name attribute stores object's relative distinguished name (RDN) which looks similar to the following: User 10ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b

Type: String[]

Parameter Sets: Name

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Partition**

Specifies the distinguished name of the Active Directory partition from which you want to retrieve objects.

If this parameter is omitted, the default naming context is used.

This parameter is required if you specify an AD LDS (ADAM) instance host in the Server parameter.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Port**

Specifies the port number to connect to.

If this parameter is set to 0 or omitted, the default LDAP port (389) is used.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Restorable**

Specifies to retrieve only those objects that can be completely restored.  
That is, objects located in Microsoft's Active Directory Recycle Bin or in a backup registered with Recovery Manager for Active Directory.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-RetrieveOnlyUnpackedBackups**

Retrieves the deleted objects only from the unpacked backups.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SearchBase**

Specifies an Active Directory container in which to search for deleted objects.  
This is the container from which the objects you want to find were deleted.  
The search is performed in the specified container and all its subcontainers, including the deleted ones.  
Specify the distinguished name (DN) of the container in which you want to search.

Type: String  
Parameter Sets: Name, Filter  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Server**

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects.  
If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain.  
To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address.  
If you specify an Active Directory domain name in this parameter, deleted objects are retrieved from any available domain controller in the specified domain.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Timeout**

Specifies the maximum wait time for retrieving the objects, in seconds.  
The default value is 30.

```
Type: Int32  
Parameter Sets: Name, Filter  
Aliases:  
  
Required: False  
Position: Named  
Default value: 30  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-UseSsl**

Specifies whether use Secure Sockets Layer (SSL) to encrypt the connection.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFEAvailableSubnet

## SYNOPSIS

For internal use only.

## SYNTAX

```
Get-RMADFEAvailableSubnet [[-NetworkAddress] <String>]
    [[-CurrentSubnets] <System.Collections.Generic.List`1[System.String]>] [[-Cidr] <Int32>] [<CommonParameters>]
```

## DESCRIPTION

For internal use only.

## EXAMPLES

### Example 1

```
PS C:\> {{ Add example code here }}
```

```
 {{ Add example description here }}
```

## PARAMETERS

### -Cidr

For internal use only.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -CurrentSubnets

For internal use only.

Type: System.Collections.Generic.List`1[System.String]  
Parameter Sets: (All)  
Aliases: Subnets

Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False

Accept wildcard characters: False

## -NetworkAddress

For internal use only.

Type: String

Parameter Sets: (All)

Aliases: Network

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**None**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

**schema: 2.0.0**

## Get-RMADFECloudStorage

### SYNOPSIS

Returns cloud storage registered in Recovery Manager for Active Directory.

## SYNTAX

```
Get-RMADFECloudStorage [-Id <Int32>] [<CommonParameters>]
```

## DESCRIPTION

Returns cloud storage registered in Recovery Manager for Active Directory specified by the Id parameter. Display name, container and type of cloud storage is returned.  
If no Id parameter provided all registered cloud storages will be returned.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADFECloudStorage  
Id DisplayName Container Type  
----  
1 MyCloudStorage adbackups CloudStorageAzure  
2 CompanyStorage bmrbackups CloudStorageAzure
```

Returns all registered cloud storages in Recovery Manager for Active Directory.

### Example 2

```
PS C:\> Get-RMADFECloudStorage -Id 1  
Id DisplayName Container Type  
----  
1 MyCloudStorage adbackups CloudStorageAzure
```

Retrieve a cloud storage specified by the Id parameter. If no Id parameter provided all registered cloud storages will be returned.

## PARAMETERS

### -Id

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32  
Parameter Sets: (All)  
Aliases: StorageId

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**None**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

**schema: 2.0.0**

# Get-RMADFECloudStorageCollection

## SYNOPSIS

Returns computer collections for the cloud storage registered in Recovery Manager for Active Directory.

## SYNTAX

### **Id**

```
Get-RMADFECloudStorageCollection [-Id] <Int32[]> [-IgnoreReadOnly]  
[<CommonParameters>]
```

### **InputObject**

```
Get-RMADFECloudStorageCollection [-InputObject] <CloudStorage[]> [-  
IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Returns computer collections for the cloud storage specified in the parameter Id. Each computer collection is returned with collection name, last status result, last run date, next run date and schedule.

## EXAMPLES

### **Example 1**

```
PS C:\> Get-RMADFECloudStorage
```

```

Id DisplayName Container Type
-- ----- ----- -----
1 CloudStorageAF adbackups CloudStorageAzure

PS C:\>Get-RMADFECloudStorageCollection -Id 1

Name LastResult LastRunDate NextRunDate
Schedule
----- ----- -----
MyCollection Success 10/28/2021 16:45 10/28/2021 13:55
{At 4:55 PM every day}

```

Returns all computer collections for the cloud storage with Id 1.

## PARAMETERS

### **-Id**

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases: StorageId

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-InputObject**

Specifies the CloudStorage object representing the storage.

Type: CloudStorage[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

**schema: 2.0.0**

# Get-RMADFECloudStorageUploadSession

## SYNOPSIS

Retrieves the cloud storage upload session details.

## SYNTAX

```
Get-RMADFECloudStorageUploadSession [-Id <Int32>] [-StorageId <Int32>] [-Limit <Int32>] [<CommonParameters>]
```

## DESCRIPTION

Returns the upload sessions details for the specified cloud storage. Each upload session is returned with a status, creation timestamp and error message if available.

Using the Limit parameter specify the number of upload sessions to be returned.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADFECloudStorageUploadSession -StorageId 1 -Limit 1  
Id : 1  
StorageId : 1  
BackupId : 248  
SourceBackupPath : \mycomputer.company.ca\Backups\mycomputer-2021-10-28 16-13-51.bkf  
TargetBackupPath : mycomputer.company.ca\Backups\mycomputer-2021-10-28 16-13-51.bkf  
ErrorMessage :  
CreationTimestamp : 10/28/2021 4:14:10 PM  
ModificationTimestamp : 10/28/2021 4:14:17 PM  
Status : UploadStatusCompleted
```

Retrieve the latest upload session for the cloud storage with Id 1.

# PARAMETERS

## -Id

Specifies the upload session Id.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Limit

Maximum number of session to return. When not specified all upload sessions will be returned.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -StorageId

Specifies the cloud storage Id.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**None**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Get-RMADFEComputer

## SYNOPSIS

Retrieves a list of computer settings from the current RMADFE project.

## SYNTAX

```
Get-RMADFEComputer [ [-ComputerName] <String> ] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet retrieves the computer settings for one or more computers from the current RMADFE project. By default, this cmdlet retrieves the following information for each computer: - Computer Name

- User Name
- DSRM User Name
- Network Share User Name
- Use of Default Domain Settings

# EXAMPLES

## EXAMPLE 1

```
PS C:\> Get-RMADFEComputer -Name dc1.acme.com
```

This command retrieves information about the specified computer from the current RMADFE project.

## EXAMPLE 2

```
PS C:\> Get-RMADFEComputer
```

This command retrieves information about all computers from the current RMADFE project.

# PARAMETERS

## -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases: Name

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Get-RMADFEConsole

## SYNOPSIS

Gets all registered RMAD FE consoles.

## SYNTAX

```
Get-RMADFEConsole [<CommonParameters>]
```

## DESCRIPTION

Gets all registered in the persistence database RMAD FE consoles.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADFEConsole
```

This command gets a list of all FR Console instances registered in the persistence database.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFEDnsCache

## SYNOPSIS

Returns cached DNS records in the Forest Recovery project.

## SYNTAX

```
Get-RMADFEDnsCache [<CommonParameters>]
```

## DESCRIPTION

This cmdlet returns a list of DNS records saved in the Forest Recovery project.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADFEDnsCache
```

This command returns a list of DNS records saved in the Forest Recovery project.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

### None

## OUTPUTS

### System.Object

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFEDomain

## SYNOPSIS

Retrieves the domain settings.

## SYNTAX

```
Get-RMADFEDomain [-Domain <String>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet gets the domain settings for one or more domains from the RMADFE project. By default, this cmdlet retrieves the following information for each domain: - Domain Name

- User Name
- DSRM User Name
- Password Resetting

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Get-RMADFEDomain -Domain acme.com
```

This command retrieves the domain settings for the specified domain.

```
Domain : acme.com Recover : True AuthoritativeSysvolRestoreComputer : dc1.acme.com UserName : Administrator DsrmUserName : Administrator ResetPasswords : False Groups : {} Exclusions : {}
```

### EXAMPLE 2

```
PS C:\> Get-RMADFEDomain
```

This command retrieves information about all domains from the current RMADFE project.

```
Domain : acme.com Recover : True AuthoritativeSysvolRestoreComputer : dc1.acme.com UserName : Administrator DsrmUserName : Administrator ResetPasswords : False Groups : {} Exclusions : {}
```

```
Domain : child.acme.com Recover : True AuthoritativeSysvolRestoreComputer : UserName : DsrmUserName : ResetPasswords : True Groups : {} Exclusions : {}
```

```
Domain : resource.acme.com Recover : True AuthoritativeSysvolRestoreComputer : UserName : DsrmUserName : ResetPasswords : True Groups : {Group_A, Group_B, Group_C} Exclusions : {User_01, User_02}
```

# PARAMETERS

## -Domain

Specifies the fully qualified domain name.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Get-RMADFEEvent

## SYNOPSIS

Returns recovery events related to the entire Active Directory forest or a specific domain controller.

## SYNTAX

```
Get-RMADFEEvent [ [-ComputerName] <String>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet returns recovery events related to the entire Active Directory forest or a specific domain controller.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Get-RMADFEEvent -ComputerName dc5.child.acme.test | select -ExpandProperty EventDescription | Format-Table EventKind,EventMessage,MessageCode
```

This command returns a list of recovery events related to dc5.child.acme.test.

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFEGlobalOptions

## SYNOPSIS

Gets global application settings.

## SYNTAX

```
Get-RMADFEGlobalOptions [ [-Name] <String>] [<CommonParameters>]
```

## DESCRIPTION

Retrieves global settings that are applied to all recovery projects by default.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADFEGlobalOptions -Name "SMTPServer"
```

This command returns the address of SMTP server.

## PARAMETERS

### -Name

Specifies the name of the parameter whose value will be returned by the command.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Get-RMADFEOperation

## SYNOPSIS

Returns information about the progress of the recovery operations.

## SYNTAX

```
Get-RMADFEOperation [[-ComputerName] <String>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet shows progress information for the recovery stages and steps that are applicable to the selected domain controller.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Get-RMADFEOperation -ComputerName DC1.rmad.local
```

This command gets the errors that occurred during the recovery session.

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

```
Required: False
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFEPersistenceConnection

## SYNOPSIS

Gets persistence connection settings.

## SYNTAX

```
Get-RMADFEPersistenceConnection [<CommonParameters>]
```

## DESCRIPTION

Retrieves persistence connection settings that are used to store the state of Forest Recovery process.

## EXAMPLES

### Example 1

```
PS C:\> $creds = new-object PSCredential("sa", (ConvertTo-SecureString 'Password' -asPlainText -Force))
```

```
Set-RMADFEPersistenceConnection -DataSource "ws\SQLExpress" -Credentials $creds  
Set-RMADFEPersistenceConnection -Enable  
Get-RMADFEPersistenceConnection
```

This command retrieves persistence connection settings that are used to store the state of the Forest Recovery process.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

## Get-RMADFEProject

### SYNOPSIS

Gets the current status of the RMADFE project.

### SYNTAX

```
Get-RMADFEProject [-ProjectInfo] [<CommonParameters>]
```

### DESCRIPTION

This cmdlet gets the current status of the RMADFE project.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> Get-RMADFEProject | Format-List *
```

This command gets the current status of the RMADFE project.

# PARAMETERS

## -ProjectInfo

Specifies to return special project information container

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Get-RMADFERecoveryAgent

## SYNOPSIS

Returns information about Forest Recovery Agents that are installed and registered in Forest Recovery Console.

## SYNTAX

### ProjectSpecificParameters (Default)

```
Get-RMADFERecoveryAgent [[-ComputerName] <String>] [<CommonParameters>]
```

### ProjectLessNormalMode

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential <PSCredential> [<CommonParameters>]
```

### ProjectLessDsrm

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DsrmCredential <PSCredential> [<CommonParameters>]
```

### ProjectLessBothMode

```
Get-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential <PSCredential> -DsrmCredential <PSCredential> [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve a list of Forest Recovery Agent instances that are installed and registered in Forest Recovery Console.

You can get the agent information for an existing RMADFE project using the user credentials specified in the project or by providing credentials as parameters.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-SecureString "password" -AsPlainText -Force)
```

```
Get-RMADFERecoveryAgent
```

Returns information about all Forest Recovery Agents installed and registered in the RMADFE project.

### EXAMPLE 2

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-SecureString "password" -AsPlainText -Force)
```

```
Get-RMADFERecoveryAgent -name dc1.RMAD.local
```

Returns information about the Forest Recovery Agent installed on the specified domain controller in the RMADFE project.

## EXAMPLE 3

```
PS C:\> $credentilas = New-Object PSCredential(".\Administrator",
(ConvertTo-SecureString 'Password' -AsPlainText -Force))

Get-RMADFERecoveryAgent -name dcl.RMAD.local -DcCredential $credentilas -
DsrmCredential $credentilas
```

Returns information about the Forest Recovery Agent installed on the specified domain controller (either in Normal or DSRM mode).

In this example, you should use only domain credentials or DSRM credentials, or both.

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String  
Parameter Sets: ProjectSpecificParameters  
Aliases:

Required: False  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: String  
Parameter Sets: ProjectLessNormalMode, ProjectLessDsrm, ProjectLessBothMode  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential  
Parameter Sets: ProjectLessNormalMode, ProjectLessBothMode  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -DsrmCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential  
Parameter Sets: ProjectLessDsrm, ProjectLessBothMode

Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Get-RMADFESchedule

## SYNOPSIS

Gets a schedule for the RMADFE project verification.

## SYNTAX

Get-RMADFESchedule [<CommonParameters>]

## DESCRIPTION

This cmdlet returns a schedule for verification of the current RMADFE project.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> Get-RMADFESchedule
```

Returns the current project schedule or nothing if the schedule is not configured.

# PARAMETERS

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADGlobalOptions

## SYNOPSIS

Sets global settings for the application.

## SYNTAX

```
Get-RMADGlobalOptions [ [-Name] <String>] [<CommonParameters>]
```

## DESCRIPTION

Sets Recovery Manager for Active Directory global settings.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADGlobalOptions -Name "UnpackingPath"
```

This cmdlet returns the value of the "UnpackingPath" global option.

## Example 2

```
PS C:\> Get-RMADGlobalOptions "UnpackingPath"
```

This cmdlet also can return the value of the "UnpackingPath" global option.

## Example 3

```
PS C:\> Get-RMADGlobalOptions
```

This code returns a HashTable which contains the name and value of all global options.

# PARAMETERS

## -Name

Specifies the name to the option whose value is retrieved.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADLicenseInfo

## SYNOPSIS

Retrieves information about the installed license key file.

## SYNTAX

```
Get-RMADLicenseInfo [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve information about the installed license key file including the following fields: - aboutText - purchased - allocated - expirationDate - managedUsers - isDemo - isForestRecoveryLicensed - isOrwAgentModeDisabled

## EXAMPLES

### Example 1

```
PS C:\> (Get-RMADLicenseInfo) .Allocated
```

This code returns the number of already allocated licenses.

### Example 2

```
PS C:\> (Get-RMADLicenseInfo) .Purchased
```

This code returns the number of purchased licenses.

### Example 3

```
PS C:\> (Get-RMADLicenseInfo) .ManagedUsers
```

This code returns the maximum number of users allowed by a Per Managed Person license.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADObject

## SYNOPSIS

Retrieves specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory.

## SYNTAX

### Name (Default)

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Name <String[]>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>] [-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

### Identity

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Id <String[]>] [-Attribute <String[]>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

### Filter

```
Get-RMADObject [-KeepBackupUnpacked] [-State <ObjectState>] [-Backup <Guid[]>] [-BackupPassword <SecureString>] [-DisableADSearch] [-Filter <String>] [-Count <Int32>] [-Attribute <String[]>] [-SearchBase <String>]
```

```
[-Timeout <Int32>] [-UseSsl] [-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to retrieve specific objects from Active Directory or certain backups registered with Recovery Manager for Active Directory. By default, with each object, this cmdlet retrieves the following attributes: - distinguishedName

- name
- objectClass
- objectguid
- isDeleted
- isRecycledIf the object is deleted, in addition to the above-listed attributes, the cmdlet also retrieves the following attributes:
  - whentchanged
  - whencreated
  - lastKnownParent,
  - msDS-LastKnownRDNYou can also specify additional attributes to retrieve.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADObject -Name "User 1"
```

This command uses ambiguous name resolution (ANR) to look for and retrieve the objects whose Name attribute value is User 1.

### Example 2

```
PS C:\> $b = Get-RMADBackup
```

```
C:\PS>Get-RMADObject -DisableADSearch -Backup $b -Name "User 1" -Attribute *
```

In the first line of this command, the Get-RMADBackup gets all backups registered with Recovery Manager for Active Directory and stores the backup objects in the \$b variable.

### Example 3

```
PS C:\> Get-RMADObject -Name "User 1" -State Live, Deleted -Attribute usnChanged, usnCreated
```

This command uses ambiguous name resolution (ANR) to look for and retrieve objects whose Name attribute value is User 1 and whose state is either live or deleted.

In addition to the default attribute set, the command retrieves the usnChanged and usnCreated attributes for each object.

### Example 4

```
PS C:\> Get-RMADObject -Filter "givenName=User 1|User 2,sn=Smith"
```

This command retrieves the objects whose givenName attribute value is either User 1 or User 2 and whose sn attribute value is Smith.

### Example 5

```
PS C:\> Get-RMADObject -Filter "whenCreated>=20130601123000.0Z"
```

This command retrieves all objects that were created on 1 June 2013 at 12:30:00 or after this date.

### Example 6

```
PS C:\> Get-RMADObject -Filter "whenCreated=20130601000000.0Z"
```

This command retrieves all objects that were created on 1 June 2013 between 00:00:00 and 23:59:59.

### Example 7

```
PS C:\> Get-RMADObject -Filter  
"distinguishedName='CN=user1,DC=mydomain,DC=com'"
```

Retrieves the object whose distinguished name (DN) is CN=user1,DC=mydomain,DC=com.

### Example 8

```
PS C:\> Get-RMADObject -Name user1 -State live -SearchBase  
'OU=Users,DC=domain,DC=com'
```

Gets the object whose Name attribute value is user1 and that is located in the container with DN OU=Users,DC=domain,DC=com or in any of its subcontainers.

## PARAMETERS

### -Attribute

Specifies the object attributes to retrieve in addition to the attributes the cmdlet retrieves by default. If this parameter is omitted or empty, the cmdlet retrieves the following default set of object attributes: - distinguishedName

- name
- objectClass
- objectguid
- isDeleted
- isRecycledTo specify all available object attributes, type an asterisk (\*) in this parameter.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -Backup

Specifies the backup that contains the object to retrieve.

To specify a backup, type the backup GUID in this parameter or use the Get-RMADBackup cmdlet.

Type: Guid[]  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access the password-protected backup that contains the object you want to retrieve.

Type: SecureString  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Count**

Limits the maximum number of objects to retrieve.

Type: Int32  
Parameter Sets: Name, Filter  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Credential**

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DisableADSearch**

When present, specifies to search Active Directory for objects to retrieve.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False

```
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Filter**

Allows you to filter objects by attribute names and attribute values.  
For the syntax this parameter accepts, see the examples provided for this cmdlet.

```
Type: String
Parameter Sets: Filter
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Id**

Specifies the identifier of the object to retrieve.  
This parameter accepts one of the following: - GUID

- Distinguished name (DN)
- samAccountName
- userLogonName

```
Type: String[]
Parameter Sets: Identity
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-KeepBackupUnpacked**

Determines whether to save the unpacked backup after the search operation.  
If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:
```

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Name**

Retrieves objects whose Name attribute value is equal to the value specified in this parameter.  
The Name attribute stores object's relative distinguished name (RDN) which looks similar to the following: User 1\0ADEL:7dbac5c7-f38d-4270-8ac2-7a0674bc246b

Type: String[]  
Parameter Sets: Name  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Partition**

Specifies the distinguished name of the Active Directory partition from which you want to retrieve objects.  
If this parameter is omitted, the default naming context is used.  
This parameter is required if you specify an AD LDS (ADAM) instance host in the Server parameter

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Port**

Specifies the port number to connect to.  
If this parameter is set to 0 or omitted, the default LDAP port (389) is used.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SearchBase**

Specifies an Active Directory container in which to search for objects.  
The search is performed in the specified container and all its subcontainers.  
Specify the distinguished name (DN) of the container in which you want to search.

Type: String  
Parameter Sets: Name, Filter  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Server**

Specifies the Active Directory domain, domain controller, or AD LDS (ADAM) instance host from which you want the cmdlet to retrieve objects.

If this parameter is omitted, the cmdlet retrieves objects from any available domain controller in the current domain.

To specify a domain controller or AD LDS (ADAM) instance host, use the computer name or IP address.

If you specify an Active Directory domain name in this parameter, the cmdlet retrieves objects from any available domain controller in the specified domain.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-State**

Retrieves objects whose state is equal to any of the values specified in this parameter.

This parameter can take one of the following values: - All

- Deleted
- Live
- RecycledWhen specifying multiple values in this parameter, use a comma as a separator.

```
Type: ObjectState
Parameter Sets: (All)
Aliases:
Accepted values: Live, Deleted, Recycled, All
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Timeout**

Specifies the maximum wait time for retrieving the objects, in seconds.

The default value is 30.

```
Type: Int32
Parameter Sets: Name, Filter
Aliases:
```

```
Required: False
Position: Named
Default value: 30
Accept pipeline input: False
Accept wildcard characters: False
```

## **-UseSsl**

Specifies whether use Secure Sockets Layer (SSL) to encrypt the connection.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## **schema: 2.0.0**

# **Get-RMADReplicationConsole**

## **SYNOPSIS**

Gets all the RMAD consoles in the replication console list.

## **SYNTAX**

```
Get-RMADReplicationConsole [<CommonParameters>]
```

## **DESCRIPTION**

Gets all the RMAD consoles in the replication console list.

## EXAMPLES

### Example 1

```
PS C:\> C:\>Get-RMADReplicationConsole
```

This command gets all the RMAD consoles in the replication console list.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

### schema: 2.0.0

## Get-RMADReplicationSchedule

### SYNOPSIS

Allows you to get the replication schedule from a specified computer.

### SYNTAX

```
Get-RMADReplicationSchedule [<CommonParameters>]
```

### DESCRIPTION

Allows you to get the replication schedule from a specified computer.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADReplicationSchedule
```

This example illustrates how to get the replication schedule from a specified computer.

# PARAMETERS

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADReplicationSession

## SYNOPSIS

Retrieves information about replication sessions.

## SYNTAX

```
Get-RMADReplicationSession [[-Id] <Int32[]>] [<CommonParameters>]
```

## DESCRIPTION

Retrieves replication sessions.

Each replication session contains a set of properties including the session start time, end time, and replication result.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADReplicationSession
```

This command retrieves all the replication sessions.

## Example 2

```
PS C:\> Get-RMADReplicationSession -Id 1
```

This command retrieves the replication session by session ID.

# PARAMETERS

## -Id

Specifies the IDs of the replication sessions.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADReplicationSessionItem

## SYNOPSIS

Retrieves a list of remote consoles that are involved in the specified replication session.

## SYNTAX

### Session

```
Get-RMADReplicationSessionItem [-Session] <ReplicationSession>
[<CommonParameters>]
```

### Id

```
Get-RMADReplicationSessionItem [-SessionId] <Int32> [<CommonParameters>]
```

## DESCRIPTION

Retrieves a list of remote consoles that are involved in the specified replication session.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADReplicationSession -Id 1 | Get-RMADReplicationSessionItem
```

This command retrieves the remote consoles that are involved in the replication session whose ID is 1.

## PARAMETERS

### -Session

Specifies the replication session for which you want to return a list of remote consoles.

Type: ReplicationSession  
Parameter Sets: Session  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

### -SessionId

Specifies the replication session ID for which you want to return a list of remote consoles.

Type: Int32  
Parameter Sets: Id

Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADReportObject

## SYNOPSIS

Retrieves an object representing the online comparison or restore operation item.

## SYNTAX

```
Get-RMADReportObject [-SessionId <Int32[]>] [-SqlCredential <PSCredential>]
[<CommonParameters>]
```

## DESCRIPTION

Retrieves an object representing the online comparison or restore operation item.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADReportObject
```

This command retrieves an object representing the online comparison or restore operation item.

## Example 2

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectAttributes
```

This command retrieves an object representing the online comparison operation item attributes.

# PARAMETERS

## -SessionId

Specifies the compare or restore session identifier from which to get changed or restored objects. If this parameter is not set, the latest compare or restore session will be used.

Type: Int32[]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName)  
Accept wildcard characters: False

## -SqlCredential

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report.

The user name and password must be in the form of a PSCredential object.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADReportObjectAttributes

## SYNOPSIS

Retrieves an object representing the online comparison or restore operation item attributes.

## SYNTAX

```
Get-RMADReportObjectAttributes -ObjectId <Int32[]> [-SqlCredential <PSCredential>] [<CommonParameters>]
```

## DESCRIPTION

Retrieves an object representing the online comparison or restore operation item attributes.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectAttributes
```

This command retrieves an object representing the online comparison operation item attributes.

## PARAMETERS

### -ObjectId

Specifies changed or restored object identifier.

To get the object, use the Get-RMADReportObject cmdlet.

Type: Int32[]

Parameter Sets: (All)

Aliases:

```
Required: True
Position: Named
Default value: None
Accept pipeline input: True (ByPropertyName)
Accept wildcard characters: False
```

### **-SqlCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report.

The user name and password must be in the form of a PSCredential object.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Get-RMADReportObjectChildren**

## **SYNOPSIS**

Retrieves an object representing the online comparison or restore operation item child items.

## SYNTAX

```
Get-RMADReportObjectChildren -ObjectId <Int32[]> [-SqlCredential <PSCredential>] [<CommonParameters>]
```

## DESCRIPTION

Retrieves an object representing the online comparison or restore operation item child items.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADReportObject | Get-RMADReportObjectChildren
```

This command retrieves an object representing the online comparison or restore operation item child items.

## PARAMETERS

### -ObjectId

Specifies changed or restored object identifier.

To get the object, use the Get-RMADReportObject cmdlet.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: True (ByPropertyName)

Accept wildcard characters: False

### -SqlCredential

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report.

The user name and password must be in the form of a PSCredential object.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADReportSession

## SYNOPSIS

Retrieves an object representing the online comparison or restore operation report.

## SYNTAX

```
Get-RMADReportSession [-SessionId <Int32>] [-SqlCredential <PSCredential>]  
[<CommonParameters>]
```

## DESCRIPTION

Retrieves an object representing the online comparison or restore operation report.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADReportSession | Sort OperationDate
```

This command retrieves an object representing the online comparison or restore operation report.  
The report data is sorted by date.

## PARAMETERS

### -SessionId

Specifies the compare or restore session identifier.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-SqlCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report.

The user name and password must be in the form of a PSCredential object.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Get-RMADSession**

## **SYNOPSIS**

Retrieves an object representing Recovery Manager backup sessions.

# SYNTAX

## collection (Default)

```
Get-RMADSession [[-Collection] <ComputerCollection[]>] [-Result  
<SessionResult[]>] [-UseCache]  
[-DayCount <Int32>] [-StartType <SessionStartType>] [<CommonParameters>]
```

## collectionId

```
Get-RMADSession [[-CollectionId] <Int32[]>] [-Result <SessionResult[]>] [-  
UseCache] [-DayCount <Int32>]  
[-StartType <SessionStartType>] [<CommonParameters>]
```

## collectionName

```
Get-RMADSession [[-CollectionName] <String[]>] [-Result <SessionResult[]>]  
[-UseCache] [-DayCount <Int32>]  
[-StartType <SessionStartType>] [<CommonParameters>]
```

# DESCRIPTION

Retrieves an object representing one or more Recovery Manager backup sessions for a specified Computer Collection.

The retrieved object has such properties as names of the domain controllers that participated in the backup session, names of the domains to which the domain controllers belong, backup session result, and error messages, if any, encountered during the backup session.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADSession -CollectionName col1 -Result Error,Warning -  
DayCount 5
```

Returns backup sessions that ended with an error or warning and started in the recent 5 days for the Computer Collection named col1.

## Example 2

```
PS C:\> Get-RMADSession -CollectionName "Collection1"
```

Returns all backup sessions for the Computer Collection named Collection1.

# PARAMETERS

## -Collection

Specifies the name of the computer collection for which you want to retrieve backup sessions.

Type: ComputerCollection[]

Parameter Sets: collection

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-CollectionId**

Specifies the ID of the computer collection for which you want to retrieve backup sessions.

Type: Int32[]

Parameter Sets: collectionId

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-CollectionName**

Specifies the name of the computer collection for which you want to retrieve backup sessions.

Type: String[]

Parameter Sets: collectionName

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-DayCount**

Specifies the number of days within which the sessions you want to retrieve started.

If you omit this parameter, sessions are retrieved regardless of when they started.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Result**

Retrieves backup sessions based on their result.

If you omit this parameter, sessions are retrieved regardless of their result.

This parameter can take one of the following values:<sup>\*</sup> Success \* Error

- Warning
- Unknown
- Running
- Canceled
- Abandoned
- Pending
- Verifying

- Installing
- Working

Type: SessionResult[]  
 Parameter Sets: (All)  
 Aliases:  
 Accepted values: Success, Error, Warning, Unknown, Running, Canceled, Abandoned, Pending, Verifying, Installing, Working

Required: False  
 Position: Named  
 Default value: None  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-StartType**

Specifies to return either scheduled backup sessions or backup sessions that were started manually.  
 This parameter can take one of the following values: \* Manual - Specifies to return backup sessions that were started manually.

- Scheduled - Specifies to return scheduled backup sessions.

Type: SessionStartType  
 Parameter Sets: (All)  
 Aliases:  
 Accepted values: Manual, Scheduled

Required: False  
 Position: Named  
 Default value: None  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-UseCache**

Specifies to return the data from the cache.

Type: SwitchParameter  
 Parameter Sets: (All)  
 Aliases:  
  
 Required: False  
 Position: Named  
 Default value: False  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADSessionItem

## SYNOPSIS

Gets items from a specified backup creation session.

## SYNTAX

### session (Default)

```
Get-RMADSessionItem [-Session <Session[]>] [-Result <SessionResult[]>]  
[<CommonParameters>]
```

### sessionId

```
Get-RMADSessionItem [-SessionId <Int32[]>] [-Computer <String[]>] [-Result  
<SessionResult[]>]  
[<CommonParameters>]
```

## DESCRIPTION

Gets items from a specified backup creation session.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADSessionItem -Computer "Comp*"
```

This command gets all session items from all backup creation sessions created for the computers whose name starts with Comp.

# PARAMETERS

## -Computer

Gets items from the backup creation sessions run for the computer whose name specified in this parameter.  
This parameter accepts the asterisk (\*) wildcard.

Type: String[]  
Parameter Sets: sessionId  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Result

Gets items from the backup creation sessions that completed with the result specified in this parameter.

Type: SessionResult[]  
Parameter Sets: (All)  
Aliases:  
Accepted values: Success, Error, Warning, Unknown, Running, Canceled, Abandoned, Pending, Verifying, Installing, Working

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Session

Specifies the backup creation session from which to get session items.

Type: Session[]  
Parameter Sets: session  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -SessionId

Specifies the identifier of the backup creation session from which to get session items.

Type: Int32[]  
Parameter Sets: sessionId  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Get-RMADSessionItemEvent

## SYNOPSIS

Gets events from a specified backup creation session item.

## SYNTAX

### sessionItem (Default)

```
Get-RMADSessionItemEvent [-SessionItem] <SessionItem[]> [-Type <EventType[]>] [<CommonParameters>]
```

### sessionId

```
Get-RMADSessionItemEvent [-SessionItemId] <Int32[]> [-Type <EventType[]>] [<CommonParameters>]
```

## DESCRIPTION

Gets events from a specified backup creation session item.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADSessionItemEvent -Type Warning
```

Gets all Warning events for all backup creation sessions.

# PARAMETERS

## -SessionItem

Specifies the backup creation session item from which to get events.

```
Type: SessionItem[]  
Parameter Sets: sessionItem  
Aliases:
```

```
Required: False  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## -SessionItemId

Specifies the identifier of the backup creation session item from which to get events.

```
Type: Int32[]  
Parameter Sets: sessionItemId  
Aliases:
```

```
Required: False  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Type

Specifies the types of events to get.

This parameter accepts the following values for event types:  
\* Information \* Warning

- ErrorWhen specifying multiple event types, use a comma as a separator.

```
Type: EventType[]  
Parameter Sets: (All)  
Aliases:  
Accepted values: Information, Warning, Error
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Get-RMADStorageServer

## SYNOPSIS

Returns a list of registered secure storage servers.

## SYNTAX

```
Get-RMADStorageServer [ [-Name] <String>] [<CommonParameters>]
```

## DESCRIPTION

Returns a list of currently registered secure storage servers.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServer
```

Displays the list of currently registered storage servers.

### Example 2

```
PS C:\> Get-RMADStorageServer -Name storage.local
```

Displays a secure storage server with the 'storage.local' name, if any.

# PARAMETERS

## -Name

Specifies the name of a secure storage server to display.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

## String

# NOTES

# RELATED LINKS

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## schema: 2.0.0

# Get-RMADStorageServerAllowedVolumes

## SYNOPSIS

## SYNTAX

```
Get-RMADStorageServerAllowedVolumes [<CommonParameters>]
```

## DESCRIPTION

This cmdlet retrieves the volumes allowed for storing backups on a Secure Storage server. If the list is not configured, the Secure Storage server will automatically select an available volume when storing backups. When the volume is automatically selected it will not select the system volume.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServerAllowedVolumes
Retrieving volume policy...
```

```
Volumes
-----
{c: d:}
```

Retrieves the list of configured volumes on a Secure Storage server.

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## schema: 2.0.0

# Get-RMADStorageServerHardeningStatus

## SYNOPSIS

Retrieves the hardening status of the current server.

## SYNTAX

```
Get-RMADStorageServerHardeningStatus [<CommonParameters>]
```

## DESCRIPTION

This cmdlet retrieves the hardening status of the current server.  
Returns status for SMB Disabled, Is Hardened and Network Traffic Disabled.  
The server is hardened if all values are True.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServerHardeningStatus
```

| Name                   | Value |
|------------------------|-------|
| SMBDisabled            | True  |
| IsHardened             | True  |
| NetworkTrafficDisabled | True  |

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## schema: 2.0.0

# Get-RMADStorageServerRetentionPolicy

## SYNOPSIS

Retrieves the retention policy status of the current server.

## SYNTAX

```
Get-RMADStorageServerRetentionPolicy [<CommonParameters>]
```

## DESCRIPTION

This cmdlet retrieves the retention policy of the current server.

Returns the current value for number of days to keep backups and current value of IncludeLWTProcessing option.

IncludeLWTProcessing(Last Write Time) is used in cases the backups do not include a copy of backup details with the time the backup was created.

If IncludeLWTProcessing is set to true will tell the retention policy to check Last Write Time of the backup file and use that instead.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServerRetentionPolicy  
DaysToKeep IncludeLWTProcessing  
----- 5 False
```

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Import-RMADBackup

## SYNOPSIS

Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects.

## SYNTAX

### Paths

```
Import-RMADBackup [-Path] <String[]> [-IgnoreReadOnly] [<CommonParameters>]
```

### Definition

```
Import-RMADBackup -Definition <String> [-IgnoreReadOnly]  
[<CommonParameters>]
```

## DESCRIPTION

Reads the backup registration information from the .xml file and returns backup descriptions in the BackupInfo objects.

After you import backups, you need to register them with Recovery Manager so that the backups become available in the Recovery Manager user interface.

To register the backups, use the Add-RMADBackup cmdlet.

## EXAMPLES

### Example 1

```
PS C:\> Import-RMADBackup C:\ImportedBackups\RMADBackups.xml | Add-RMADBackup
```

Imports backups from the C:\ImportedBackups\RMADBackups.xml file to the Recovery Manager for Active Directory backup registration database on the computer where you are using this cmdlet.

Then, the Add-RMADBackup registers the imported backups with Recovery Manager for Active Directory.

## PARAMETERS

### -Definition

Specifies the registration information about the backups you want to import into the Recovery Manager for Active Directory backup registration database.

Type: String

Parameter Sets: Definition

Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

### **-Path**

Specifies the path to the .xml file that contains the registration information about the backups you want to import into the Recovery Manager for Active Directory backup registration database.

Type: String[]  
Parameter Sets: Paths  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Import-RMADFERecoveryCertificate

## SYNOPSIS

Imports Forest Recovery certificates.

## SYNTAX

```
Import-RMADFERecoveryCertificate [-Path] <String> [-Password]
<SecureString> [<CommonParameters>]
```

## DESCRIPTION

This cmdlet imports Forest Recovery certificates from the specified location. You must also supply the password that is used to protect the certificates.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Import-RMADFERecoveryCertificate -Path
C:\Certificates\RMADFeCertificates.pfx" -Password (ConvertTo-SecureString
"protection password" -AsPlainText -Force)
```

This command imports Forest Recovery certificates from the specified location.

## PARAMETERS

### -Password

Specifies the password that is used to access the Forest Recovery certificates.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Path

Specifies the full path to the Forest Recovery certificate file.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Install-RMADBackupAgent

## SYNOPSIS

Installs Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

## SYNTAX

### DC

```
Install-RMADBackupAgent [-Computer] <String> [[-Credentials] <PSCredential>] [[-ConfigureFirewall] <Boolean>] [-IgnoreReadOnly] [<CommonParameters>]
```

### Collection

```
Install-RMADBackupAgent [[-Credentials] <PSCredential>] [[-ConfigureFirewall] <Boolean>] [-CollectionName] <String> [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to install the Recovery Manager Backup Agent on a specified computer which can be a domain controller or AD LDS (ADAM) host, or on each computer in a particular Computer Collection.

## EXAMPLES

### Example 1

```
PS C:\> $credential = Get-Credential  
Install-RMADBackupAgent -Computer dc1 -Credentials $credential
```

This code connects to the computer "dc1" under the user represented by the "credential" object and installs Recovery Manager Backup Agent there.

### Example 2

```
PS C:\> Install-RMADBackupAgent -CollectionName "New Computer Collection"
```

This code installs the Recovery Manager Backup Agent on each computer in the collection named "New Computer Collection".

## PARAMETERS

### -CollectionName

Specifies the name of the Computer Collection that includes the computers on which Backup Agent should be installed.

Type: String  
Parameter Sets: Collection  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Computer

Specifies the name of the computer which can be domain controller or AD LDS (ADAM) host, where to install a Recovery Manager Backup Agent.

Type: String  
Parameter Sets: DC  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -ConfigureFirewall

Specifies whether Recovery Manager automatically configures Windows Firewall on target Windows Server 2008-based or Windows Server 2012-based DCs to allow backup operations.

Type: Boolean  
Parameter Sets: (All)

Aliases:

```
Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Credentials

Specifies the user name and the password of the user account to use for connecting to the target computer and installing Backup Agent.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes: \* The user should be a local Administrator on the target computer.

- If you omit this parameter, Backup Agent will be installed under the current user account.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Install-RMADFERecoveryAgent

## SYNOPSIS

Installs Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.

## SYNTAX

### ProjectSpecificParameters (Default)

```
Install-RMADFERecoveryAgent [-ComputerName] <String> [<CommonParameters>]
```

### ProjectLessNormalMode

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential> [<CommonParameters>]
```

### ProjectLessBothMode

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential  
<PSCredential>  
-DsrmCredential <PSCredential> [<CommonParameters>]
```

### ProjectLessDsrm

```
Install-RMADFERecoveryAgent [-ComputerName] <String> -DsrmCredential  
<PSCredential> [<CommonParameters>]
```

## DESCRIPTION

Allows you to install Forest Recovery Agent on a specified domain controller or on each domain controller in the forest.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-SecureString "password" -AsPlainText -Force)
```

```
Install-RMADFERecoveryAgent -Name dc1.RMAD.local
```

Installs Forest Recovery Agent on the specified domain controller in the RMADFE project.

## EXAMPLE 2

```
PS C:\> $credentilas = New-Object PSCredential(".\Administrator", (ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Install-RMADFERecoveryAgent -name dc1.RMAD.local -DcCredential $credentilas -DsrmCredential $credentilas
```

Installs Forest Recovery Agent on the specified domain controller (either in Normal or DSRM mode). In this example, you should use only domain credentials or DSRM credentials, or both.

# PARAMETERS

## -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential

Parameter Sets: ProjectLessNormalMode, ProjectLessBothMode

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -DsrmCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential

Parameter Sets: ProjectLessBothMode, ProjectLessDsrm

Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# New-RMADCollection

## SYNOPSIS

Creates a new computer collection.

## SYNTAX

```
New-RMADCollection [[-Name] <String>] [-Temporary] [-IgnoreReadOnly]
[<CommonParameters>]
```

## DESCRIPTION

Creates a new computer collection with a default name or with the name you specify. The new computer collection is created using the default computer collection parameters set in the Recovery Manager console.

# EXAMPLES

## Example 1

```
PS C:\> New-RMADCollection -Name Collection1
```

This command creates a new computer collection named Collection1.

## Example 2

```
PS C:\> New-RMADCollection Collection1 -Temporary
```

This command creates a new temporary computer collection from the existing collection named Collection1.

# PARAMETERS

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -Name

Allows you to specify a name for the computer collection to be created.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

## -Temporary

Creates a new temporary computer collection.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# New-RMADFEProject

## SYNOPSIS

Creates a new RMADFE project in the file system.

## SYNTAX

### AD (Default)

```
New-RMADFEProject -Domain <String> -Credential <PSCredential>
[<CommonParameters>]
```

### Backup

```
New-RMADFEProject -Backup <BackupInfo> [-BackupPassword <SecureString>]
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet creates a new RMADFE project in the file system.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> $backupInfo = Get-RMADBackupInfo -Path "C:\RMAD_TEMP\backup.bak"
```

```
New-RMADFEProject -Backup $backupInfo -BackupPassword (ConvertTo-SecureString "Backup Password" -AsPlainText -Force)
```

This example demonstrates how to create a new project from a backup.

# PARAMETERS

## -Backup

Specifies the backup that contains the data to be restored.

Type: BackupInfo

Parameter Sets: Backup

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -BackupPassword

Specifies the password to access a password-protected backup.

Type: SecureString

Parameter Sets: Backup

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -Credential

Specifies credentials to access the domain controller.

Type: PSCredential

Parameter Sets: AD

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -Domain

Specifies the fully qualified domain name.

Type: String

Parameter Sets: AD

Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# New-RMADFERecoveryMedia

## SYNOPSIS

Creates a new Recovery Media ISO in the file system.

## SYNTAX

### FromWsb (Default)

```
New-RMADFERecoveryMedia -IsoPath <String> -WsbPath <String> [-IpAddress <String>] [-DriversFolder <String>] [-SubnetMask <String>] [-DefaultGateway <String>] [-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

### FromWim

```
New-RMADFERecoveryMedia -IsoPath <String> -WimPath <String> [-IpAddress <String>] [-DriversFolder <String>]
```

```
[-SubnetMask <String>] [-DefaultGateway <String>] [-AllowAddCustomDrivers <Boolean>]
[-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

## FromBmr

```
New-RMADFERecoveryMedia -IsoPath <String> -BmrPath <String> [-
BackupPassword <SecureString>]
[-IpAddress <String>] [-DriversFolder <String>] [-SubnetMask <String>] [-
DefaultGateway <String>]
[-AllowAddCustomDrivers <Boolean>] [-AllowAddCustomDriversFromBackup <Boolean>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet creates a new Recovery Media ISO in the file system.

## EXAMPLES

### Example 1

```
PS C:\> New-RMADFERecoveryMedia -WimPath C:\Recovery\WindowsRE\WinRe.wim -
IsoPath C:\ProgramData\Quest\RecoveryMedia\QuestWinRe.iso
```

This example illustrates how to create the Recovery Media from the Windows Recovery Environment image.

### Example 2

```
PS C:\> New-RMADFERecoveryMedia -WsbPath \\BackupServer\Storage\Backup1 -
IsoPath C:\ProgramData\Quest\RecoveryMedia\QuestWinRe.iso
```

This example illustrates how to create the Recovery Media from the Windows Server backup.

## PARAMETERS

### -AllowAddCustomDrivers

Turns on the ability to set up custom drivers.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -AllowAddCustomDriversFromBackup

Turns on the ability to set up custom drivers from the backup.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access a password-protected backup.  
This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString  
Parameter Sets: FromBmr  
Aliases: Password

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BmrPath**

Specifies a path to Bare Metal Recovery backup.

Type: String  
Parameter Sets: FromBmr  
Aliases: Bmr

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DefaultGateway**

Specifies the preconfigured Default Gateway to be used for the generated Recovery Media Bare Metal Console

Type: String  
Parameter Sets: (All)  
Aliases: Gateway

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DriversFolder**

Specifies the folder for custom drivers.

Type: String  
Parameter Sets: (All)  
Aliases: Drivers

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-IpAddress**

Specifies the preconfigured IP Address to be used for the generated Recovery Media Bare Metal Console

Type: String

Parameter Sets: (All)

Aliases: Ip

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-IsoPath**

Path to the output Quest Recovery Environment image file

Type: String

Parameter Sets: (All)

Aliases: Iso, Output

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-SubnetMask**

Specifies the preconfigured Subnet Mask to be used for the generated Recovery Media Bare Metal Console

Type: String

Parameter Sets: (All)

Aliases: Subnet

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-WimPath**

Path to Windows Image file

Type: String

Parameter Sets: FromWim

Aliases: Wim

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-WsbPath**

Path to Windows Server Backup

Type: String

Parameter Sets: FromWsb

Aliases: Wsb

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# New-RMADSchedule

## SYNOPSIS

Creates a schedule for the backup creation operation you want to perform on a particular computer collection.

## SYNTAX

### Once

```
New-RMADSchedule [-Once] -StartDate <DateTime> [-MinutesDuration <UInt32>]
[-MinutesInterval <UInt32>]
[<CommonParameters>]
```

### Daily

```
New-RMADSchedule [-Daily] -DaysInterval <Int32> -StartDate <DateTime> [-
EndDate <DateTime>]
[-MinutesDuration <UInt32>] [-MinutesInterval <UInt32>]
[<CommonParameters>]
```

## **Weekly**

```
New-RMADSchedule [-Weekly] -WeeksInterval <Int32> -DaysOfWeek  
<DaysOfTheWeek> -StartDate <DateTime>  
[-EndDate <DateTime>] [-MinutesDuration <UInt32>] [-MinutesInterval  
<UInt32>] [<CommonParameters>]
```

## **MonthlyDate**

```
New-RMADSchedule [-MonthlyDate] -Day <Int32> [-Months <Months>] -StartDate  
<DateTime> [-EndDate <DateTime>]  
[-MinutesDuration <UInt32>] [-MinutesInterval <UInt32>]  
[<CommonParameters>]
```

## **MonthlyDOW**

```
New-RMADSchedule [-MonthlyDOW] [-DaysOfWeek <DaysOfTheWeek>] [-Months  
<Months>] -Week <WhichWeek>  
-StartDate <DateTime> [-EndDate <DateTime>] [-MinutesDuration <UInt32>] [-  
MinutesInterval <UInt32>]  
[<CommonParameters>]
```

# **DESCRIPTION**

Creates a schedule to perform the backup creation operation a particular computer collection.  
You can use the parameters of this cmdlet to set a recurring or non-recurring schedule for the backup creation operation.

# **EXAMPLES**

### **Example 1**

```
PS C:\> New-RMADSchedule -Once -StartDate "2/20/2008 1:00"
```

Runs the backup creation operation at 1:00 a.m.  
on the 20th February 2008.

### **Example 2**

```
PS C:\> New-RMADSchedule -Daily -StartDate "2/20/2008 1:00" -DaysInterval 3
```

Runs the backup creation operation every 3 days, starting from 1:00 a.m.  
on the 20th February 2008.

### **Example 3**

```
PS C:\> New-RMADSchedule -Weekly -StartDate "2/20/2008 1:00" -WeeksInterval  
2 -DaysOfWeek Monday,Friday
```

Runs the backup creation operation on Monday and Friday of every second week, starting from 1:00 a.m.  
on the 20th February 2008.

### **Example 4**

```
PS C:\> New-RMADSchedule -MonthlyDate -StartDate "2/20/2008 1:00" -Day 1
```

Runs the backup creation operation on every first day of each month (the Months parameter is omitted, therefore the backup creation operation is invoked each month), starting from 1:00 a.m.  
on the 20th February 2008.

## Example 5

```
PS C:\> New-RMADSchedule -MonthlyDOW -StartDate "2/20/2008 1:00" -  
DaysOfWeek 1,5 -Week 1
```

Runs the backup creation operation on every first Monday and Friday of each month, starting from 1:00 a.m. on the 20th February 2008.

# PARAMETERS

### -Daily

Runs the backup creation operation on a daily basis.

Type: SwitchParameter

Parameter Sets: Daily

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -Day

Sets the day of the month when you want to run the backup creation operation.

Type: Int32

Parameter Sets: MonthlyDate

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -DaysInterval

Sets an interval (in number of days) between invocations of the backup creation operation.

Type: Int32

Parameter Sets: Daily

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -DaysOfWeek

Runs the backup creation operation on particular days of week.

To set the weeks when you want to run the backup creation operation, use the Weekly or MonthlyDOW parameter.

Type: DaysOfTheWeek

Parameter Sets: Weekly

Aliases:

Accepted values: Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: DaysOfTheWeek  
Parameter Sets: MonthlyDOW  
Aliases:  
Accepted values: Sunday, Monday, Tuesday, Wednesday, Thursday, Friday, Saturday

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-EndDate**

Specifies the date when the backup creation operation schedule expires.

Type: DateTime  
Parameter Sets: Daily, Weekly, MonthlyDate, MonthlyDOW  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MinutesDuration**

Specifies the time period (in minutes) during which you want to repeatedly run (invoke) the backup creation operation.

To set the time interval between invocations of the backup creation operation, use the MinutesInterval parameter.

Type: UInt32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MinutesInterval**

Specifies the time interval (in minutes) between invocations of the backup creation operation.

To set the time period during which you want to repeatedly run (invoke) the backup creation operation, use the MinutesDuration parameter.

Type: UInt32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MonthlyDate**

Runs the backup creation operation on particular day of month.  
To set the months and day of month when you want to run the backup creation operation, use the Months and Day parameters respectively.

Type: SwitchParameter  
Parameter Sets: MonthlyDate  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-MonthlyDOW**

Runs the backup creation operation on particular days of week in particular months.  
To set the months, weeks, and days of week, use the Months, Week, and DaysOfWeek parameters respectively.

Type: SwitchParameter  
Parameter Sets: MonthlyDOW  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Months**

Sets the months when you want to run the backup creation operation.

Type: Months  
Parameter Sets: MonthlyDate, MonthlyDOW  
Aliases:  
Accepted values: January, February, March, April, May, June, July, August, September, October, November, December

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Once**

Runs the backup creation operation only once.

Type: SwitchParameter  
Parameter Sets: Once  
Aliases:

Required: True  
Position: Named  
Default value: False  
Accept pipeline input: False

Accept wildcard characters: False

## **-StartDate**

Specifies the date when the backup creation operation schedule comes into effect.

Type: DateTime

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Week**

Sets the week of the month when you want to run the backup creation operation.

This parameter accepts the following values:<sup>\*</sup> 1.

Specifies the first week of the month.

- 2.  
Specifies the second week of the month.
- 3.  
Specifies the third week of the month.
- 4.  
Specifies the fourth week of the month.
- 5.  
Specifies the fifth week of the month.

Type: WhichWeek

Parameter Sets: MonthlyDOW

Aliases:

Accepted values: None, FirstWeek, SecondWeek, ThirdWeek, FourthWeek, LastWeek

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Weekly**

Runs the backup creation operation on a weekly basis.

Type: SwitchParameter

Parameter Sets: Weekly

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WeeksInterval**

Sets an interval (in number of weeks) between invocations of the backup creation operation.

Type: Int32

Parameter Sets: Weekly

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## **schema: 2.0.0**

# **Open-RMADFEProject**

## **SYNOPSIS**

Opens the RMADFE project.

## **SYNTAX**

```
Open-RMADFEProject [-Path] <String> [-Password] <SecureString>
[<CommonParameters>]
```

## **DESCRIPTION**

This cmdlet opens the RMADFE project from the specified location.

You must also supply the password that is used to access the project content.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\RMADFEProjects\SampleProject.frproj -  
Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
```

This command opens SampleProject.frproj from the specified location.

# PARAMETERS

## -Password

Specifies the password that is used to access the RMADFE project content.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Path

Specifies the path to the existing RMADFE project file.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Protect-RMADSecureStorageServer

## SYNOPSIS

Enables storage server hardening.

## SYNTAX

### Name

```
Protect-RMADSecureStorageServer [-IgnoreReadOnly] [-Name] <String> [-WhatIf] [-Confirm] [<CommonParameters>]
```

### Server

```
Protect-RMADSecureStorageServer [-IgnoreReadOnly] [-Server] <StorageServer> [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Enables storage server hardening.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServer | Protect-RMADSecureStorageServer
```

Enables hardening on all registered secure storage servers.

### Example 2

```
PS C:\> Protect-RMADSecureStorageServer -Name "storage.srv"
```

Enables hardening on the specified storage server.

## PARAMETERS

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Name**

Specifies the name of the secure storage server.

```
Type: String
Parameter Sets: Name
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **-Server**

Specifies the secure storage server. Use Get-RMADStorageServer to get a list of all secure storage servers.

```
Type: StorageServer
Parameter Sets: Server
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **-Confirm**

Prompts you for confirmation before running the cmdlet.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-WhatIf**

Shows what would happen if the cmdlet runs.

The cmdlet is not run.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## **schema: 2.0.0**

# **Protect-RMADStorageServer**

## **SYNOPSIS**

Enable storage server hardening.

## **SYNTAX**

```
Protect-RMADStorageServer [-Wait] [-Port <Int32>] [<CommonParameters>]
```

## **DESCRIPTION**

Enable storage server hardening.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADStorageServer | Protect-RMADStorageServer
```

Enables hardening on all registered secure storage servers.

## Example 3

```
PS C:\> Protect-RMADStorageServer -Name "storage.srv"
```

Enables hardening on the specified storage server.

# PARAMETERS

## -Port

Port used to connect to the secure storage agent

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -Wait

@{Text=}

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

**schema: 2.0.0**

# Publish-RMADBackupSecurityStatus

## SYNOPSIS

Publishes security check information for a specified backup.

## SYNTAX

```
 Publish-RMADBackupSecurityStatus -BackupGuid <Guid[]> -SecurityStatus  
<BackupSecurityStatus>  
 [<CommonParameters>]
```

## DESCRIPTION

Saves security check information for a specified backup registered with Recovery Manager for Active Directory.

## EXAMPLES

### Example 1

```
PS C:\> $bkf = (Get-RMADBackup -ComputerName DC.DomainName.local) [-1]  
$status = New-Object -TypeName  
QuestSoftware.RecoveryManager.AD.PowerShell.BackupSecurityStatus  
$status.Summary = "Passed"
```

```
$status.Details = "some passed"
$status.CheckDate = Get-Date
Publish-RMADBackupSecurityStatus -BackupGuid $bkf.backupGuid -
SecurityStatus $status
Get-RMADBackupSecurityStatus -BackupGuid $bkf.BackupGuid
```

For troubleshooting only.

This command saves antimalware scan results for a specified backup registered with Recovery Manager for Active Directory.

## PARAMETERS

### **-BackupGuid**

This is the GUID of the backup for which a user wants to get the antimalware scan results.

Type: Guid[]

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-SecurityStatus**

Result information about the security check of a particular backup.

Type: BackupSecurityStatus

Parameter Sets: (All)

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Refresh-RMADStorageServer

## SYNOPSIS

Refreshes current information of the secure storage server.

## SYNTAX

### Name

```
Refresh-RMADStorageServer [-IgnoreReadOnly] [-Name] <String>
[<CommonParameters>]
```

### Server

```
Refresh-RMADStorageServer [-IgnoreReadOnly] [-Server] <StorageServer>
[<CommonParameters>]
```

## DESCRIPTION

Connects to the secure storage server and retrieves the current status (agent state and hardening state).

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADStorageServer | Refresh-RMADStorageServer
```

Updates statuses of all registered secure storage servers.

### Example 2

```
PS C:\> Refresh-RMADStorageServer -Name "storage.srv"
```

Refreshes the status of the specified secure storage server.

## PARAMETERS

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False

```
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Name**

Specifies the name of the secure storage server.

```
Type: String  
Parameter Sets: Name  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **-Server**

Specifies the secure storage server. Use Get-RMADStorageServer to get a list of all secure storage servers.

```
Type: StorageServer  
Parameter Sets: Server  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Register-RMADSecureStorageBackups

## SYNOPSIS

Registers backups on an existing secure storage server in a Recovery Manager database.

## SYNTAX

### Name

```
Register-RMADSecureStorageBackups [-IgnoreReadOnly] [-Name] <String>
[<CommonParameters>]
```

### Server

```
Register-RMADSecureStorageBackups [-IgnoreReadOnly] [-Server]
<StorageServer> [<CommonParameters>]
```

## DESCRIPTION

Registers backups on an existing secure storage server in a Recovery Manager database so that the backups become available in the Recovery Manager user interface.

## EXAMPLES

### Example 1

```
PS C:\> Register-RMADSecureStorageBackups -Name "storage.srv"
Registers backups on a specified storage server.
```

## PARAMETERS

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Name**

Specifies the name of the secure storage server.

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-Server**

Specifies the secure storage server. Use Get-RMADStorageServer to get a list of all secure storage servers.

Type: StorageServer

Parameter Sets: Server

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

### **System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## **OUTPUTS**

### **System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Remove-RMADBackup

## SYNOPSIS

Allows you to selectively unregister backups from the Recovery Manager backup registration database.

## SYNTAX

### Instance

```
Remove-RMADBackup [-InputObject] <BackupInfo[]> [-Delete <Boolean>] [-ShareCredential <PSCredential>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

### Id

```
Remove-RMADBackup [-Id] <Int32[]> [-Delete <Boolean>] [-ShareCredential <PSCredential>] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Allows you to selectively unregister backups from the Recovery Manager backup registration database. Optionally, you can delete the unregistered backups from their location.

## EXAMPLES

### Example 1

```
PS C:\> Get-RMADBackup | Where-Object {$_ .Date -lt (Get-Date) .AddDays(-15)} | Remove-RMADBackup -Delete $true
```

Gets all backups created by Recovery Manager for Active Directory in the last 15 days, unregisters these backups from the backup registration database, and then deletes the backup files.

## PARAMETERS

### -Delete

Specifies to delete the backups being unregistered from their locations.  
This parameter can take one of the following values: - \$true

- \$false

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Id**

Specifies the IDs of the backups you want to unregister from the Recovery Manager backup registration database.

If you use this parameter, omit the InputObject parameter of this cmdlet.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-InputObject**

Specifies the IBackupInfo objects representing the backups you want to unregister from the Recovery Manager backup registration database.

If you use this parameter, omit the Id parameter of this cmdlet.

```
Type: BackupInfo[]  
Parameter Sets: Instance  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **-ShareCredential**

Specifies credential for share folder that contains the backup in case of -delete flag is true.

```
Type: PSCredential  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Confirm**

Prompts for a confirmation before executing the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Remove-RMADBackupAgent

## SYNOPSIS

Removes Recovery Manager Backup Agent from a specified computer, or its registration information from the Recovery Manager Console.

## SYNTAX

```
Remove-RMADBackupAgent [-Computer] <String> [[-Credentials] <PSCredential>]  
[-Uninstall] [-IgnoreReadOnly]  
[<CommonParameters>]
```

## DESCRIPTION

Allows you to completely remove Recovery Manager Backup Agent from a specified computer. You can also select to remove only registration information that relates to a particular Backup Agent from the Recovery Manager Console. This may be useful if you removed Backup Agent from a computer manually but the related agent entry remains on the Backup Agent Management node of the Recovery Manager Console.

## EXAMPLES

### Example 1

```
PS C:\> Remove-RMADBackupAgent -Computer "dc1"
```

This code removes registration information that relates to Backup Agent installed on the computer "dc1" from the Recovery Management Console.

### Example 2

```
PS C:\> $credential = Get-Credential  
Remove-RMADBackupAgent -Computer "dc1" -Credentials $credential -Uninstall
```

This code connects to the computer "dc1" under the user represented by the "credential" object and removes Backup Agent from it.

Note that corresponding Backup Agent registration information is removed from the Recovery Management Console as well.

## PARAMETERS

### -Computer

Specifies the name of the computer from which to remove Recovery Manager Backup Agent.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Credentials

Specifies the user name and the password of the user account to use for connecting to the target computer and removing Backup Agent.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes: \* The user should be a local Administrator on the target computer.

- If you omit this parameter, Backup Agent will be removed under the current user account.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Uninstall

Specifies whether the Recovery Manager Backup Agent should be completely removed.  
If this parameter is omitted, only the agent registration information will be removed.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Remove-RMADCollection

## SYNOPSIS

Deletes specified Computer Collections.

## SYNTAX

### Name (Default)

```
Remove-RMADCollection [-Name] <String[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

### InputObject

```
Remove-RMADCollection [-InputObject] <ComputerCollection[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

### Id

```
Remove-RMADCollection [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Deletes the Computer Collections that have the specified name or are represented by the specified objects.

## EXAMPLES

### Example 1

```
PS C:\> Remove-RMADCollection -Name "New Computer Collection"
```

Deletes the computer collection named New Computer Collection.

## Example 2

```
PS C:\> Get-RMADCollection | Where-Object {$_ .Schedule.Count -eq 0} | Remove-RMADCollection
```

The Get-RMADCollection cmdlet gets all computer collections.

The Where-Object cmdlet then filters out the collections for which no backup creation operation is scheduled.

The pipeline operator passes the filtered collection objects to the Remove-RMADCollection cmdlet, which deletes these collection objects.

# PARAMETERS

## -Id

Specifies the identifier of the Computer Collection to delete.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -InputObject

Deletes Computer Collections represented by the specified collection objects.

Enter a variable that contains the objects or type a command or expression that gets the objects.

Type: ComputerCollection[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## -Name

Specifies the name of the Computer Collection to be deleted.

Type: String[]

Parameter Sets: Name  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName)  
Accept wildcard characters: False

## **-Confirm**

Prompts for confirmation before executing the command.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: cf

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: wi

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Remove-RMADCollectionItem

## SYNOPSIS

Removes items from a specified Computer Collection.

## SYNTAX

```
Remove-RMADCollectionItem [-Collection] <String[]> [-Item] <String[]> [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to selectively remove items from the Computer Collection you specify.

## EXAMPLES

### Example 1

```
PS C:\> Remove-RMADCollectionItem -Collection Collection1 -Item Comp1
```

Removes the item named Comp1 from the Computer Collection named Collection1.

## PARAMETERS

### -Collection

Specifies the Computer Collection from which to remove items.

To specify a Computer Collection, type the Computer Collection name in this parameter.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

#### **-Item**

Specifies items to remove from the Computer Collection.  
To specify an item, type the item name in this parameter.

Type: String[]  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

#### **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## **schema: 2.0.0**

# **Remove-RMADFECloudStorage**

## **SYNOPSIS**

Removes a registered cloud storage from Recovery Manager for Active Directory.

## **SYNTAX**

### **Id**

Remove-RMADFECloudStorage [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]

## **InputObject**

```
Remove-RMADFECloudStorage [-InputObject] <CloudStorage[]> [-IgnoreReadOnly]
[-WhatIf] [-Confirm]
[<CommonParameters>]
```

## **DESCRIPTION**

Removes a registered cloud storage from Recovery Manager for Active Directory. Only storage registration in Recovery Manager will be removed; backup and any other data on the cloud storage is not affected.

## **EXAMPLES**

### **Example 1**

```
PS C:\> Get-RMADFECloudStorage
PS C:\> Remove-RMADFECloudStorage -Id 1
```

Removes cloud storage specified by the Id parameter.

### **Example 2**

```
PS C:\> Get-RMADFECloudStorage | Remove-RMADFECloudStorage -Confirm:$false
```

Remove all registered cloud storages without a confirmation.

## **PARAMETERS**

### **-Id**

Specifies the cloud storage Id representing the storage you want to unregister from the Recovery Manager.

Type: Int32[]
Parameter Sets: Id
Aliases: StorageId

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False

## **-InputObject**

Specifies the CloudStorage object representing the storage you want to unregister from the Recovery Manager. If you use this parameter, omit the Id parameter of this cmdlet.

Type: CloudStorage[]  
Parameter Sets: InputObject  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **-Confirm**

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: cf

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-WhatIf**

Shows what would happen if the cmdlet runs.

The cmdlet is not run.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: wi

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Remove-RMADFECloudStorageUploadSession

## SYNOPSIS

Removes an existing cloud storage upload session.

## SYNTAX

### **Id**

```
Remove-RMADFECloudStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

### **InputObject**

```
Remove-RMADFECloudStorageUploadSession [-InputObject] <UploadSession[]> [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Removes an existing cloud storage upload session. Only session information in Recovery Manager for Active Directory will be removed; backup and any other data on the cloud storage is not affected.

# EXAMPLES

## Example 1

```
PS C:\> Get-RMADFECloudStorageUploadSession | Remove-RMADFECloudStorageUploadSession
```

Removes all registered upload sessions without a confirmation.

## Example 2

```
PS C:\> Remove-RMADFECloudStorageUploadSession -Id 1
```

Removes a specific registered upload session with the session Id of 1.

# PARAMETERS

## -Id

Specifies the upload session Id representing the upload session you want to remove from the history in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -InputObject

Specifies the UploadSession object representing the cloud storage upload session you want to unregister from Recovery Manager for Active Directory. If you use this parameter, omit the Id parameter of this cmdlet.

Type: UploadSession[]

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-Confirm**

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Shows what would happen if the cmdlet runs.

The cmdlet is not run.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Remove-RMADFERecoveryAgent

## SYNOPSIS

Removes Forest Recovery Agent from a specified domain controller, or its registration information from Forest Recovery Console.

## SYNTAX

### ProjectSpecificParameters (Default)

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> [<CommonParameters>]
```

### ProjectLessNormalMode

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential <PSCredential> [<CommonParameters>]
```

### ProjectLessBothMode

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DcCredential <PSCredential> -DsrmCredential <PSCredential> [<CommonParameters>]
```

### ProjectLessDsrm

```
Remove-RMADFERecoveryAgent [-ComputerName] <String> -DsrmCredential <PSCredential> [<CommonParameters>]
```

## DESCRIPTION

Allows you to completely remove Forest Recovery Agent from a specified domain controller.  
You can also select to remove only registration information that relates to a particular Forest Recovery Agent from Forest Recovery Console.  
This may be useful if you removed Forest Recovery Agent from a domain controller manually, but the related agent entry remains in Forest Recovery Console.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Open-RMADFEProject -Path C:\rmadfe.frproj -Password (ConvertTo-SecureString "password" -AsPlainText -Force)
```

```
Remove-RMADFERecoveryAgent -Name dc1.RMAD.local
```

Removes Forest Recovery Agent from the specified domain controller in the RMADFE project.

### EXAMPLE 2

```
PS C:\> $credentilas = New-Object PSCredential(".\Administrator", (ConvertTo-SecureString 'Password' -AsPlainText -Force))
```

```
Remove-RMADFERecoveryAgent -name dc1.RMAD.local -DcCredential $credentialas  
-DsrmCredential $credentialas
```

Removes Forest Recovery Agent from the specified domain controller (either in Normal or DSRM mode). In this example, you should use only domain credentials or DSRM credentials, or both.

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -DcCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.

Type: PSCredential

Parameter Sets: ProjectLessNormalMode, ProjectLessBothMode

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -DsrmCredential

Specifies the user name and password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM).

Type: PSCredential

Parameter Sets: ProjectLessBothMode, ProjectLessDsrm

Aliases:

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Remove-RMADFESchedule

## SYNOPSIS

Removes an existing verification schedule for the RMADFE project.

## SYNTAX

```
Remove-RMADFESchedule [-Credential] <PSCredential> [-WhatIf] [-Confirm]
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet allows you to remove the verification schedule for the RMADFE project.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Remove-RMADFESchedule
```

Removes the current project schedule.

## PARAMETERS

### -Credential

Specifies credentials that will be used to run the command.

Type: PSCredential

Parameter Sets: (All)

Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Confirm

Prompts for confirmation before executing the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -WhatIf

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Remove-RMADReplicationConsole

## SYNOPSIS

Removes an RMAD console from the replication console list.

## SYNTAX

### **Id**

```
Remove-RMADReplicationConsole [-Id] <Int32[]> [<CommonParameters>]
```

### **ComputerName**

```
Remove-RMADReplicationConsole [-ComputerName] <String[]>  
[<CommonParameters>]
```

### **InputObject**

```
Remove-RMADReplicationConsole [-InputObject] <ReplicationConsole[]>  
[<CommonParameters>]
```

## DESCRIPTION

Removes the specified RMAD console or replication consoles from the replication console list.

## EXAMPLES

### **Example 1**

```
PS C:\> C:\> Remove-RMADReplicationConsole Hostname1
```

This command removes the RMAD console on Hostname1 from the replication console list.

### **Example 2**

```
PS C:\> C:\> Remove-RMADReplicationConsole -Id 1
```

This command removes the RMAD console with specified ID from the replication console list.

### **Example 3**

```
PS C:\> C:\> Get-RMADReplicationConsole | Remove-RMADReplicationConsole
```

This command removes all the replication consoles from the replication console list.

## PARAMETERS

### **-ComputerName**

Specifies the hostname of the replication console you want to remove.

```
Type: String[]
Parameter Sets: ComputerName
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

## -Id

Specifies the ID of the replication console you want to remove.

```
Type: Int32[]
Parameter Sets: Id
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByPropertyName, ByValue)
Accept wildcard characters: False
```

## -InputObject

Specifies the replication console object you want to remove.

```
Type: ReplicationConsole[]
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Remove-RMADReplicationSchedule

## SYNOPSIS

Allows you to remove the replication schedule from a specified computer.

## SYNTAX

```
Remove-RMADReplicationSchedule [<CommonParameters>]
```

## DESCRIPTION

Allows you to remove the replication schedule from a specified computer.

## EXAMPLES

### Example 1

```
PS C:\> Remove-RMADReplicationSchedule
```

## PARAMETERS

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Remove-RMADReplicationSession

## SYNOPSIS

Deletes replication sessions from the replication history.

## SYNTAX

### Session

```
Remove-RMADReplicationSession [-Session] <ReplicationSession[]>
[<CommonParameters>]
```

### Id

```
Remove-RMADReplicationSession [-Id] <Int32[]> [<CommonParameters>]
```

## DESCRIPTION

Deletes one or more replication sessions from the replication history.

## EXAMPLES

### Example 1

```
PS C:\> Remove-RMADReplicationSession -Id 1
```

This command deletes the replication session whose ID is 1.

### Example 2

```
PS C:\> Get-RMADReplicationSession | Remove-RMADReplicationSession
```

This command clears the replication history.

## PARAMETERS

### -Id

Specifies the IDs of replication sessions for deleting.

Type: Int32[]

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-Session**

Specifies the replication sessions for deleting.

Type: ReplicationSession[]

Parameter Sets: Session

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## **schema: 2.0.0**

# **Remove-RMADStorageServer**

## **SYNOPSIS**

Removes the secure storage server.

## **SYNTAX**

### **Name**

```
Remove-RMADStorageServer [-IgnoreReadOnly] [-Name] <String> [-WhatIf] [-Confirm] [<CommonParameters>]
```

## **Server**

```
Remove-RMADStorageServer [-IgnoreReadOnly] [-Server] <StorageServer> [-WhatIf] [-Confirm] [<CommonParameters>]
```

## **DESCRIPTION**

Removes currently registered secure storage servers.

## **EXAMPLES**

### **Example 1**

```
PS C:\> Remove-RMADStorageServer -Name "backupsrv01.acme.test"
```

Removes the specified secure storage server.

### **Example 2**

```
PS C:\> Get-RMADStorageServer | Remove-RMADStorageServer
```

Removes all registered secure storage servers.

## **PARAMETERS**

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-Name**

Specifies the name of the registered storage server (DNS name or IP address).

Type: String  
Parameter Sets: Name  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

### **-Server**

Specifies the secure storage server object.

Type: StorageServer  
Parameter Sets: Server  
Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **-Confirm**

Prompts you for confirmation before running the cmdlet.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-WhatIf**

Shows what happens when you run the cmdlet. The cmdlet does not actually run.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: `-Debug`, `-ErrorAction`, `-ErrorVariable`, `-InformationAction`, `-InformationVariable`, `-OutVariable`, `-OutBuffer`, `-PipelineVariable`, `-Verbose`, `-WarningAction`, and `-WarningVariable`. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

**schema: 2.0.0**

# Remove-RMADUnpackedComponent

## SYNOPSIS

Allows you to delete components (data) unpacked from specified backups.

## SYNTAX

### Instance

```
Remove-RMADUnpackedComponent [-InputObject] <BackupInfo[]> [-  
IgnoreReadOnly] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

### Id

```
Remove-RMADUnpackedComponent [-Id] <Int32[]> [-IgnoreReadOnly] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

## DESCRIPTION

Allows you to delete all components (data) unpacked from specified backups and saved in the Recovery Manager cache for further use.

# EXAMPLES

## Example 1

```
PS C:\> Remove-RMADUnpackedComponent (Get-RMADBackup | where{$_._.IsUnpacked -eq "true"})
```

Deletes all components unpacked from backups created with Recovery Manager for Active Directory.

# PARAMETERS

## -Id

Specifies the IDs of the backups whose unpacked components you want to delete.  
If you use this parameter, omit the InputObject parameter of this cmdlet.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -InputObject

Specifies the IBackupInfo objects representing the backups whose unpacked components you want to delete.  
If you use this parameter, omit the Id parameter of this cmdlet.

Type: BackupInfo[]  
Parameter Sets: Instance  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## -Confirm

Prompts for confirmation before executing the command.

Type: SwitchParameter  
Parameter Sets: (All)

Aliases: cf  
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

### **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: wi

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Rename-RMADCollection**

## **SYNOPSIS**

Renames a computer collection.

# SYNTAX

## Name (Default)

```
Rename-RMADCollection [-Name] <String> [-Value] <String> [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## InputObject

```
Rename-RMADCollection [-InputObject] <ComputerCollection> [-Value] <String> [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## Id

```
Rename-RMADCollection [-Id] <Int32> [-Value] <String> [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

# DESCRIPTION

Renames a computer collection with the name you specify.

# EXAMPLES

## Example 1

```
PS C:\> Rename-RMADCollection -Name "New Computer Collection" -Value Collection1
```

This command renames the computer collection named "New Computer Collection" to "Collection1".

## Example 2

```
PS C:\> $c = Get-RMADCollection -Name "Collection1"
```

```
C:\PS>Rename-RMADCollection -InputObject $c -Value "Collection2"
```

The Get-RMADCollection cmdlet retrieves the computer collection named Collection1.

This collection is then passed to the Rename-RMADCollection cmdlet that renames it to Collection2.

# PARAMETERS

## -Id

Specifies the identifier of the computer collection you want to rename.

Type: Int32

Parameter Sets: Id

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-InputObject**

Renames the computer collection represented by the specified collection objects.

Specify the name of the variable that contains the objects or type a command or expression that gets the objects.

Type: ComputerCollection

Parameter Sets: InputObject

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## **-Name**

Specifies the name of the computer collection to be renamed.

Type: String

Parameter Sets: Name

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

## **-PassThru**

Passes the renamed collection along the pipeline.

If this parameter is omitted, the renamed collection is not passed along the pipeline.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Value**

Specifies the new name you want to assign to the computer collection.

Type: String

Parameter Sets: (All)

```
Aliases: NewName  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: True (ByPropertyName)  
Accept wildcard characters: False
```

## -Confirm

Prompts for a confirmation before executing the command.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: cf
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -WhatIf

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: wi
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Restart-RMADFECloudStorageUploadSession

## SYNOPSIS

Restart a failed or canceled cloud storage upload session.

## SYNTAX

### **Id**

```
Restart-RMADFECloudStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly] [<CommonParameters>]
```

### **InputObject**

```
Restart-RMADFECloudStorageUploadSession [-InputObject] <UploadSession[]> [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Restart a previously failed or canceled cloud storage upload session. The copy of the backup is restarted and the specified session is updated.

## EXAMPLES

### **Example 1**

```
PS C:\> Restart-RMADFECloudStorageUploadSession -Id 4
```

Restart upload session with Id 4.

## PARAMETERS

### **-Id**

Specifies the upload session Id to restart the copy of the backup to cloud storage.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

### **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication (for internal use only).

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases:

Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

### **-InputObject**

Specifies the UploadSession object representing the cloud storage upload session you want to restart.

```
Type: UploadSession[]
Parameter Sets: InputObject
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Restore-RMADDeletedObject

## SYNOPSIS

Restores deleted Active Directory objects.

This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

## SYNTAX

### Default (Default)

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-  
    RestoreParent <RestoreParent>] [-Full]  
    [-NoReport] [-SkipReplication] [-ReportUnchangedObjects] [-  
    ReportUnchangedAttributes] [-RestoreTo <String>]  
    [-KeepBackupUnpacked] [-Id] <String[]> [-ProcessChildren] [-  
    ChildObjectClass <String[]>]  
    [-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor] [-Server  
    <String>] [-Credential <PSCredential>]  
    [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-  
    Confirm] [<CommonParameters>]
```

### ADLds

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-  
    BackupPassword <SecureString>]  
    [-NoReport] [-SkipReplication] [-SQLCredential <PSCredential>] [-  
    ReportUnchangedObjects]  
    [-ReportUnchangedAttributes] [-RestoreTo <String>] [-AsJob] [-  
    KeepBackupUnpacked] [-Id] <String[]>  
    [-ProcessChildren] [-ChildObjectClass <String[]>] [-AdLds] -AdLdsInstance  
    <String>  
    [-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor] [-Server  
    <String>] [-Credential <PSCredential>]  
    [-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-  
    Confirm] [<CommonParameters>]
```

### Bkf

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] -Backup <Guid> [-  
    BackupPassword <SecureString>] [-NoReport]  
    [-SkipReplication] [-SQLCredential <PSCredential>] [-  
    ReportUnchangedObjects] [-ReportUnchangedAttributes]  
    [-RestoreTo <String>] [-AsJob] [-KeepBackupUnpacked] [-Id] <String[]> [-  
    ProcessChildren]  
    [-ChildObjectClass <String[]>] [-ChangeAuditorDbName <String>] [-  
    RestoreUsingChangeAuditor] [-Server <String>]  
    [-Credential <PSCredential>] [-Partition <String>] [-Port <Int32>] [-  
    IgnoreReadOnly] [-WhatIf] [-Confirm]  
    [<CommonParameters>]
```

## Firewall

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-  
BackupPassword <SecureString>]  
[-RestoreParent <RestoreParent>] [-Full] [-NoReport] [-SkipReplication] [-  
SQLCredential <PSCredential>]  
[-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo  
<String>] [-AsJob] [-KeepBackupUnpacked]  
[-Id] <String[]> [-ProcessChildren] [-ChildObjectClass <String[]>] [-  
AdLds] [-ChangeAuditorDbName <String>]  
[-ConfigureFirewall] [-RestoreUsingChangeAuditor] [-Server <String>] [-  
Credential <PSCredential>]  
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

## Agentless

```
Restore-RMADDeletedObject [-ProcessRecycledObjects] [-Backup <Guid>] [-  
BackupPassword <SecureString>]  
[-RestoreParent <RestoreParent>] [-Full] [-NoReport] [-SkipReplication] [-  
SQLCredential <PSCredential>]  
[-ReportUnchangedObjects] [-ReportUnchangedAttributes] [-RestoreTo  
<String>] [-AsJob] [-KeepBackupUnpacked]  
[-Id] <String[]> [-UseAgentlessMethod] [-ProcessChildren] [-  
ChildObjectClass <String[]>] [-AdLds]  
[-ChangeAuditorDbName <String>] [-RestoreUsingChangeAuditor] [-Server  
<String>] [-Credential <PSCredential>]  
[-Partition <String>] [-Port <Int32>] [-IgnoreReadOnly] [-WhatIf] [-  
Confirm] [<CommonParameters>]
```

## DESCRIPTION

Restores deleted Active Directory objects whose applicable tombstone lifetime or deleted object lifetime has not expired.

Depending on your settings and your environment, this cmdlet can restore deleted objects by using the following methods:

- Restore deleted objects from Microsoft's Active Directory Recycle Bin (provided that it is available in your environment).

- Restore deleted objects from a backup registered with Recovery Manager for Active Directory.
- Reanimate object's tombstones.

You can only use this cmdlet when Windows PowerShell is started using MTA.

To start Windows PowerShell using MTA, run this command: `PowerShell -mta`

## EXAMPLES

### Example 1

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcf-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -ProcessRecycledObjects -  
Server dc1.mydomain.com
```

Retrieves the recycled object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID.

This command is only applicable to environments where Microsoft's Active Directory Recycle Bin is enabled. In this example, the Server parameter is mandatory.

## Example 2

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcf-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -Server dc1.mydomain.com
```

Retrieves deleted object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID.

In this example, the Server parameter is mandatory.

## Example 3

```
PS C:\> Restore-RMADDeletedObject -Id d8742dcf-3e6a-4b3c-b3fe-374623cdcf06  
-Backup 2b509d4e-40f5-4337-82f7-458584555d0c -Server dc1.mydomain.com -  
WindowsServerBackup -AsJob
```

Retrieves deleted object with the specified Id (GUID) from the domain controller dc1.mydomain.com, and then restores the object from the backup with the specified GUID in the background job.

In this example, the Server parameter is mandatory.

# PARAMETERS

## -AdLds

Specifies that the AD LDS instance is used as a data storage.

Type: SwitchParameter

Parameter Sets: ADLds

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: Firewall, Agentless

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -AdLdsInstance

If you restore the backed up AD LDS (ADAM) objects, you should specify the AD LDS instance whose backup you want to use.

Type: String

Parameter Sets: ADLds

Aliases: AdamInstance

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-AsJob**

Runs the command as a background job.  
You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter  
Parameter Sets: ADLds, Bkf, Firewall, Agentless  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Backup**

Specifies the backup that contains the deleted object you want to restore.  
To specify a backup, type the backup GUID in this parameter or use the Get-RMADBackup cmdlet.

Type: Guid  
Parameter Sets: Default, ADLds, Firewall, Agentless  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: Guid  
Parameter Sets: Bkf  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access the password-protected backup that contains the deleted object you want to restore.

Type: SecureString  
Parameter Sets: ADLds, Bkf, Firewall, Agentless  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ChangeAuditorDbName**

Specifies a location of the ChangeAuditor SQL database.  
If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-ChildObjectClass**

Allows you to reanimate only those child objects that belong to the classes you specify in this parameter.

```
Type: String[]
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-ConfigureFirewall**

Specifies whether Recovery Manager automatically configures Windows Firewall on the target Windows Server 2008-based or Windows Server 2012-based DCs to allow compare and restore operations.

```
Type: SwitchParameter
Parameter Sets: Firewall
Aliases:
```

```
Required: True
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Credential**

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

```
Type: PSCredential
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Full**

Specifies to restore the deleted objects with all their attributes.

When this parameter is present, the cmdlet does one of the following:

- Restores the deleted objects from Microsoft's Active Directory Recycle Bin.

This occurs only if the Recycle Bin is available and if you do not specify to restore the deleted objects from a backup.

- Restores the deleted object from the backup whose GUID you specify in the BackupGuid parameter.

When this parameter is omitted, the cmdlet does one of the following:

- If Microsoft's Active Directory Recycle Bin is available, the cmdlet completely undeletes the deleted objects from the Recycle Bin.
- If Microsoft's Active Directory Recycle Bin is disabled or not supported, the cmdlet reanimates the objects' tombstones.

Type: SwitchParameter  
 Parameter Sets: Default, Firewall, Agentless  
 Aliases:

Required: False  
 Position: Named  
 Default value: False  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-Id**

Specifies the deleted objects to restore.  
 To specify an object, you can use object GUID, distinguished name (DN), sAMAccountName, or user principal name (UPN).

Type: String[]  
 Parameter Sets: (All)  
 Aliases:

Required: True  
 Position: 0  
 Default value: None  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
 Parameter Sets: (All)  
 Aliases:

Required: False  
 Position: Named  
 Default value: False  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-KeepBackupUnpacked**

Determines whether to save the unpacked backup after the search operation.  
 If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter  
 Parameter Sets: (All)  
 Aliases:

Required: False  
 Position: Named  
 Default value: False  
 Accept pipeline input: False  
 Accept wildcard characters: False

## **-NoReport**

Specifies to not create any report about the restore operation.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Partition**

Specifies the distinguished name of the Active Directory partition from which deleted objects are to be retrieved.

If this parameter is omitted, the default naming context is used.

This parameter is required if you specify an ADAM instance host in the DirectoryHost parameter.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Port**

Specifies the port number to be used for connection.

If this parameter is set to 0 or not specified, the default LDAP port (389) is used.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ProcessChildren**

Specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ProcessRecycledObjects**

Specifies to process recycled objects.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ReportUnchangedAttributes**

Includes information about the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ReportUnchangedObjects**

Includes information about the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-RestoreParent**

Restores the deleted parents of the deleted objects being recovered.

This parameter can take one of the following values: \* Never - Specifies to not restore deleted parents.

- Always - Specifies to always restore deleted parents.
- Prompt - Prompts you for action.

Type: RestoreParent

Parameter Sets: Default, Firewall, Agentless

Aliases:

Accepted values: Never, Always, Prompt

Required: False

Position: Named

Default value: Prompt

Accept pipeline input: False

Accept wildcard characters: False

## **-RestoreTo**

Specifies a target container for the restore operation.

To specify a target container, specify the container's distinguished name (DN) in this parameter.

You can use this parameter to specify a target container if the parent container of the object you want to restore has been deleted.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RestoreUsingChangeAuditor**

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Server**

Specifies the domain controller or ADAM instance host from which deleted objects are to be retrieved.

The domain controller can be specified by its computer name, IP address, or domain name.

If you specify a domain name, deleted objects are retrieved from any available domain controller in the specified domain.

The ADAM instance host can be specified by its computer name or IP address.

If this parameter is omitted, deleted objects are retrieved from any available domain controller in the current domain.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-SkipReplication**

Specifies to skip replication during the restore operation.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-SQLCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report about the performed operation.

The user name and password must be in the form of a PSCredential object.

When this parameter is omitted, the cmdlet uses the credentials of the account under which Management Shell is running.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential

Parameter Sets: ADLds, Bkf, Firewall, Agentless

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-UseAgentlessMethod**

Specifies to use the agentless method to access the target domain controller.

If this parameter is omitted, the target domain controller is accessed via Restore Agent.

Type: SwitchParameter

Parameter Sets: Agentless

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Confirm**

Prompts for a confirmation before executing the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Restore-RMADDomainController

## SYNOPSIS

Restores a domain controller from backup.

## SYNTAX

### Default (Default)

```
Restore-RMADDomainController -Backup <BackupInfo> [-BackupComponents <BackupComponents>]
[-BackupPassword <SecureString>] [-ComputerName <String>] [-Credential <PSCredential>]
-DsrmCredential <PSCredential> [-ResetDsrmPassword] [-ManualRestartToDsrm]
[-ManualRestartToNormal]
[-MarkSysvolPrimary] [-AsJob] [-WhatIf] [<CommonParameters>]
```

### AuthoritativeRestore

```
Restore-RMADDomainController -Backup <BackupInfo> [-BackupComponents <BackupComponents>]
[-BackupPassword <SecureString>] [-ComputerName <String>] [-Credential <PSCredential>]
-DsrmCredential <PSCredential> [-ResetDsrmPassword] [-ManualRestartToDsrm]
[-ManualRestartToNormal]
[-MarkSysvolPrimary] -AuthoritativeRestore <Boolean> [-AuthoritativeRestoreSubtree <String>] [-AsJob]
```

```
[-WhatIf] [<CommonParameters>]
```

## DESCRIPTION

Restores a domain controller from backup.

During the Restore operation, the domain controller would be rebooted to the Directory Service Restore mode.

## EXAMPLES

### Example 1

```
PS C:\> $backup = (Get-RMADBackup -ComputerName 'DC.Domain.local')[-1]
$dsrmCredential = New-Object PSCredential(".\Administrator", (ConvertTo-
SecureString 'DsrmPassword' -AsPlainText -Force))
$job = Restore-RMADDomainController -ComputerName "DC.Domain.local" -Backup
$backup -BackupComponents ActiveDirectory -DsrmCredential $dsrmCredential -
AsJob
$job | Format-List
```

This command restores a domain controller from backup.

## PARAMETERS

### **-AsJob**

Runs a command as a background job.

You can use this parameter to run commands that take a significant amount of time to complete.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

### **-AuthoritativeRestore**

Performs an authoritative restore.

Type: Boolean  
Parameter Sets: AuthoritativeRestore  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-AuthoritativeRestoreSubtree**

Specifies a subtree that will be marked as authoritative.

If this parameter is not specified, the whole Active Directory will be marked as authoritative.

Type: String  
Parameter Sets: AuthoritativeRestore

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Backup**

Specifies the backup that contains the data to be restored.

Type: BackupInfo  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupComponents**

Specifies the components of backup to be restored.

Type: BackupComponents  
Parameter Sets: (All)  
Aliases:  
Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, All

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access a password-protected backup.

This is the same password that is set in the properties of the computer collection in the Recovery Manager for Active Directory console.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ComputerName**

Specifies DNS name or IP address of the domain controller to be restored.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Credential**

Specifies credentials to access the domain controller and then deploy and connect to the Restore Agent in the Normal mode.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DsrmCredential**

Specifies credentials for the Directory Service Restore Mode.  
If ResetDSRMPassword is specified, the password will be reset.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ManualRestartToDsrm**

Specifies whether a domain controller will be rebooted to DSRM manually.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ManualRestartToNormal**

Specifies whether a domain controller will be rebooted to the Normal mode manually after the Restore operation is completed.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False

Accept wildcard characters: False

## **-MarkSysvolPrimary**

Specifies to mark SYSVOL as primary.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-ResetDsrmpassword**

Specifies whether the DSRM password will be reset to the password from the DSRCredential parameter.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Tests the connection to the restore agent

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Restore-RMADObject

## SYNOPSIS

Restores Active Directory objects from a backup.

This cmdlet requires Windows PowerShell to be started using a multi-threaded apartment (MTA).

## SYNTAX

### Default (Default)

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-ChangeAuditorDbName <String>] [-
RestoreUsingChangeAuditor]
[-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]
```

### Bkf

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-ChangeAuditorDbName <String>] [-
RestoreUsingChangeAuditor]
[-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
```

```
[<CommonParameters>]
```

## ADLds

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-AdLds] -AdLdsInstance <String> [-
ChangeAuditorDbName <String>]
[-RestoreUsingChangeAuditor] [-Server <String>] [-Credential
<PSCredential>] [-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## Firewall

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-AdLds] [-ChangeAuditorDbName <String>]
[-ConfigureFirewall]
[-RestoreUsingChangeAuditor] [-Server <String>] [-Credential
<PSCredential>] [-Partition <String>]
[-Port <Int32>] [-IgnoreReadOnly] [<CommonParameters>]
```

## Agentless

```
Restore-RMADObject [-Attribute <String[]>] [-NoReport] [-SkipReplication]
[-KeepBackupUnpacked]
[-Id] <String[]> -Backup <Guid> [-BackupPassword <SecureString>] [-
UseAgentlessMethod] [-ProcessChildren]
[-ChildObjectClass <String[]>] [-ReportUnchangedAttributes] [-
ReportUnchangedObjects]
[-SQLCredential <PSCredential>] [-AdLds] [-ChangeAuditorDbName <String>]
[-RestoreUsingChangeAuditor]
[-Server <String>] [-Credential <PSCredential>] [-Partition <String>] [-
Port <Int32>] [-IgnoreReadOnly]
[<CommonParameters>]
```

## DESCRIPTION

Restores the Active Directory objects that have specified parameters from a backup.  
You can only use this cmdlet when Windows PowerShell is started using MTA.  
To start Windows PowerShell using MTA, run this command: `PowerShell -mta`

## EXAMPLES

### Example 1

```
PS C:\> $backups = Get-RMADBackup | Sort-Object -Property date -Descending
C:\PS>$object = Get-RMADObject -Id "user1"
```

```
C:\PS>Restore-RMADObject -Id $object.ObjectInfo.Guid -Backup $backups[0] -  
UseAgentlessMethod -NoReport
```

In the first line of this example, the Get-RMADBackup cmdlet gets all registered backups and sorts them by date in the descending order.

Then, the backup objects are stored in the \$backups variable.

## Example 2

```
PS C:\> $b = Get-RMADBackup -Id 1
```

```
C:\PS>Restore-RMADObject -Id "user1" -Backup $b -Attribute  
samAccountName,description -ReportUnchangedAttributes
```

```
Start-RMADReportViewer
```

In the first line of this example, the Get-RMADBackup cmdlet gets the registered backup whose ID is 1. Then, the backup object is stored in the \$b variable.

# PARAMETERS

## -AdLds

Specifies that the AD LDS instance is used as a data storage.

Type: SwitchParameter

Parameter Sets: ADLds

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

Type: SwitchParameter

Parameter Sets: Firewall, Agentless

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -AdLdsInstance

If you restore the backed up AD LDS (ADAM) objects, you should specify the AD LDS instance whose backup you want to use.

Type: String

Parameter Sets: ADLds

Aliases: AdamInstance

Required: True

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Attribute**

Specifies the display names of the attributes to restore.  
When specifying multiple display names, use a comma as a separator.

Type: String[]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Backup**

Specifies the backup that contains the AD objects to be restored.

Type: Guid  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access a password-protected backup.  
This is the same password that is set in the computer collection properties in the Recovery Manager console.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ChangeAuditorDbName**

Specifies the location of the ChangeAuditor SQL database.  
If this parameter is omitted, the 'ModifyBy' cell in AD reports will be empty.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ChildObjectClass**

Allows you to restore only those child objects that belong to the classes you specify in this parameter.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ConfigureFirewall**

Specifies whether Recovery Manager automatically configures Windows Firewall on target Windows Server 2008-based or Windows Server 2012-based DCs to allow compare and restore operations.

Type: SwitchParameter

Parameter Sets: Firewall

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-Credential**

The user name and password of the user account with which you want to connect, in the form of a PSCredential object.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter. If this parameter is omitted, the credentials of current user account are used.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Id**

Specifies the objects to restore.

To specify an object, you can use object GUID, distinguished name (DN), sAMAccountName, or user principal name (UPN).

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -KeepBackupUnpacked

Determines whether to save the unpacked backup after the search operation.  
If this parameter is not set, the unpacked backup will be deleted after the search operation is completed.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -NoReport

When present, specifies to not create any report about the restore operation.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -Partition

Specifies the AD LDS (ADAM) partition where you want to restore objects.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Port

Specifies the port on which to access the AD LDS (ADAM) instance where you want to restore objects.

Type: Int32  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
```

Accept wildcard characters: False

## -ProcessChildren

When present, specifies to process children of the objects specified in the Id attribute.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -ReportUnchangedAttributes

Includes the object attributes that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -ReportUnchangedObjects

Includes the objects that have not changed since the time of the specified backup into the operation report.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -RestoreUsingChangeAuditor

Specifies if Change Auditor is used to restore the latest changes to the object.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## -Server

Specifies the domain controller or ADAM instance host on which objects are to be restored.

The domain controller can be specified by its computer name, IP address, or domain name.

If you specify a domain name, deleted objects are restored to any available domain controller in the specified domain.

The ADAM instance host can be specified by its computer name or IP address.

If this parameter is omitted, objects are restored to any available domain controller in the current domain.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-SkipReplication**

When present, specifies to skip replication during the restore operation.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-SQLCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report about the performed operation.

The user name and password must be in the form of a PSCredential object.

When this parameter is omitted, the cmdlet uses the credentials of the account under which Management Shell is running.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-UseAgentlessMethod**

Specifies to use the agentless method to access the target domain controller.

If this parameter is omitted, the target domain controller is accessed via Restore Agent.

Type: SwitchParameter

Parameter Sets: Agentless

Aliases:

Required: True

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Resume-RMADFERecovery

## SYNOPSIS

Resumes recovery process.

## SYNTAX

### Resume (Default)

```
Resume-RMADFERecovery [-ProjectPassword] <SecureString> [-  
IgnoreDialogueTimeout] [-GroupPasswords <Hashtable>]  
[<CommonParameters>]
```

### Drop

```
Resume-RMADFERecovery [-DropStoredSession] [<CommonParameters>]
```

## DESCRIPTION

If some workstations have begun the restore process and failed, this cmdlet can resume the recovery process.

SQL Persistence must be properly configured on both processes.  
Both processes must be registered as restoring workstations.

If you chose to reset the password for domain users in privileged groups when you started a forest recovery, you need to provide passwords again using -GroupPasswords parameter because the product does not store user passwords.

# EXAMPLES

## Example 1

```
WS1:  
PS C:\> Open-RMADFEProject 'c:\ActiveDirectoryRestore.frproj' (ConvertTo-SecureString "Password" -AsPlainText -Force)  
Start-RmadFeRecovery -Force  
  
WS2:  
PS C:\> Resume-RmadFeRecovery -ProjectPassword (ConvertTo-SecureString "Password" -AsPlainText -Force)
```

For example, there are two RMAD workstations in your environment.  
Both workstations must be registered as restoring workstations.  
Therefore, if one of them is not responding, you can run the recovery process from another workstation.

## Example 2

```
PS C:\> Resume-RmadFeRecovery -DropStoredSession  
This command cleans up the recovery session if any.
```

# PARAMETERS

## -DropStoredSession

Lead to a session drop in the persistence DB.

Type: SwitchParameter  
Parameter Sets: Drop  
Aliases:

Required: True  
Position: 2  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -GroupPasswords

Resets the password for domain users in the specified privileged groups.

Type: Hashtable  
Parameter Sets: Resume  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -IgnoreDialogueTimeout

Allows you to proceed if another console does not answer.

Type: SwitchParameter  
Parameter Sets: Resume  
Aliases:

```
Required: False
Position: 1
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **-ProjectPassword**

The password that was configured for restore project.

```
Type: SecureString
Parameter Sets: Resume
Aliases:
```

```
Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## **schema: 2.0.0**

# **Save-RMADFEProject**

## **SYNOPSIS**

Saves the RMADFE project.

## SYNTAX

```
Save-RMADFEProject [-Path] <String> [-Password] <SecureString>
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet saves the RMADFE project to the specified location.  
You must also supply the password that is used to access the project content.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Save-RMADFEProject -Path C:\RMADFEProjects\SampleProject.frproj -
>Password (ConvertTo-SecureString "project password" -AsPlainText -Force)
```

This command saves SampleProject.frproj to the specified location.

## PARAMETERS

### -Password

Specifies the password that is used to access the RMADFE project content.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Path

Specifies the full path to the RMADFE project file.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Set-RMADCollection

## SYNOPSIS

Sets properties for a computer collection.

## SYNTAX

### Name (Default)

```
Set-RMADCollection [-Name] <String[]> [-BackupComponents <BackupComponents>] [-Properties <Hashtable>] [-Schedule <Schedule[]>] [-ScheduleCredential <PSCredential>] [-AgentCredentialEnabled <Boolean>] [-AgentCredential <PSCredential>] [-StorageCredentialEnabled <Boolean>] [-StorageCredential <PSCredential>] [-ConsoleStorageCredential <PSCredential>] [-SecondaryStorageCredential <PSCredential>] [-RetentionPolicyEnabled <Boolean>] [-RetentionPolicyCount <Int32>] [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

### InputObject

```
Set-RMADCollection [-InputObject] <ComputerCollection[]> [-BackupComponents <BackupComponents>] [-Properties <Hashtable>] [-Schedule <Schedule[]>] [-ScheduleCredential <PSCredential>] [-AgentCredentialEnabled <Boolean>] [-AgentCredential <PSCredential>] [-StorageCredentialEnabled <Boolean>] [-StorageCredential <PSCredential>] [-ConsoleStorageCredential <PSCredential>] [-SecondaryStorageCredential <PSCredential>] [-RetentionPolicyEnabled <Boolean>]
```

```
[-RetentionPolicyCount <Int32>] [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## Id

```
Set-RMADCollection [-Id] <Int32[]> [-BackupComponents <BackupComponents>] [-Properties <Hashtable>] [-Schedule <Schedule[]>] [-ScheduleCredential <PSCredential>] [-AgentCredentialEnabled <Boolean>] [-AgentCredential <PSCredential>] [-StorageCredentialEnabled <Boolean>] [-StorageCredential <PSCredential>] [-ConsoleStorageCredential <PSCredential>] [-SecondaryStorageCredential <PSCredential>] [-RetentionPolicyEnabled <Boolean>] [-RetentionPolicyCount <Int32>] [-PassThru] [-IgnoreReadOnly] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Sets properties for the Recovery Manager computer collection you specify.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADCollection -Name Collection1 -BackupComponents ActiveDirectory,Registry,GroupMembership,ForestRecoveryMetadata
```

This command sets properties for the computer collection named Collection1.

### Example 2

```
PS C:\> Set-RMADCollection * -RetentionPolicyEnabled $false
```

This command disables all backup retention policies for all existing computer collections.

### Example 3

```
PS C:\> $c = Get-RMADCollection | Where-Object { $_.AgentCredentialEnabled -eq $true }
```

```
C:\PS>$cred = Get-Credential
```

```
C:\PS>Set-RMADCollection -InputObject $c -AgentCredential $cred
```

The first command in this example gets objects representing the computer collections whose properties are set to access Backup Agent and backup files with a specific user account.

Then the command saves the computer collection objects in the \$c variable.

### Example 4

```
PS C:\> $a = Get-RMADCollection -Name "Collection1"
```

```
C:\PS>Set-RMADCollection -InputObject $a[1] -Properties @{BackupComponents="ActiveDirectory","BootFiles"; UsePreinstalledAgent=$true}
```

In the first line of this example, the Get-RMADCollection cmdlet gets the Computer Collection whose name is Collection1 and saves it to the \$a variable.

In the second line of this example, the Set-RMADCollection cmdlet sets the components to be backed up (that is,

Active Directory and boot files) and specifies to use preinstalled Backup Agent for backup operations. For a complete list of items you can include in the braces, see the description of the Properties parameter.

## Example 5

```
PS C:\> $schedule=(New-RMADSchedule -Daily -StartDate "9/20/2013 10:00" -DaysInterval 1), (New-RMADSchedule -Daily -StartDate "9/20/2013 22:00" -DaysInterval 1)

C:\PS>Set-RMADCollection -InputObject $col -Properties @{EnableEmailLog=$true; EmailLogTo="administrator@mydomain.com"; EmailLogLevel="Everything"}
```

This example illustrates how to back up a Computer Collection by using two backup schedules. The first line of this example creates two backup creation schedules and stores them in the \$schedule variable. One schedule invokes the backup operation once in every two days at 10 a.m.. Another schedule invokes the backup operation once in every two days at 10 p.m.. The two backup schedules become effective starting from the 20th September 2013. The second line of this example enables e-mail notifications for the Computer Collection. The recipient address for e-mail notifications is administrator@mydomain.com. The e-mail notifications provide information about all backup events.

## Example 6

```
PS C:\> $cred = Get-Credential

C:\PS>Set-RMADCollection -Name MyCollection -Properties @{AgentSideScriptBeforeBackupEnabled = $true; AgentSideScriptBeforeBackup = 'Set-Disk -Number 5 -IsOffline $false'; AgentSideScriptAfterBackupEnabled = $true; AgentSideScriptAfterBackup = 'Set-Disk -Number 5 -IsOffline $true'; AgentSideScriptCredential = $cred}
```

This example illustrates how to customize your environment by running PowerShell scripts on the domain controller before and after creating a backup.

# PARAMETERS

## -AgentCredential

Specifies the credentials for the account you want to use to access Backup Agent installed on the DCs in the computer collection and locations where backup files for the computer collection will be saved. To enable using the account whose credentials you supply in this parameter, use the AgentCredentialEnabled parameter.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -AgentCredentialEnabled

Specifies to use a particular account to access Backup Agent installed on the DCs in the computer collection and locations where backup files for the computer collection will be saved. To specify the credentials for the account, use the AgentCredential parameter.

Type: Boolean  
Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupComponents**

Use this parameter to specify the names of the System State components you want to back up.

Type: BackupComponents  
Parameter Sets: (All)  
Aliases:  
Accepted values: None, ActiveDirectory, Adam, BootFiles, CertificateServer, ClusterQuorum, EnterpriseServices, ForestRecoveryMetadata, GroupMembership, IisMetabase, PerformanceCounters, Registry, CryptoKeys, All

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ConsoleStorageCredential**

Specifies the credentials for the account you want to use to access local (console) backup files for the computer collection.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Id**

Specifies the identifier of the computer collection whose properties you want to set.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False

```
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-InputObject**

Renames the computer collection represented by the specified collection objects.  
Specify the name of the variable that contains the objects or type a command or expression that gets the objects.

```
Type: ComputerCollection[]  
Parameter Sets: InputObject  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## **-Name**

Specifies the name of the computer collection whose properties you want to set.

```
Type: String[]  
Parameter Sets: Name  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

## **-PassThru**

Passes the computer collection whose properties you have set along the pipeline.  
If this parameter is omitted, the computer collection is not passed along the pipeline.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Properties**

Allows you to modify the Computer Collection properties.

To specify the properties you want to modify, use an associative array or hash table.

For more information, see the Windows PowerShell help topic on associative arrays (hash tables).

To open the topic, at the PowerShell command prompt enter the following: `help about_associative_array`  
Below are the properties you can modify by using this parameter.

The properties are grouped by the names of tabs in the "Computer Collection Properties" dialog box, because each property corresponds to an option on these tabs. To assign a new value to a property, use the following format: `PropertyName=PropertyValue * UseAlternateStoragePath`.

Specifies whether to store a copy of each backup in an alternate location.

Can take one of these values: \$true, \$false.

- **AlternateStoragePath.**  
Specifies a storage path format for the alternate location.  
Surround the path with double quotes.
- **AgentCredentialEnabled.**  
Causes the Recovery Manager console to use a specified user account to access the Backup Agent and backup files on target computers.  
Can take one of these values: \$true, \$false.
- **AgentCredential.**  
Specifies the account under which the Recovery Manager console accesses the Backup Agent and backup files, in the form of a PSCredential object.  
Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.
- **ConfigureFirewall.**  
Specifies whether Recovery Manager automatically configures Windows Firewall on target Windows Server 2008-based or Windows Server 2012-based DCs to allow backup operations.  
Can take one of these values: \$true, \$false.
- **UsePreinstalledAgent.**  
Specifies whether Recovery Manager automatically preinstalls the Backup Agent.  
Can take one of these values: \$true, \$false.
- **DeployForestRecoveryAgent.**  
Specifies whether Recovery Manager verifies that the Forest Recovery Agent is installed on each domain controller in the Computer Collection.  
Can take one of these values: \$true, \$false.
- **BackupDescription.**  
Specifies a description for the backups to be created for the Computer Collection.  
The description may include expressions, such as %COMPUTERNAME% and %DATETIME%.
- **BackupPasswordEnabled.**  
Specifies whether to protect the backups with a password.  
Can take one of these values: \$true, \$false.
- **BackupPassword.**  
Specifies a password to protect the backups.  
The value must be a SecureString object.
- **ConsoleSideBackupEnabled.**  
Specifies to store backups on the Recovery Manager computer or on a Universal Naming Convention (UNC) share.  
Can take one of these values: \$true, \$false.
- **ConsoleSideBackupPath.**  
Specifies a storage path format for backup files.  
The path format can include expressions, such as %COMPUTERNAME% and %DATETIME%.  
Surround the path format with double quotes.
- **ConsoleSideRetentionPolicyEnabled.**  
Specifies whether to apply a retention policy to backups stored at the path provided in the ConsoleSideBackupPath parameter.  
Can take one of these values: \$true, \$false.

- **ConsoleSideRetentionPolicyCount.**  
Specifies the number of the most recent backups to retain.  
Other backups are automatically deleted.
- **AgentSideBackupEnabled.**  
Specifies to store backups on the backed-up DC or on a Universal Naming Convention (UNC) share.  
Can take one of these values: \$true, \$false.
- **AgentSideBackupPath.**  
Specifies a storage path format for backup files.  
The path format can include expressions, such as %COMPUTERNAME% and %DATETIME%.  
Surround the path format with double quotes.
- **AgentSideRetentionPolicyEnabled.**  
Specifies whether to apply a retention policy to backups stored at the path provided in the ConsoleSideBackupPath parameter.  
Can take one of these values: \$true, \$false.
- **AgentSideRetentionPolicyCount.**  
Specifies the number of the most recent backups to retain.  
Other backups are automatically deleted.
- **StorageCredentialEnabled.**  
Causes the Recovery Manager console to use a specified user account to access backup files on target computers.  
Can take one of these values: \$true, \$false.
- **StorageCredential.**  
Specifies the account under which the Recovery Manager Backup Agent accesses the backup files, in the form of a PSCredential object.  
Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.
- **EnableEmailLog.**  
Specifies whether to send information about backup creation sessions by e-mail.  
Can take one of these values: \$true, \$false.
- **EnableEmailLogOnlyOnErrors.**  
Specifies to send information over e-mail only when an error occurs.  
Can take one of these values: \$true, \$false.
- **EmailLogLevel.**  
Specifies the type of information to send over e-mail.  
Possible values: "Everything", "ErrorsOnly".
- **EmailLogTo.**  
Specifies the recipient's e-mail address to send the information about backup creation sessions.
- **EnableApplicationLog.**  
Specifies whether to write information about backup creation sessions to the Windows application log on the Recovery Manager computer.  
Can take one of these values: \$true, \$false.
- **EnableApplicationLogOnlyOnErrors.**  
Specifies whether to create an Application log event only upon backup creation session errors or warnings.  
Can take one of these values: \$true, \$false.

- **ApplicationLogLevel.**  
Specifies the type of information to write to the Application log.  
Possible values: "Everything", "ErrorsOnly".
- **EnableLogFile.**  
Specifies whether to write information about backup creation sessions to the additional text file you specify.  
Can take one of these values: \$true, \$false.
- **EnableLogFileOnlyOnErrors.**  
Specifies whether to write information to the additional text file only upon backup creation session errors or warnings.  
Can take one of these values: \$true, \$false.
- **LogFileLevel.**  
Specifies the type of information to write to the additional text file.  
Possible values: "Everything", "ErrorsOnly".
- **LogFileName.**  
Specifies a path and name for the additional text file.
- **LogFileAppend.**  
Specifies whether to append information to the additional text file.  
Can take one of these values: "True", "False".
- **ExtendedLogging.**  
Specifies the logging settings for DCs in the collection.  
Can take one of these values: Use global (default) - use settings from the root node: Recovery Manager for Active Directory->Settings...>Logging, Yes - for all DCs in the current collection: for logs will be used the "Trace" option, No - for all DCs in the current collection: in logs will be only Warnings and Error messages.
- **CompressionMethod.**  
Specifies a method to compress the backups to be created.  
Can take one of these values: "None", "Fast", "Normal", "Maximum".
- **ParallelBackups.**  
Specifies the maximum number of computers serviced in parallel when creating backups.  
Increasing this number can speed the backup creation, however, this may result in network saturation and slow network response.
- **EnableTransferRateLimit.**  
Specifies whether to limit the total bandwidth used by the Backup Agent when transferring data over the network.  
Use this property to prevent the Backup Agent from generating excessive network traffic.  
Can take one of these values: \$true, \$false.
- **TransferRateLimit.**  
Specifies the bandwidth limit in Mbits/sec for the Backup Agent.
- **EnableCpuUsageLimit.**  
Specifies whether to limit the CPU processing time used by the Backup Agent on each computer.  
Can take one of these values: \$true, \$false.
- **CpuUsageLimit.**  
Specifies the CPU processing limit in percent.

- **ScheduleEnabled.**  
Specifies whether to enable backup creation schedule.  
Can take one of these values: \$true, \$false.
- **Schedule.**  
Sets up a backup creation schedule.  
To set up a schedule, use the New-RMADSchedule cmdlet.
- **ScheduleCredential.**  
Specify the user account under which the Task Scheduler performs backup creation tasks, in the form of a PSCredential object.  
Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.
- **BackupComponents.**  
Specifies the system state components to back up.  
Possible values: "All", "None", "ActiveDirectory", "Adam", "BootFiles", "CertificateServer", "ClusterQuorum", "EnterpriseServices", "ForestRecoveryMetadata", "GroupMembership", "IisMetabase", "PerformanceCounters", "Registry".  
When specifying multiple values, use a comma as a separator.
- **CollectGroupMembership.**  
Specifies whether to back up group membership data stored on Global Catalog servers.  
Can take one of these values: \$true, \$false.
- **CollectForestRecoveryMetadata.**  
Specifies whether to create backups that can be used to recover the Active Directory forest.  
Can take one of these values: \$true, \$false.
- **OverrideDefaultBackupUnpackSettings.**  
Specifies whether to override the global settings for unpacking backups for the Computer Collection.  
Can take one of these values: \$true, \$false.
- **UnpackBackupsUponCreation.**  
Specifies whether to unpack each backup upon its creation.  
Can take one of these values: \$true, \$false.
- **UnpackedBackupsToKeep.**  
Specifies the number of the most recent unpacked backups to retain.  
Other unpacked backups are automatically deleted.
- **IsUnpackOnlySelected.**  
Specifies whether to keep unpacked backups only for a list of selected domain controllers.  
Can take one of these values: \$true, \$false.
- **SelectedDCsToUnpack.**  
Specifies the names (separated by comma) of domain controllers you want to keep unpacked backups for.

Type: Hashtable

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RetentionPolicyCount**

Specifies the number of latest backups you want to keep for each DC in the computer collection. To enable the deletion of obsolete backups, use the RetentionPolicyEnabled parameter.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RetentionPolicyEnabled**

Specifies to delete obsolete backups for particular computer collection.

To set the number of latest backups you want to keep for each DC in the computer collection, use the RetentionPolicyCount parameter.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Schedule**

Causes the computer collection you specify to use the backup creation schedule you set by using the New-RMADSchedule cmdlet.

Type: Schedule[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-ScheduleCredential**

Specifies the user account under which the scheduled backup creation task will be run.

This account must have sufficient permissions to back up the computer collection you specify.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-SecondaryStorageCredential**

Specifies the credentials for the account you want to use to Tier 1 remote storage to copy backups to the secondary storage like Secure Storage Server or Cloud Storage.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-StorageCredential**

Specifies the credentials for the account you want to use to access locations where backup files for the computer collection will be saved.

To enable using the account whose credentials you supply in this parameter, use the StorageCredentialEnabled parameter.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-StorageCredentialEnabled**

Specifies to use a particular account to access locations where backup files for the computer collection will be saved.

To specify the credentials for the account, use the StorageCredential parameter.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Confirm**

Prompts for a confirmation before executing the command.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases: cf

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## **schema: 2.0.0**

# **Set-RMADFECloudStorage**

## **SYNOPSIS**

Updates cloud storage in the Recovery Manager.

## **SYNTAX**

### **Id**

```
Set-RMADFECloudStorage [-DisplayName <String>] [-Container <String>] [-ConnectionString <String>] [-PassThru] [-Id] <Int32[]> [-IgnoreReadOnly] [<CommonParameters>]
```

## **InputObject**

```
Set-RMADFECloudStorage [-DisplayName <String>] [-Container <String>] [-ConnectionString <String>] [-PassThru] [-InputObject] <CloudStorage[]> [-IgnoreReadOnly] [<CommonParameters>]
```

## **DESCRIPTION**

Updates properties for the registered cloud storage in Recovery Manager for Active Directory.

## **EXAMPLES**

### **Example 1**

```
PS C:\> Set-RMADFECloudStorage -Id 7 -DisplayName "MyStorage" -ConnectionString "..." -Container "MyContainer"
```

Updates cloud storage settings for the cloud storage with the Id 7.

## **PARAMETERS**

### **-ConnectionString**

Full connection string to the cloud storage.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-Container**

Name of container in storage account. Backups will be copied to this location.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### **-DisplayName**

Cloud storage display name for the registered storage in Recovery Manager for Active Directory.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

```
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Id

Specifies the cloud storage Id representing the storage you want to update.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases: StorageId
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

## -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -InputObject

Specifies the CloudStorage object representing the storage you want to update.

```
Type: CloudStorage[]  
Parameter Sets: InputObject  
Aliases:
```

```
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## -PassThru

Passes the modified cloud storage along the pipeline.

If this parameter is omitted, the modified cloud storage is not passed along the pipeline.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

**schema: 2.0.0**

# Set-RMADFECloudStorageCollection

## SYNOPSIS

Configure a computer collection to use a registered cloud storage.

## SYNTAX

### Id

```
Set-RMADFECloudStorageCollection [-Collection <ComputerCollection[]>] [-  
CollectionId <Int32[]>] [-Id] <Int32[]>  
[-IgnoreReadOnly] [<CommonParameters>]
```

### InputObject

```
Set-RMADFECloudStorageCollection [-Collection <ComputerCollection[]>] [-  
CollectionId <Int32[]>  
[-InputObject] <CloudStorage[]> [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Configure a computer collection to use a registered cloud storage. Backups from the specified computer collections will be copied to the cloud storage. Multiple computer collections can use a cloud storage account.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADFECloudStorageCollection -Id 2 -CollectionId @(1,2,3)
```

Specifies the computer collections with Id 1, 2 and 3 to copy backups to the cloud storage with Id 2.

## PARAMETERS

### -Collection

Computer collection object.

Type: ComputerCollection[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -CollectionId

Id of computer collection to copy backups from to cloud storage.

Type: Int32[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -Id

Cloud storage Id that is registered in Recovery Manager for Active Directory.

Type: Int32[]

Parameter Sets: Id

Aliases: StorageId

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

### -IgnoreReadOnly

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-InputObject**

Specifies the CloudStorage object representing the storage you want to update.

Type: CloudStorage[]  
Parameter Sets: InputObject  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.CloudStorage[]**

## **OUTPUTS**

**System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Set-RMADFEComputer

## SYNOPSIS

Applies computer settings to the RMADFE project.

## SYNTAX

```
Set-RMADFEComputer [-ComputerName] <String> [-Domain <String>] [-Backup
<Guid>] [-BmrBackup <Guid>]
[-BackupPassword <SecureString>] [-BmrBackupPassword <SecureString>] [-
LocalCredential <PSCredential>]
[-DcCredential <PSCredential>] [-DsrmCredential <PSCredential>] [-
NetworkShareCredential <PSCredential>]
[-BmrBackupNetworkShareCredential <PSCredential>] [-UseDomainSettings
<Boolean>]
[-RecoveryMethod <RecoveryMethod>] [-RestoreSysvolFromBackup <Boolean>] [-
InstallFromMedia <Boolean>]
[-DitPath <String>] [-LogPath <String>] [-SysvolPath <String>] [-
RestoreAdOverBmrBackup <Boolean>]
[-WipeDisks <Boolean>] [-PerformMalwareScan <Boolean>] [-
UseOriginalTargetNetworkSettings <Boolean>]
[-UseNatRouter <Boolean>] [-NatRouterPort <UInt32>] [-NatRouterAddress
<String>] [-TargetIpAddress <String>]
[-IsoIpAddress <String>] [-SubnetMask <String>] [-DefaultGateway <String>]
[-DnsServers <String>]
[-ConfigureAsGlobalCatalog <Boolean>] [-InstallReadOnly <Boolean>] [-
RecoveryMediaPath <String>]
[-RecoveryMediaShareCredential <PSCredential>] [-
SaveRecoveryMediaOnBackupShare <Boolean>]
[-TargetHardwareType <TargetInfrastructureType>] [-
TargetHardwareManagementAddress <String>]
[-TargetHardwareManagementProtocol <String>] [-
TargetHardwareManagementPort <Int32>]
[-TargetHardwareManagementCredential <PSCredential>] [-
TargetHostCreateVMScript <String>]
[-TargetHostBootScript <String>] [-TargetHostEjectScript <String>] [-
CreateVM <Boolean>] [-VMName <String>]
[-VMCPUNum <Int32>] [-VMMemorySize <Int64>] [-HypervisorHost <String>] [-
HypervisorHostPlacement <String>]
[-VMNetwork <String>] [-VMFolder <String>] [-VMNetworkRange <String>] [-
VMSubNetworkName <String>]
[-VMSubNetworkRange <String>] [-UseVMNetworkGateway <Boolean>] [-
VMNetworkGateway <String>] [-VMVpnAddressPool <String>]
[-UseStaticIPAddress <Boolean>] [-DriversPath <String>] [-
AllowAddCustomDrivers <Boolean>]
[-AllowAddCustomDriversFromBackup <Boolean>] [-TargetHardwareBootScript
<String>] [-SubscriptionId <String>]
[-TenantId <String>] [-AutoSelectVMSize <Boolean>] [-VMSize <VMSize>] [-
VMLocation <String>]
[-VMResourceGroup <String>] [-VMSecurityGroup <String>] [-VMStorageType
<String>] [-VMStorageSize <Int32>]
[-VMStorageSizeMode <VMStorageSizeMode>] [-DeleteVMAfterVerify <Boolean>]
```

```
[ -DeleteInfrastructureAfterVerify <Boolean> ] [ -OverwriteExistingVM <Boolean> ] [ -KeepInProject <Boolean> ] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet applies computer settings to the current RMADFE project.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> $dcCreds = Get-Credential  
$dsrmCreds = Get-Credential  
$shareCreds = Get-Credential  
  
Set-RMADFEComputer -Name dc1.acme.com -BackupPassword (ConvertTo-SecureString "pwd" -AsPlainText -Force) -DcCredential $dcCreds -DsrmCredential $dsrmCreds -NetworkShareCredential $shareCreds -UseDomainSettings $false
```

This command applies the specified settings to the dc1.acme.com computer.

### EXAMPLE 2

```
PS C:\> $shareCreds= Get-Credential  
$dcCreds = Get-Credential  
$dsrmCreds = Get-Credential  
$localCreds = Get-Credential  
  
Set-RMADFEComputer -Name dc1.acme.com -NetworkShareCredential $shareCreds -DcCredential $dcCreds -DsrmCredential $dsrmCreds -LocalCredential $localCreds -RecoveryMethod InstallAD -InstallFromMedia $true
```

This command applies the specified settings to the dc1.acme.com computer, and installs AD using media.

## PARAMETERS

### -AllowAddCustomDrivers

Turns on the ability to set up custom drivers.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -AllowAddCustomDriversFromBackup

Turns on the ability to set up custom drivers from the backup.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-AutoSelectVMSize**

Specifies if VM size should be selected automatically.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Backup**

Specifies a System System State backup that is used for recovery.

Type: Guid  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BackupPassword**

Specifies the password to access a password-protected backup.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BmrBackup**

Specifies a Bare Metal Recovery backup that is used in case of the Bare Metal Active Directory Recovery method.

Type: Guid  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BmrBackupNetworkShareCredential**

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers to the BMR backup location.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-BmrBackupPassword**

Specifies the password to access a password-protected BMR backup.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ComputerName**

Specifies the fully qualified domain name of the computer.

Type: String  
Parameter Sets: (All)  
Aliases: Name

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-ConfigureAsGlobalCatalog**

Sets the Global Catalog role for the domain controller.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-CreateVM**

Specifies if a new machine must be created on the target platform.

Type: Boolean

Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DcCredential**

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in the Normal mode.  
Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DefaultGateway**

Specifies the default gateway for the custom Bare Metal Recovery network settings.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DeleteInfrastructureAfterVerify**

Specifies if infrastructure (security group, virtual network, virtual network gateway) must be deleted after project verification.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-DeleteVMAfterVerify**

Specifies if a virtual machine must be deleted after project verification.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-DitPath**

Specifies a path to the DIT file if the custom location is required.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-DnsServers**

Specifies DNS Servers for the custom Bare Metal Recovery network settings.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Domain**

Specifies the Domain DNS name of the computer.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-DriversPath**

Specifies a path to custom drivers.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-DsrmCredential**

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers in Directory Services Restore Mode (DSRM).  
Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-HypervisorHost**

Specifies Hypervisor host name.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-HypervisorHostPlacement**

Specifies the placement of the virtual machine.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-InstallFromMedia**

This option allows you to install or reinstall AD using media.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-InstallReadOnly**

Sets Read-only property for the domain controller.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-IsIpAddress**

Specifies the IP address for ISO image which is used as a boot disk.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-KeepInProject**

Marks domain controller to be recovered later.

If this domain controller is removed from the Active Directory, it will not removed from the project on updating with Active Directory changes.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-LocalCredential**

Specifies local credentials for the computer.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-LogPath**

Specifies a path to Active Directory log files if the custom location is required.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-NatRouterAddress**

Set the NAT routing address (deprecated).

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-NatRouterPort**

Set the NAT routing port (deprecated).

Type: UInt32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-NetworkShareCredential**

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access the selected domain controllers to the backup location.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-OverwriteExistingVM**

Specifies if an existing machine must be deleted before creation.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-PerformMalwareScan**

Specifies if the backup must be scanned for malware threats.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RecoveryMediaPath**

Specifies a path to ISO image which is used as a boot disk.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RecoveryMediaShareCredential**

Specifies credentials to get access to ISO image which is used as a boot disk.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RecoveryMethod**

Specifies the recovery method for this domain controller.

Type: RecoveryMethod

Parameter Sets: (All)

Aliases:

Accepted values: DoNotRecover, RestoreFromBackup, ReinstallAD, AdjustADChanges, UninstallAD, RestoreSYSVOL, InstallAD, RestoreFromWindowsBackup, RestoreOnCleanOS, Skip

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-RestoreAdOverBmrBackup**

This option allows you to select the RMADFE Active Directory and Registry backup to be restored over the BMR backup.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-RestoreSysvolFromBackup**

`{{ Fill RestoreSysvolFromBackup Description }}`

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SaveRecoveryMediaOnBackupShare**

Specifies a location of the ISO image which is used as a boot disk.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SubnetMask**

Specifies a subnet mask for the custom Bare Metal Recovery network settings.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SubscriptionId**

Specifies an Azure SubscriptionId.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-SysvolPath**

Specifies a path to SYSVOL if the custom location is required.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-TargetHardwareBootScript**

Specifies custom script to boot the target host.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-TargetHardwareManagementAddress**

Specifies the address of the target platform for the new domain controller.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-TargetHardwareManagementCredential**

Specifies network credentials for communicating with the platform for the new domain controller.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-TargetHardwareManagementPort**

Specifies the network port for communicating with the platform for the new domain controller.

Type: Int32  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-TargetHardwareManagementProtocol**

Specifies the network protocol for communicating with the platform for the new domain controller.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-TargetHardwareType**

Specifies the target platform for the new domain controller.

Type: TargetInfrastructureType  
Parameter Sets: (All)  
Aliases:  
Accepted values: None, PhysicalDell, PhysicalHP, Custom, VMWare, HyperV, Azure, AWS  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-TargetHostBootScript**

Specifies a custom script to boot the target host.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-TargetHostCreateVMScript**

Specifies a custom script to create a virtual machine on the target platform.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False

```
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-TargetHostEjectScript**

Specifies a custom script to eject bootable disk on the target host.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-TargetIpAddress**

Specifies the target IP for the computer.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-TenantId**

Specifies an Azure TenantId.

```
Type: String
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-UseDomainSettings**

This option lets you use the default domain credentials to access domain controllers.

```
Type: Boolean
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-UseNatRouter**

Allows using NAT (deprecated).

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-UseOriginalTargetNetworkSettings**

This option allows you to use network settings from Bare Metal Recovery backup.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-UseVMNetworkGateway**

Specifies if VPN Gateway should be used to connect the virtual machine.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-VMCPUNum**

Specifies the number of CPUs on the virtual machine.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-VMFolder**

Specifies a target folder for the virtual machine.

Type: String

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMLocation**

Specifies an Azure VM location.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMMemorySize**

Specifies memory size on the virtual machine.

Type: Int64  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMName**

Specifies the name of the virtual machine on the target platform.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMNetwork**

Specifies network settings for the virtual machine.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMNetworkGateway**

Specifies VPN Gateway used to connect the virtual machine.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-VMNetworkRange**

Specifies network range for the virtual network.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-UseStaticIPAddress**

Specifies if static IP address should be assigned to the virtual machine.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-VMResourceGroup**

Specifies an Azure VM resource group.

Type: String

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-VMSecurityGroup**

Specifies an Azure VM security group.

Type: String

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMSize**

Specifies an Azure VM size.

Type: VMSIZE  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMStorageSize**

Specifies the virtual machine disk size in GB.

Applicable with VMStorageSizeMode = SetVMStorageSize.

Type: Int32  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMStorageSizeMode**

Specifies the virtual machine disk size selection mode.

UseDefaultVMStorageSize - set disk size based on the Active Directory data size.

SetVMStorageSize - set custom disk size.

Minimal disk size values are 128 GB for OS disk and 8 GB for AD data disk.

Type: VMStorageSizeMode  
Parameter Sets: (All)  
Aliases:  
Accepted values: UseDefaultVMStorageSize, SetVMStorageSize

Required: False  
Position: Named  
Default value: UseDefaultVMStorageSize  
Accept pipeline input: False  
Accept wildcard characters: False

## **-VMStorageType**

Specifies the virtual machine storage type.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-VMSubNetworkName**

Specifies subnetwork name for the virtual network.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-VMSubNetworkRange**

Specifies subnetwork range for the virtual network.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-VMVpnAddressPool**

Specifies virtual machine address pool.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### **-WipeDisks**

Specifies if a full disk cleanup on the target machine is required before starting restore from the Bare Metal Recovery backup.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Set-RMADFEDnsCache

## SYNOPSIS

Updates cached DNS records in the Forest Recovery project.

## SYNTAX

```
Set-RMADFEDnsCache [-HostName] <String> [-Address] <Object> [-Override] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet updates the cached DNS records for the specified hostname in the Forest Recovery project.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address "192.168.0.2"
```

This command prepends "192.168.0.2" to the cached DNS records of DC1.rmad.local.

### Example 2

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address @("192.168.0.2", "10.0.0.2")
```

This command prepends "192.168.0.2" and "10.0.0.2" to the cached DNS records of DC1.rmad.local.

### Example 3

```
PS C:\> Set-RMADFEDnsCache -HostName DC1.rmad.local -Address "192.168.0.2"  
-Override
```

This command resets the cached DNS records of DC1.rmad.local to "192.168.0.2".

## PARAMETERS

### -Address

Specifies a list of IP addresses for the specified hostname.

Type: Object  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -HostName

Specifies the hostname of the domain controller.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Override

This option lets you reset the cached DNS records to the specified address.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 2  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**None**

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Set-RMADFEDomain

## SYNOPSIS

Sets the domain settings for the current RMADFE project.

## SYNTAX

### AnyParameters (Default)

```
Set-RMADFEDomain [-Domain] <String> [-Recover <Boolean>] [-  
AuthoritativeSysvolRestoreComputer <String>]  
[-ResetPasswords <Boolean>] [-Groups  
<System.Collections.Generic.List`1[System.String]>]  
[-Exclusions <System.Collections.Generic.List`1[System.String]>]  
[<CommonParameters>]
```

### IncludeCredentials

```
Set-RMADFEDomain [-Domain] <String> [-Recover <Boolean>] [-  
AuthoritativeSysvolRestoreComputer <String>]  
-DcCredential <PSCredential> -DsrmCredential <PSCredential> -  
LocalCredential <PSCredential>  
[-ResetPasswords <Boolean>] [-Groups  
<System.Collections.Generic.List`1[System.String]>]  
[-Exclusions <System.Collections.Generic.List`1[System.String]>]  
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet sets the domain settings for the current RMADFE project.

# EXAMPLES

## EXAMPLE 1

```
PS C:\> $dcCreds = Get-Credential  
$dsrmCreds = Get-Credential  
  
Set-RMADFEDomain -Domain acme.com -Recover $true -  
AuthoritativeSysvolRestoreComputer dc1.acme.com -DcCredential $dcCreds -  
DsrmCredential $dsrmCreds
```

This command applies the domain settings to the acme.com domain.

## EXAMPLE 2

```
Set-RMADFEDomain acme.com -ResetPasswords $true -Groups Group_A, Group_B,  
Group_C -Exclusions User_01, User_02
```

This command enables password resetting for domain users in the following privileged groups: Group\_A, Group\_B, and Group\_C in the domain acme.com, except User\_01 and User\_02.

# PARAMETERS

## -AuthoritativeSysvolRestoreComputer

This option allows you to configure the domain controller where the authoritative restore of SYSVOL will be performed.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -DcCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in the Normal mode.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: IncludeCredentials  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Domain

Specifies the fully qualified domain name.

Type: String  
Parameter Sets: (All)

Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -DsrmCredential

Specifies the user name and the password with which you want Recovery Manager for Active Directory Forest Edition to access domain controllers in the selected domain in Directory Services Restore Mode (DSRM). Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Type: PSCredential  
Parameter Sets: IncludeCredentials  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Exclusions

This parameter specifies one or more users (separated by commas). By default, only the domain administrator configured in your project settings is excluded from password resetting. When this parameter is specified, both the administrator and the specified user(s) are excluded.

Type: System.Collections.Generic.List`1[System.String]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Groups

This parameter specifies one or more groups of users (separated by commas). When this parameter is specified, this command ONLY resets the password for the specified groups of users in the domain instead of the predefined administrative accounts.

Type: System.Collections.Generic.List`1[System.String]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -LocalCredential

Specifies local credentials for the machine.

Type: PSCredential  
Parameter Sets: IncludeCredentials

Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Recover

This option lets you include the domain into or exclude the domain from the current RMADFE project.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -ResetPasswords

This parameter resets the password for administrative accounts in the domain during forest recovery, including members of Enterprise Admins, Domain Admins, Administrators, Account Operators, Schema Admins, Group Policy Creator Owners, Backup Operators, Server Operators, and Print Operators.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Set-RMADFEGlobalOptions

## SYNOPSIS

Sets global settings for recovery projects.

## SYNTAX

```
Set-RMADFEGlobalOptions [[-SmtpServer] <String>] [[-SmtpPort] <Int32>] [[-SmtpUserName] <String>]
    [[-SmtpUserPassword] <SecureString>] [[-FromAddress] <String>] [[-ToAddress] <String>]
    [[-SendVerifyNotification] <Boolean>] [[-SendRecoveryNotification] <Boolean>] [[-SmtpEnableSsl] <Boolean>]
    [[-SmtpAuthRequired] <Boolean>] [[-CustomDriversPath] <String>] [[-AgentOperationAbortTimeout] <UInt32>]
    [-Save] [<CommonParameters>]
```

## DESCRIPTION

Sets global settings that will be applied to all recovery projects by default.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADFEGlobalOptions -SmtpServer "server" -SmtpPort 587 -SmtpEnableSsl $true -FromAddress "from@domain.com" -ToAddress "to@domain.com" -SmtpAuthRequired $true -SmtpUserName "username" -SmtpUserPassword "password"
```

This command applies the specified settings to the configuration.

### Example 2

```
PS C:\> Set-RMADFEGlobalOptions -FromAddress "from@domain.com" -ToAddress "to@domain.com" -Save
```

This command applies the specified settings to the configuration and saves the updated settings to the file.

## PARAMETERS

### -AgentOperationAbortTimeout

Specifies the path of a custom driver that you want to add to the Quest Recovery Environment image.

Type: UInt32

Parameter Sets: (All)

Aliases:

Required: False

Position: 12

Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-CustomDriversPath**

Specifies the path to the Quest Recovery Environment image.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 11  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-FromAddress**

Specifies the sender of email notifications.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 4  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-Save**

Saves the global settings to the file.

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SendRecoveryNotification**

Indicates whether the email notification option is enabled for the restore process.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 7  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SendVerifyNotification**

Indicates whether the email notification option is enabled for the verification process.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 6  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SmtpAuthRequired**

Indicates whether a SMTP server requires authentication.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 9  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SmtpEnableSsl**

Indicates whether Secure Sockets Layer (SSL) is used to encrypt the connection with SMTP server.

Type: Boolean  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 8  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SmtpPort**

Specifies the SMTP server port.

Type: Int32  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-SmtpServer**

Specifies the address of the SMTP server.

Type: String  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: 0  
Default value: None

```
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-SmtpUserName**

Specifies the name of the SMTP server.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-SmtpUserPassword**

Specifies the password that is used to access the SMTP server.

Type: SecureString  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: 3  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-ToAddress**

Specifies the recipient of email notifications.

Type: String  
Parameter Sets: (All)  
Aliases:

```
Required: False  
Position: 5  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Set-RMADFEPersistenceConnection

## SYNOPSIS

Sets persistence connection settings.

## SYNTAX

### MSSQLSecurity (Default)

```
Set-RMADFEPersistenceConnection [-DataSource] <String> [-Credentials]
<PSCredential> [<CommonParameters>]
```

### DisableConnection

```
Set-RMADFEPersistenceConnection [-Disable] [<CommonParameters>]
```

### EnableConnection

```
Set-RMADFEPersistenceConnection [-Enable] [<CommonParameters>]
```

### IntegratedSecurity

```
Set-RMADFEPersistenceConnection [-DataSource] <String> [-
IntegratedSecurity] [<CommonParameters>]
```

## DESCRIPTION

Sets persistence connection settings that are used to store the Forest Recovery process state.

# EXAMPLES

## Example 1

```
PS C:\> $creds = new-object PSCredential("sa", (ConvertTo-SecureString  
'Password' -asPlainText -Force))  
Set-RMADFEPersistenceConnection -DataSource "ws\SQLExpress" -Credentials  
$creds  
Get-RMADFEPersistenceConnection
```

This command sets persistence connection settings.

## Example 2

```
PS C:\> Set-RMADFEPersistenceConnection -Disable  
Get-RMADFEPersistenceConnection
```

This command disable persistence connection settings.

# PARAMETERS

## -Credentials

Specifies MS SQL security credentials

Type: PSCredential  
Parameter Sets: MSSQLSecurity  
Aliases:  
  
Required: True  
Position: 3  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -DataSource

Specifies MS SQL instance

Type: String  
Parameter Sets: MSSQLSecurity, IntegratedSecurity  
Aliases:  
  
Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Disable

Disables persistence connection

Type: SwitchParameter  
Parameter Sets: DisableConnection  
Aliases:  
  
Required: True  
Position: 0  
Default value: False  
Accept pipeline input: False

Accept wildcard characters: False

## **-Enable**

Enables persistence connection

Type: SwitchParameter  
Parameter Sets: EnableConnection  
Aliases:

Required: True  
Position: 0  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **-IntegratedSecurity**

Enable Windows Authentication using

Type: SwitchParameter  
Parameter Sets: IntegratedSecurity  
Aliases:

Required: True  
Position: 2  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Set-RMADFERecoveryMode

## SYNOPSIS

Sets recovery mode for the current recovery project

## SYNTAX

```
Set-RMADFERecoveryMode [-RecoveryMode] <RecoveryMode> [[-ExcludingDomains]
<String[]>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet changes the recovery mode of the recovery project.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADFERecoveryMode -RecoveryMode SYSVOLRecovery
```

Sets up SYSVOL recovery mode on the recovery project

### Example 2

```
PS C:\> Set-RMADFERecoveryMode -RecoveryMode DomainRecovery -
ExcludingDomains @("domain1", "domain2")
```

Sets up Domain recovery mode on the recovery project and exclude "domain1" and "domain2" from recovering.

## PARAMETERS

### -ExcludingDomains

Specifies domains that must not be recovered when DomainRecovery mode selected.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -RecoveryMode

Specifies recovery mode which can accept one of the following values: 1.

ForestRecovery - complete forest recovery mode 2.

DomainRecovery - recover selected domains only 3.

SYSVOLRecovery - recover SYSVOL only 4.  
Repromotion - recover domain controllers that were not recovered in previous recovery sessions  
Type: RecoveryMode  
Parameter Sets: (All)  
Aliases:  
Accepted values: ForestRecovery, DomainRecovery, SYSVOLRecovery, Repromotion  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Set-RMADFESchedule

## SYNOPSIS

Applies settings to the verification schedule for the RMADFE project.

## SYNTAX

```
Set-RMADFESchedule [[-Schedules] <Schedule[]>] [-Credential] <PSCredential>
[-NewCredential] <PSCredential>
[-IsEnabled] <Boolean> [<CommonParameters>]
```

## DESCRIPTION

This cmdlet applies settings to the verification schedule for the current RMADFE project.

## EXAMPLES

### Example 1

```
PS C:\> $schedule = New-RMADFESchedule -Once -StartDate "2/20/2008 1:00"
$credential = Get-Credential
Set-RMADFESchedule -Schedules $schedule -Credential $credential -IsEnabled
$true
```

Set a one-time schedule for the current project.

Schedule is enabled and will run under the specified user account.

## PARAMETERS

### -Credential

Specifies credentials that will be used to run the command.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -IsEnabled

Specifies whether the schedule is enabled.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 3  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -NewCredential

Credential to change an account to.

If a new credential is specified, the Credential parameter should contain the previous account credential for a task.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: 2  
Default value: None  
Accept pipeline input: False

Accept wildcard characters: False

## -Schedules

Specifies schedules for project verification.

Type: Schedule[]

Parameter Sets: (All)

Aliases:

Required: False

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Set-RMADGlobalOptions

## SYNOPSIS

Sets global application settings

## SYNTAX

```
Set-RMADGlobalOptions [-EmailServer <String>] [-EmailSender <String>] [-ExtendedLogging <Boolean>]
[-Properties <Hashtable>] [-IgnoreReadOnly] [-WhatIf] [-Confirm]
[<CommonParameters>]
```

## DESCRIPTION

Sets Recovery Manager global application settings

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADGlobalOptions -EmailServer "WS.DomainName.local"  
Set-RMADGlobalOptions -EmailSender "from@WS.DomainName.local"  
Set-RMADGlobalOptions -ExtendedLogging $True
```

This command sets global email settings in Recovery Manager for Active Directory.

### Example 2

```
PS C:\> $mailOptions = @{  
    "Email.Server"      ='WS.DomainName.local';  
    "Email.UseSSL"     =$True;  
    "Email.Sender"      ='from@WS.DomainName.local';  
    "Email.AuthRequired"=$True;  
    "Email.UserName"   ='SmtpAccount';  
    "Email.Password"   ='Password'  
}  
Set-RMADGlobalOptions -Properties $mailOptions
```

This command sets global email settings in Recovery Manager for Active Directory using the 'Properties' option.

### Example 3

```
PS C:\> Set-RMADGlobalOptions -Properties @{"UseRestoreAgentPort" = $True;  
"DefaultRestoreMethod" = 0; "AgentPort" = 3845 }
```

This command sets Recovery Manager global settings for agent.

## PARAMETERS

### -EmailSender

Specifies the sender field of e-mail notifications

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -EmailServer

Specifies the SMTP server for e-mail notifications

Type: String  
Parameter Sets: (All)  
Aliases:

Required: False

```
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-ExtendedLogging**

Specifies diagnostic logs

```
Type: Boolean  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

```
Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Properties**

Allows you to modify the application settings.

To specify the properties you want to modify, use an associative array or hash table.

For more information, see the Windows PowerShell help topic on associative arrays (hash tables).

To open the topic, at the PowerShell command prompt enter the following: help about\_associative\_arrayBelow are the properties you can modify by using this parameter.

The properties are grouped by the names of tabs in the "Computer Collection Properties" dialog box, because each property corresponds to an option on these tabs. To assign a new value to a property, use the following format:PropertyName=Value E-MAIL TAB \* Email.Server.

Specifies the SMTP server for e-mail notifications \* Email.Port.

Specifies the SMTP port for e-mail notifications \* Email.Sender.

Specifies the sender of e-mail notifications LOGGING TAB \* ExtendedLogging.

Specifies option "Use diagnostic logging" \* LogsFolder.

Specify the directory for application logs.

```
Type: Hashtable  
Parameter Sets: (All)  
Aliases:
```

```
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## **-Confirm**

Prompts for a confirmation before executing the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

### **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Set-RMADReplicationConsole**

## **SYNOPSIS**

Sets replication properties of consoles in the replication console list.

# SYNTAX

## **Id**

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>]
[-FallbackCredential <PSCredential>] [-Id] <Int32[]> [<CommonParameters>]
```

## **ComputerName**

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>]
[-FallbackCredential <PSCredential>] [-ComputerName] <String[]>
[<CommonParameters>]
```

## **InputObject**

```
Set-RMADReplicationConsole [-AccessCredential <PSCredential>] [-Enabled <Boolean>]
[-FallbackCredential <PSCredential>] [-InputObject] <ReplicationConsole[]>
[<CommonParameters>]
```

# DESCRIPTION

Updates user credentials for connecting to a specified computer, and enables/disables the manual and scheduled replication for the console.

# EXAMPLES

## **Example 1**

```
PS C:\> C:\>$credential = Get-Credential
C:\>Set-RMADReplicationConsole -ComputerName Hostname1 -AccessCredential
$credential -Enabled $true
```

This command changes the credentials for accessing the console on Hostname1, and enables the replication for the console.

## **Example 2**

```
PS C:\> C:\>Set-RMADReplicationConsole -Id 1 -AccessCredential $credential
-Enabled $true
```

This command changes the credentials for accessing the console with specified ID, and enables the replication for the console.

## **Example 3**

```
PS C:\> C:\>Set-RMADReplicationConsole -ComputerName Hostname1 -
FallbackCredential $($([System.Management.Automation.PSCredential]::Empty))
```

This command removes the fallback account for the console on Hostname1.

# PARAMETERS

## -AccessCredential

Specifies the user credentials to read data from the target computer.

The user must be a local Administrator on the target computer.

To obtain the user credentials, create a PSCredential object using the Get-Credential cmdlet provided by Windows PowerShell.

If you need to use the credentials of the currently logged in user, specify [System.Management.Automation.PSCredential]::Empty value for this parameter.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -ComputerName

Specifies the hostname of the replication console.

Type: String[]

Parameter Sets: ComputerName

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

## -Enabled

Set replication item enabled.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## -FallbackCredential

Supplies a fallback account for replacing the account that is used by the backup schedule task.

The account must have administrator privileges on the system(s) to be backed up.

If you need to reset the fallback account, specify [System.Management.Automation.PSCredential]::Empty value for this parameter.

You can use this parameter only when Full mode is set for the console.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

```
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -Id

Specifies the ID of the replication console.

```
Type: Int32[]  
Parameter Sets: Id  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False
```

## -InputObject

Specifies the replication console object you want to update.

```
Type: ReplicationConsole[]  
Parameter Sets: InputObject  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Set-RMADReplicationSchedule

## SYNOPSIS

Sets replication schedules for a computer.

## SYNTAX

```
Set-RMADReplicationSchedule [-Schedules <Schedule[]>] -Credential <PSCredential> [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

Sets replication schedules with credentials for the Recovery Manager computer you specify.

## EXAMPLES

### Example 1

```
PS C:\> $credential = Get-Credential  
$schedule=(New-RMADSchedule -Daily -StartDate "9/20/2013 10:00" -  
DaysInterval 1), (New-RMADSchedule -Daily -StartDate "9/20/2013 22:00" -  
DaysInterval 1)  
C:\PS>Set-RMADReplicationSchedule -Schedule $schedule
```

This example illustrates how to replicate computers by using two replication schedules.

The first line of this example creates a PSCredential object.

The second line of this example creates two replication schedules and stores them in the \$schedule variable.

One schedule invokes the replicate operation once in every two days at 10 a.m.

Another schedule invokes the replicate operation once in every two days at 10 p.m.

The two replication schedules become effective starting from the 20th September 2013.

The third line of this example set schedules with credentials to the computer you specify.

### Example 2

```
PS C:\> $credential = Get-Credential  
C:\PS>Set-RMADReplicationSchedule -Credential $credential
```

This command updates the credentials for an existing schedule.

## PARAMETERS

### -Credential

Specifies the user credentials for setting the replication schedule.

The user must be a local Administrator on the target computer.

To obtain the user credentials, create a PSCredential object using the Get-Credential cmdlet provided by Windows PowerShell.

Type: PSCredential

Parameter Sets: (All)

Aliases:

```
Required: True
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Schedules

Causes the computer you specify to use the replication schedule you set by using the New-RMADSchedule cmdlet.

```
Type: Schedule[]
Parameter Sets: (All)
Aliases:
```

```
Required: False
Position: Named
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## -Confirm

Prompts for confirmation before executing the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## -WhatIf

Describes what would happen if you ran the command without actually running the command.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi
```

```
Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## schema: 2.0.0

# Set-RMADStorageServerAllowedVolumes

## SYNOPSIS

## SYNTAX

```
Set-RMADStorageServerAllowedVolumes [-Volumes] <String[]> [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet sets the list of volumes that the Secure Storage server will use for storing new backup files.

## EXAMPLES

### Example 1

```
PS C:\> Set-RMADStorageServerAllowedVolumes 'C:','D:'  
Saving volume policy...
```

```
Volumes  
-----  
{C:, D:}
```

Sets the allowed volumes for Secure Storage backups to be C: and D:.

### Example 2

```
PS C:\> Set-RMADStorageServerAllowedVolumes @('C:','D:')  
Saving volume policy...
```

```
Volumes  
-----
```

```
{C:, D:}
```

Sets the allowed volumes for Secure Storage backups to be C: and D: using an explicit string array.

### Example 3

```
PS C:\> Set-RMADStorageServerAllowedVolumes @()  
Saving volume policy...
```

```
Volumes  
-----  
{ }
```

Clears the list of allowed volumes. This will cause Secure Storage to automatically chose which volume to use when storing backups. The system drive will not be selected.

## PARAMETERS

### -Force

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -Volumes

Specifies the list of volumes that the Storage Server can use for storing backups.

This list must include only drive letters in the form 'X:'.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -Confirm

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage

online version:

## **schema: 2.0.0**

# **Set-RMADStorageServerRetentionPolicy**

## **SYNOPSIS**

Sets the retention policy status of the current server.

## **SYNTAX**

```
Set-RMADStorageServerRetentionPolicy [-DaysToKeep] <Int32> [ [-  
IncludeLWTProcessing] <Boolean>] [-Force]  
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet sets the retention policy of the current server.

The default number of days to retain backups on a Secure Storage server is 0 days. Ensure you configure the backup retention policy after adding a new Secure Storage server.

## EXAMPLES

### Example 1

```
PS C:\>Set-RMADStorageServerRetentionPolicy -DaysToKeep 30
```

## PARAMETERS

### -DaysToKeep

Specify the number of days to keep backup files on the secure storage server.

Type: Int32

Parameter Sets: (All)

Aliases:

Required: True

Position: 1

Default value: 0

Accept pipeline input: False

Accept wildcard characters: False

### -Force

@{Text=}

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -IncludeLWTProcessing

{Specify true to enable the use of Last Write Time.

In some cases, the backups may not include a copy of their backup details which contains the time the backup was created.

This means the current retention policy for number of days will not affect these backups.

If IncludeLWTProcessing is set to true the retention policy processor will check the Last Write Time of the backup file and use that.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: 2

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Start-RMADFERecovery

## SYNOPSIS

Performs the restore operation for the RMADFE project.

## SYNTAX

```
Start-RMADFERecovery [-Force] [-NotifyByEmail <Boolean>] [-GroupPasswords <Hashtable>] [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet starts the restore operation on the current RMADFE project.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Start-RMADFERecovery
```

This command performs the restore operation on the current RMADFE project.

## EXAMPLE 2

```
$pwd1 = ConvertTo-SecureString "new password 1" -AsPlainText -Force
$pwd2 = ConvertTo-SecureString "new password 2" -AsPlainText -Force
$pwd3 = ConvertTo-SecureString "new password 3" -AsPlainText -Force
$passwords = @{ "Enterprise Admins"=$pwd1; "Domain Admins"=$pwd2;
"Administrators"=$pwd3 }
Start-RMADFERecovery -GroupPasswords $passwords
```

This command performs the restore operation and resets the password for domain users in the following privileged groups: Enterprise Admins, Domain Admins, and Administrators.

## PARAMETERS

### -Force

Overrides restrictions that prevent the command from succeeding, apart from security settings.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

### -GroupPasswords

Resets a password for domain users in specified privileged groups.

The new password can be only used once, users must change their password after logging in with the new password.

Use the Set-RMADFEDomain cmdlet to enable the password resetting before you reset the password with this parameter.

The password resetting option is available only for Forest Recovery and Domain Recovery modes.

Type: Hashtable

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -NotifyByEmail

Allows notification about the recovery result by email.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **-Confirm**

Prompts for confirmation before running the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Describes what would happen if you ran the command without actually running the command.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Start-RMADFERecoveryAgentOperation

## SYNOPSIS

Starts so-called agent operation on the remote machine where Forest Recovery agent is installed.

## SYNTAX

### ProjectSpecificParameters

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> -Parameters  
<OperationParameters>  
[-AgentPort <UInt32>] [<CommonParameters>]
```

### ProjectLessNormalMode

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-DcCredential  
<PSCredential>]  
-Parameters <OperationParameters> [-AgentPort <UInt32>]  
[<CommonParameters>]
```

### ProjectLessDsrm

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-  
DsrmCredential <PSCredential>]  
-Parameters <OperationParameters> [-AgentPort <UInt32>]  
[<CommonParameters>]
```

### ProjectLessBothMode

```
Start-RMADFERecoveryAgentOperation [-ComputerName] <String> [-DcCredential  
<PSCredential>]  
[-DsrmCredential <PSCredential>] -Parameters <OperationParameters> [-  
AgentPort <UInt32>] [<CommonParameters>]
```

## DESCRIPTION

Starts so-called agent operation on the remote machine where Forest Recovery agent is installed. Operation type and parameters are defined in the Parameters parameter.

## EXAMPLES

### Example 1

```
PS C:\> {{ Add example code here }}  
{{ Add example description here }}
```

# PARAMETERS

## -AgentPort

```
 {{ Fill AgentPort Description }}  
Type: UInt32  
Parameter Sets: (All)  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -ComputerName

Target machine name or IP address.

```
Type: String  
Parameter Sets: ProjectSpecificParameters  
Aliases:  
  
Required: False  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False  
Type: String  
Parameter Sets: ProjectLessNormalMode, ProjectLessDsrm, ProjectLessBothMode  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -DcCredential

Credentials used to access DC when DC booted in normal mode.

Not used in most cases when Schannel authentication is used between agent and console.

```
Type: PSCredential  
Parameter Sets: ProjectLessNormalMode, ProjectLessBothMode  
Aliases:  
  
Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False
```

## -DsrmCredential

Credentials used to access DC when DC booted in the DSRM.

Not used in most cases when Schannel authentication is used between agent and console.

```
Type: PSCredential  
Parameter Sets: ProjectLessDsrm, ProjectLessBothMode  
Aliases:
```

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Parameters

An OperationParameters object specifies operation type and parameters.

Type: OperationParameters  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**None**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Start-RMADFEVerification

## SYNOPSIS

Performs verification of the RMADFE project.

## SYNTAX

```
Start-RMADFEVerification [-ComputerName <String[]>] [-NotifyByEmail <Boolean>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet collects and saves information that is used for recovery from all domain controllers in the recovery project.

Then, it checks the project recovery settings against the collected information to provide you information about any inconsistencies.

Start a new project session by calling the Start-RMADFEProjectSession cmdlet first.

Use the Get-RMADFEProjectSummary cmdlet to track the progress of the project session.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Start-RMADFEVerification
```

This command performs verification of the current RMADFE project.

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### -NotifyByEmail

Allows notification about the recovery result by email.

Type: Boolean

Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Start-RMADReplication

## SYNOPSIS

Performs replication from other computers in the replication console list.

## SYNTAX

```
Start-RMADReplication [-Id <Int32[]>] [-ComputerName <String[]>] [-AsJob]
[<CommonParameters>]
```

## DESCRIPTION

Performs replication from other computers in the replication console list.

## EXAMPLES

### Example 1

```
PS C:\> Start-RMADReplication
```

perform replication

## Example 2

```
PS C:\> Start-RMADReplication -AsJob
```

This command performs the replication as a background job.

## Example 3

```
PS C:\> Start-RMADReplication -Id 1
```

This command performs replication from a replication console by its ID.

## Example 4

```
PS C:\> Start-RMADReplication -ComputerName ws1
```

This command performs replication from a replication console by its hostname.

# PARAMETERS

## -AsJob

Runs the command as a background job.

You can use this parameter to run commands that take a significant time to complete.

Type: SwitchParameter  
Parameter Sets: (All)

Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

## -ComputerName

Specifies the hostname of the replication console.

Type: String[]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## -Id

Specifies the ID of the replication console.

Type: Int32[]  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## schema: 2.0.0

# Start-RMADReportViewer

## SYNOPSIS

Displays a report about the results of the online comparison or restore operation.

## SYNTAX

```
Start-RMADReportViewer [-SqlCredential <PSCredential>] [<CommonParameters>]
```

## DESCRIPTION

Displays a report about the results of the online comparison or restore operation.

## EXAMPLES

### Example

```
PS C:\> Start-RMADReportViewer
```

Displays the online comparison or restoration report.

# PARAMETERS

## **-SqlCredential**

Specifies the user name and password of the user account with which you want to connect to SQL Server to generate a report.

The user name and password must be in the form of a PSCredential object.

When this parameter is omitted, the cmdlet uses the credentials of the account under which Management Shell is running.

Use the Get-Credential cmdlet provided by Windows PowerShell to pass a PSCredential object to this parameter.

Type: PSCredential

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

# INPUTS

# OUTPUTS

# NOTES

# RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## **schema: 2.0.0**

# Stop-RMADFECloudStorageUploadSession

## **SYNOPSIS**

Cancel queued or running cloud storage upload session.

# SYNTAX

## **Id**

```
Stop-RMADFECloudStorageUploadSession [-Id] <Int32[]> [-IgnoreReadOnly]  
[<CommonParameters>]
```

## **InputObject**

```
Stop-RMADFECloudStorageUploadSession [-InputObject] <UploadSession[]> [-  
IgnoreReadOnly] [<CommonParameters>]
```

# DESCRIPTION

Cancel a queued or running cloud storage upload session. The copy of the backup is stopped.

# EXAMPLES

## **Example 1**

```
PS C:\> Stop-RMADFECloudStorageUploadSession -Id 4
```

Cancel cloud storage upload session with Id 4.

# PARAMETERS

## **-Id**

Specifies the upload session Id representing the upload session you want to stopped.

Type: Int32[]  
Parameter Sets: Id  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByPropertyName, ByValue)  
Accept wildcard characters: False

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication (for internal use only).

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## **-InputObject**

Specifies the UploadSession object representing the cloud storage upload session you want to cancel.

Type: UploadSession[]

```
Parameter Sets: InputObject
Aliases:

Required: True
Position: 0
Default value: None
Accept pipeline input: True (ByValue)
Accept wildcard characters: False
```

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

**System.Int32[]**

**QuestSoftware.RecoveryManager.AD.FE.PowerShell.UploadSession[]**

## OUTPUTS

**System.Object**

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShellFE  
online version:

## schema: 2.0.0

# Stop-RMADFEWorkflow

## SYNOPSIS

Stops the verification or recovery workflow of the recovery project.

## SYNTAX

```
Stop-RMADFEWorkflow [-ComputerName <String[]>] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet cancels the current workflow for the specified domain controllers, or the whole session if no parameters are provided.

## EXAMPLES

### EXAMPLE 1

```
PS C:\> Stop-RMADFEWorkflow
```

## PARAMETERS

### -ComputerName

Specifies the fully qualified domain name of the computer.

Type: String[]

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: None

Accept pipeline input: False

Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Test-RMADSecureStorageBackup

## SYNOPSIS

Checks the integrity of a backup on the secure storage server.

## SYNTAX

### Name

```
Test-RMADSecureStorageBackup [-BackupPath] <String> [-Name] <String>
[<CommonParameters>]
```

### Server

```
Test-RMADSecureStorageBackup [-BackupPath] <String> [-Server]
<StorageServer> [<CommonParameters>]
```

## DESCRIPTION

Checks the integrity of a backup on the secure storage server. This operation calculates the checksum of the backup file and compares it with the checksum stored in the backup.

## EXAMPLES

### Example 1

```
Test-RMADSecureStorageBackup -Name 'storage' -BackupPath
'E:\Backups\DC1.rmad.local\2020-09-10 14-54-49.bkf'
```

## PARAMETERS

### -BackupPath

Path to the backup file stored on the secure storage server.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

### -Name

Specifies the name of the secure storage server.

Type: String

Parameter Sets: Name  
Aliases:  
  
Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **-Server**

Specifies the target storage server. Use Get-RMADStorageServer to get server objects.

Type: StorageServer  
Parameter Sets: Server  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: True (ByValue)  
Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

### **System.String**

**QuestSoftware.RecoveryManager.AD.PowerShell.Cmdlets.StorageServersManagement.StorageServer**

## **OUTPUTS**

### **System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: Quest.RecoveryManager.AD.PowerShell.SecureStorage.psm1-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell.SecureStorage  
online version:

## schema: 2.0.0

# Unprotect-RMADStorageServer

## SYNOPSIS

Disables hardening on the storage server.

## SYNTAX

```
Unprotect-RMADStorageServer [-Force] [-Wait] [-WhatIf] [-Confirm]  
[<CommonParameters>]
```

## DESCRIPTION

This cmdlet disables hardening on the current storage server.

Unhardening includes enabling network traffic and enabling SMB on the server.

## EXAMPLES

### Example 1

```
PS C:\> Unprotect-RMADStorageServer
```

Disables hardening on the current storage server.

## PARAMETERS

### -Force

@{Text=}

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False  
Accept wildcard characters: False

### -Wait

@{Text=}

Type: SwitchParameter  
Parameter Sets: (All)  
Aliases:

Required: False  
Position: Named  
Default value: False  
Accept pipeline input: False

Accept wildcard characters: False

## **-Confirm**

Prompts you for confirmation before running the cmdlet.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: cf

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **-WhatIf**

Shows what would happen if the cmdlet runs.

The cmdlet is not run.

Type: SwitchParameter

Parameter Sets: (All)

Aliases: wi

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

### **None**

## **OUTPUTS**

### **System.Object**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShell

online version:

## schema: 2.0.0

# Update-RMADBackupAgent

## SYNOPSIS

Upgrades Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

## SYNTAX

### DC

```
Update-RMADBackupAgent [-Computer] <String> [[-Credentials] <PSCredential>]
[-ConfigureFirewall] <Boolean>
[-IgnoreReadOnly] [<CommonParameters>]
```

### Collection

```
Update-RMADBackupAgent [[-Credentials] <PSCredential>] [[-ConfigureFirewall] <Boolean>]
[-CollectionName] <String> [-IgnoreReadOnly] [<CommonParameters>]
```

## DESCRIPTION

Allows you to upgrade Recovery Manager Backup Agent on a specified computer or on each computer in a particular Computer Collection.

## EXAMPLES

### Example 1

```
PS C:\> Update-RMADBackupAgent -CollectionName "New Computer Collection"
```

This code upgrades Recovery Manager Backup Agent on each computer in a collection named "New Computer Collection".

### Example 2

```
PS C:\> $credential = Get-Credential
Update-RMADBackupAgent -Computer dc1 -Credentials $credential
```

This code connects to the computer "dc1" under the user represented by the "credential" object and upgrades Recovery Manager Backup Agent there.

## PARAMETERS

### -CollectionName

Specifies the name of the Computer Collection that includes the computers on which Backup Agent should be upgraded.

Type: String

Parameter Sets: Collection

Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Computer**

Specifies the name of the computer on which to upgrade a Recovery Manager Backup Agent.

Type: String  
Parameter Sets: DC  
Aliases:

```
Required: True
Position: 0
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-ConfigureFirewall**

Specifies whether Recovery Manager automatically configures Windows Firewall on target Windows Server 2008-based or Windows Server 2012-based DCs to allow backup operations.

Type: Boolean  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: 2
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-Credentials**

Specifies the user name and the password of the user account to use for connecting to the target computer and upgrading Backup Agent.

Use the Get-Credential cmdlet provided by Windows PowerShell to get the PSCredential object representing user credentials.

Notes: \* The user should be a local Administrator on the target computer.

- If you omit this parameter, Backup Agent will be upgraded under the current user account.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

```
Required: False
Position: 1
Default value: None
Accept pipeline input: False
Accept wildcard characters: False
```

## **-IgnoreReadOnly**

Allows you to perform the action in a console currently performing full replication.

Type: SwitchParameter

Parameter Sets: (All)

Aliases:

Required: False

Position: Named

Default value: False

Accept pipeline input: False

Accept wildcard characters: False

## CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShellFE.dll-Help.xml

Module Name: Quest.RecoveryManager.AD.PowerShellFE

online version:

## schema: 2.0.0

# Update-RMADFEProject

## SYNOPSIS

Shows the difference between the current project and live Active Directory and updates the project.

## SYNTAX

```
Update-RMADFEProject [-ForestName] <String> [-Credential] <PSCredential> [-WhatIf] [-Confirm] [<CommonParameters>]
```

## DESCRIPTION

This cmdlet shows the difference between the currently opened recovery project and live Active Directory. The confirmation will be requested before applying changes to the project.

# EXAMPLES

## Example 1

```
PS C:\> $credentialas = New-Object PSCredential(".\Administrator",
(ConvertTo-SecureString 'Password' -AsPlainText -Force))

Update-RMADFEProject -ForestName "acme.test" -Credential $credential -WhatIf
```

Shows the difference between the current recovery project and the forest "acme.test".

## Example 2

```
PS C:\> $credentialas = New-Object PSCredential(".\Administrator",
(ConvertTo-SecureString 'Password' -AsPlainText -Force))

Update-RMADFEProject -ForestName "acme.test" -Credential $credential -Confirm:$true

Save-RMADFEProject -Path "UpdatedProject.frproj" -Password (ConvertTo-SecureString "protection password" -AsPlainText -Force)
```

Checks and shows the difference between the current project and the forest "acme.test", and then applies the changes to the project.

To keep the project updated, you have to save it.

# PARAMETERS

## -Credential

Credentials that are used to connect to the target Active Directory to retrieve infrastructure information.

Type: PSCredential  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 1  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -ForestName

Name of the target Active Directory forest.

Type: String  
Parameter Sets: (All)  
Aliases:

Required: True  
Position: 0  
Default value: None  
Accept pipeline input: False  
Accept wildcard characters: False

## -Confirm

Automatically confirms the update of the recovery project.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: cf

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

### **-WhatIf**

If specified, this parameter shows difference only and does not apply any changes to the recovery project.

```
Type: SwitchParameter
Parameter Sets: (All)
Aliases: wi

Required: False
Position: Named
Default value: False
Accept pipeline input: False
Accept wildcard characters: False
```

## **CommonParameters**

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## **INPUTS**

## **OUTPUTS**

## **NOTES**

## **RELATED LINKS**

---

external help file: QuestSoftware.RecoveryManager.AD.PowerShell.dll-Help.xml  
Module Name: Quest.RecoveryManager.AD.PowerShell  
online version:

## **schema: 2.0.0**

# **Update-RMADLicense**

## **SYNOPSIS**

Updates license key file.

## SYNTAX

```
Update-RMADLicense [-File] <String> [<CommonParameters>]
```

## DESCRIPTION

Allows you to update the current license key file to a new one.

## EXAMPLES

### Example 1

```
PS C:\> Update-RMADLicense -File C:\license.asc
```

Updates current license using license key file C:\license.asc.

## PARAMETERS

### -File

Full path to a new license key file.

Type: String

Parameter Sets: (All)

Aliases:

Required: True

Position: 0

Default value: None

Accept pipeline input: True (ByValue)

Accept wildcard characters: False

### CommonParameters

This cmdlet supports the common parameters: -Debug, -ErrorAction, -ErrorVariable, -InformationAction, -InformationVariable, -OutVariable, -OutBuffer, -PipelineVariable, -Verbose, -WarningAction, and -WarningVariable. For more information, see [about\\_CommonParameters](#).

## INPUTS

## OUTPUTS

## NOTES

## RELATED LINKS

# About us

---

Quest creates software solutions that make the benefits of new technology real in an increasingly complex IT landscape. From database and systems management, to Active Directory and Office 365 management, and cyber security resilience, Quest helps customers solve their next IT challenge now. Around the globe, more than 130,000 companies and 95% of the Fortune 500 count on Quest to deliver proactive management and monitoring for the next enterprise initiative, find the next solution for complex Microsoft challenges and stay ahead of the next threat. Quest Software. Where next meets now. For more information, visit [www.quest.com](http://www.quest.com).

## Technical support resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product.