

KACE Privilege Manager for Windows 4.4

Release Notes

May 2020

These release notes provide information about the KACE Privilege Manager for Windows release.

Topics:

[About this release](#)

[Enhancements](#)

[Resolved issues](#)

[Known issues](#)

[System requirements](#)

[Product licensing](#)

[Product improvement program](#)

[Upgrade and installation instructions](#)

[More resources](#)

[Globalization](#)

[About us](#)

About this release

Giving users administrator rights creates security risks but must be weighed against constant help desk calls for basic operations like updating Adobe Reader, Java, or simply changing the time zone on desktops.

Privilege Manager lets you grant selected privileges to users so they can update their own computers, reducing help desk calls while maintaining a secure network. By automating user privilege settings, Privilege Manager keeps users working; this enables you to focus on higher priority tasks, for exceptional resource and time savings.

As a system administrator, you can use Privilege Manager to elevate and manage user rights quickly and precisely with validation logic targeting technology. This provides administrators the ability to create rules that

allow administrator-level access to specific applications for specific users. You can also enable your end users to request elevated privileges for specific applications through Self-Service and Instant Elevation.

- Privilege Manager for Windows 4.4 is a minor release, with new enhancements and resolved issues. See [Enhancements](#) and [Resolved issues](#).

i **IMPORTANT:** Customers upgrading from previous versions of Privilege Manager, such as 3.x and earlier, are required to obtain a new license file. Please refer to the Product licensing section of this document for additional information.

i **IMPORTANT:** The security status of the installation file can become "blocked" after download, inhibiting the ability of the product to be properly installed. Please see [KB 262298](#) for information on detecting and resolving this issue.

Enhancements

The following is a list of enhancements implemented in Privilege Manager for Windows 4.4.

Table 1: Console enhancements

Enhancement	Issue ID
Added support for Privilege Manager Console to target existing MS SQL Server 2019 for database.	932
Added support to install Privilege Manager on MS Windows Server 2019.	930

Table 2: Client enhancement

Enhancement	Issue ID
Added support to manage Windows Server 2019 as a Privilege Manager Client.	931

Resolved issues

The following is a list of issues addressed in this release.

Table 3: Console resolved issue

Resolved Issue	Issue ID
Fixed issue with Privilege Manager Console unnecessarily downloading Remote Server Administration Tools(RSAT).	911

Table 4: Client resolved issues

Resolved Issue	Issue ID
Application filters for Executable Name and Publisher were not working in all cases for Self-Service.	954
Process caching was working incorrectly on Instant Elevation and Self-Service functions.	950
Fixed issue with process caching to improve performance.	935
Fixed performance issue by disabling Client logging by default.	913
Privilege Manager Client was incorrectly displaying the <i>Elevated processes will be terminated</i> message when setting was not selected.	608

Known issues

The following is a list of issues, including those attributed to third-party products, known to exist at the time of release.

Table 5: General known issues

Known Issue	Issue ID
Some log files are still being created and maintained on the system drive even when Privilege Manager has been installed to a non-system drive.	618
Some duplicate records exist in the database and could be optimized.	624
No ability to perform a database cleanup of the records stored in the Privilege Manager database.	623
With Data Collection enabled, possible startup delay on Windows 10 workstations (stuck at "please wait.." for an extended period of time) if the workstation is unable to resolve the DNS name of the currently configured Data Collection server. Workaround: Replace the configured Data Collection server name with the IP address for the Data Collection server.	790
"Error 1920" encountered during a PM Client installation repair (initiated from Add/Remove Programs), if the PM Client was manually installed. Workaround: Instead of performing a repair, the Client can be manually uninstalled then re-installed.	721
CSEHostEngine.log grows quickly.	824
PM Client icon occasionally shows wrong wording when Windows Display Language is non-English.	904

Table 6: Installation and Upgrade known issues

Known Issue	Issue ID
Privilege Manager may fail to install SQL Express correctly if the Privilege Manager Reporting setup reboots after the installation of Windows Installer v 4.5.	586
Occasionally, SQL Server 2008 Express may fail to install. Workaround: Use a remote database or try to install SQL Server 2008 Express on your own. If you call Tech Support, please provide the SQL Server 2008 Express install logs (found at %ProgramFiles%\Microsoft SQL Server\100\Setup Bootstrap\Log). We'll try to solve the problem.	658
There is a problem sending data from clients to the database installed with the Privilege Manager Console if there is an older Privilege Authority or Privilege Manager Client running on the network. Workaround: Ensure that the Client Data Collection Settings in the Advanced Policy Settings for the relevant GPO are enabled and that the Privilege Manager Server information is correct. Also, make sure that the Privilege Authority clients are upgraded to the current version.	1568
Some files might still be present after the Console or Client are uninstalled.	1837
Installing the Client on Windows 8.1 and Windows Server 2012 R2 operating systems using the Client Deployment Settings Wizard might take longer than installing the Client on previous versions of Windows.	1939
After uninstalling the Privilege Manager Console from a computer that also has the Privilege Manager Client installed, the Start menu shortcut to the Privilege Manager for Windows User Guide will fail to open the guide and instead prompt the user for the location of the PAClient.msi file. Workaround: Either uninstall and the re-install the Privilege Manager Client, or re-install the Privilege Manager Console.	1960
Applying a pro license to an installation with an expired trial license can cause the loss of previously saved policies.	535
Server Upgrade from 2.5 - problem in msi upgrade from v2.5 (service being unregistered).	1615
Rules in GPOs do not work after an upgrade from v 2.0.x. Workaround: To make your rules work after an upgrade, re-save them. Or force Gpupdate on your Client.	653

Table 7: Licensing known issues

Known Issue	Issue ID
Applying a Professional license fails to prevent a rule with an expiration date from expiring. Workaround: After you apply the license, open a rule that is going to expire, make your changes, and save it.	932

Table 8: Server known issues

Known Issue	Issue ID
<p>Sometimes when configuring the reporting feature, the connection to the web service fails on the last step of the wizard.</p> <p>Workaround: Try again (click the Previous and Next buttons).</p>	834
<p>If you select a remote Privilege Manager Server on a computer with a firewall enabled, you may encounter a "Database Connection" error when using the Reporting or Discovery and Remediation functions.</p> <p>Workaround: Add the following firewall exceptions to the remote Privilege Manager Server:</p> <ul style="list-style-type: none"> • SQL Server Browser Service: %ProgramFiles(x86)%Microsoft SQL Server\90\Shared\sqlbrowser.exe • SQL Server<ServerName>: %ProgramFiles%Microsoft SQL Server\MSSQL10.PAREPORTING\MSSQL\Binn\sqlservr.exe 	1105
<p>Clients using SQL Server 2012 for their Privilege Manager database may fail to send their data.</p> <p>Workaround: Reinstall the server using the Privilege Manager Server Configuration Wizard.</p>	1655
<p>If Windows Firewall is configured to deny connections (the "Don't allow exceptions" and "Block all connections" options are chosen in all other operating systems), Privilege Manager does not automatically override the settings when configuring firewall exceptions during Privilege Manager Server setup.</p> <p>Workaround: Add an exception to the firewall manually for %ProgramFiles(x86)%\Quest\Privilege Authority\Console\Data Collection Service\PADataCollectionWinSvc.exe.</p>	1657
<p>While using the Privilege Manager Server Setup wizard to download and install SQL Server Express on Windows 8.1, the user might receive a message that the computer needs to be rebooted.</p> <p>Workaround: Reboot the computer and then restart the Privilege Manager Server Setup wizard to complete the Server setup.</p>	1949
<p>If the administrator is prompted to reboot the computer after installing a pre-requisite while using the Privilege Manager Server Setup wizard, once the computer is rebooted and setup wizard continues, the administrator will need to press the "Back" button to re-enter any of the "Server Email Notification Configuration" settings that they might have entered prior to the reboot.</p>	1980
<p>If the administrator is changing the selected Privilege Manager Server that the Console points to by setting up a Privilege Manager Server on the local computer, once the wizard and Privilege Manager Server Configuration is closed, the administrator might need to re-open that dialog and make sure the newly configured Privilege Manager Server is the currently selected server if the reporting screens still appear to be pulling data from the previously selected server.</p>	1981

Table 9: Self-service Elevation known issues

Known Issue	Issue ID
The Self-Service Elevation Request Prompt does not display for a MSI Windows Installer file. Workaround: Launch the Self-Service Elevation Request Form via the Elevate! button. You must configure the corresponding Self-Service Elevation Request settings.	1311
The Adobe Flash Player ActiveX control does not trigger the Self-Service Elevation Request Prompt.	1555
Some processes do not trigger the Self-Service Elevation Request Prompt even though they trigger User Account Control (UAC).	1674
On Windows 8.1 and Windows Server 2012 R2, if your client is running on a system with UAC turned off, when you right-click the Privilege Manager icon in the Windows system tray and select the "View status of advanced features" dialog, the Self-Service Elevation Request and Self-Service Elevation Request (ActiveX installations) should display as "N/A" (Not Applicable) but will incorrectly display a status of "Enabled."	1865
When using Internet Explorer (IE) 11, ActiveX discovery and Self-Service requests are not sent to the server. Workaround: Follow these steps on the client computer: <ol style="list-style-type: none"> 1. Enable the GPE ActiveX Installer inside the IE plugin screen because by default IE 11 requires the user to enable or disable any newly loaded IE toolbar extension. 2. Uncheck the Enable Enhanced Protected Mode check box on the Advanced tab, under Security, of the Internet Options dialog. Both of these steps can also be completed from the server using Microsoft Group Policy Object settings.	1868

Table 10: Rules known issues

Known Issue	Issue ID
A login failure occurs when connecting to the database and web service if you are using a SQL Server from an untrusted domain. Workaround: Use the database server on the same trusted domain network environment.	698
When configuring reporting to use an existing SQL Server, in the Configure Database and Services step to install prerequisites, create a database, and start the service, the user is brought to an incorrect wizard step when clicking Previous. Workaround: Click Next to go to the step on the wizard to Select an Existing SQL Server.	832
Sometimes changing settings on the Advanced Policy Settings tab of a Group Policy Settings page results in the "Network path was not found" error once you save the changes to the GPO. Workaround: <ul style="list-style-type: none"> • Restart the Privilege Manager Console. 	1671

Known Issue	Issue ID
<ul style="list-style-type: none"> Check that the changes you made on the Advanced Policy Settings tab of the Group Policy Settings page have been saved. If not, re-apply your changes and save the GPO. 	
<p>If a process is running from a Universal Naming Convention (UNC) or mapped drive, a rule which specifies the file version, file hash, product code or publisher might fail to match it because the security permissions set on the network resource prevent the account of the computer that the client is running on from accessing it.</p> <p>Workaround: Edit the rule and check the check box for "User's context will be used to resolve system and resource access." This check box instructs the client to access the network resource under the security context of the user running the process.</p>	1677
No feedback message displayed when a user is denied execution access due to a Blacklist setting	124
Attempting to edit a rule might display the message "Could not find the type of the file security" if the product was just upgraded from Privilege Authority v2.7 or older.	1859
<p>The Rule Type filter on the Instant Elevation Report mistakenly contains Privilege Authority v 2.7-related values. An Instant Elevation Report generated based on these values contain no data.</p> <p>Workaround: Use only file, ActiveX, Windows Installer, and script file filters.</p>	1743

Table 11: Reporting known issues

Known Issue	Issue ID
<p>Under complex conditions, you may see this error in the Privilege Manager Console log (PAConsole_Log.txt) that results in a reporting configuration failure: "System.Data.SqlClient.SqlException: Cannot create file 'c:\Program Files\Microsoft SQL Server\MSSQL 10.PAREPORTING\MSSQL\DATA\PARReporting.mdf' because it already exists. Change the file path or the file name, and retry the operation." The same error may display for the PARReporting_log.ldf file.</p> <p>Workaround: Manually remove the files to proceed with the web service configuration</p>	665
<p>The Elevation Activity Report does not display correctly when exported to an RTF file.</p> <p>Workaround: Export to other file formats.</p>	728
The Console report shows the event time according to the current local time zone.	948
Some reports exported in Excel contain columns that do not display on the generated report page in the Privilege Manager Console.	1738
<p>Resultant Set of Policy (RSoP) output is empty or blank.</p> <p>Workaround: If the client is installed on your computer and RSoP is failing, follow these steps:</p> <ol style="list-style-type: none"> 1. Install .NET 3.5 Service Pack 1 (SP1). 2. Install GPMC, which is part of the Remote Server Administration Tools for Windows 8.1. 	1881

Known Issue	Issue ID
<ol style="list-style-type: none"> Open a command prompt and change the directory to where the client files are installed, such as the following on an x64 computer: C:\Program Files (x86)\Common Files\Quest\Privilege Manager\Client Run the following command: <pre>"%WINDIR%\Microsoft.NET\Framework\v2.0.50727\regasm.exe" "PrivilegeManager.Reporters.dll" /tlb /nologo /codebase"</pre> 	

RSoP should now work for Privilege Manager.

Table 12: Privileged Application Discovery known issues

Known Issue	Issue ID
When using the Privileged Application Discovery rules generation wizard, if the administrator “groups” the results on the “review” panel for a particular displayed column header, an exception error dialog will be presented if the administrator then attempts to view the details of one of the grouped rules.	1967

System requirements

Before installing Privilege Manager for Windows 4.4, refer to the Privilege Manager Quick Start Guide to ensure that your system meets the following minimum hardware and software requirements.

- Console software and hardware system requirements
- Console and Client operating system requirements
- Network requirements
- Required permissions
- Reporting database requirements

Product licensing

Refer to the Privilege Manager Administrator Guide for information on editions and applying a license.

Each Privilege Manager license file is compatible with only a single major version of the product (eg. 3.x or 4.x) . This means existing 3.x licenses will not be valid after upgrading to a 4.x build. Therefore, existing customers are required to obtain a new license file via the License Assistance portal (<https://support.quest.com/contact-us/licensing>) in order to be properly registered after upgrade.

i | **NOTE:** Privilege Manager does not phone home for product licensing.

Product improvement program

To assist in the development of new features, as well as drive future improvements, we have implemented a Product Improvement Program. Feedback from this program provides Product Management with valuable insight into how our products are being used. This information is essential to help the R&D team prioritize existing enhancement requests within the roadmap of the each product. Participation is voluntary, and no personal contact information is ever collected.

Please see the Administrator Guide for more information on the Product Improvement Program, including how to enable/disable the collection of data at any time.

Upgrade and installation instructions

Refer to the Privilege Manager Administrator Guide for upgrade information and the Privilege Manager Quick Start Guide for information on installing the Console, configuring the Server, and installing the Client.

More resources

Additional information is available from the following:

- [Online product documentation](#): This site provides robust search capabilities that allow you to search across all related documents.
- [Privilege Manager Community Forum](#): Get the latest product information, find helpful resources, test the product betas, and join a discussion with the Quest Software team and other community members.

Globalization

This section contains information about installing and operating this product in non-English configurations, such as those needed by customers outside of North America. This section does not replace the materials about supported platforms and configurations found elsewhere in the product documentation.

This release is Unicode-enabled and supports any character set. In this release, all product components should be configured to use the same or compatible character encodings and should be installed to use the same locale and regional options. This release is targeted to support operations in the following regions: North America, Western Europe and Latin America, Central and Eastern Europe, Far-East Asia, Japan.

About us

Quest provides software solutions for the rapidly-changing world of enterprise IT. We help simplify the challenges caused by data explosion, cloud expansion, hybrid datacenters, security threats, and regulatory requirements. We are a global provider to 130,000 companies across 100 countries, including 95% of the Fortune 500 and 90% of the Global 1000. Since 1987, we have built a portfolio of solutions that now includes database management, data protection, identity and access management, Microsoft platform management, and unified endpoint management. With Quest, organizations spend less time on IT administration and more time on business innovation. For more information, visit www.quest.com.

Technical support resources

Technical support is available to Quest customers with a valid maintenance contract and customers who have trial versions. You can access the Quest Support Portal at <https://support.quest.com>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to-videos
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

© 2020 Quest Software Inc. ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Quest Software Inc.

The information in this document is provided in connection with Quest Software products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Quest Software products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, QUEST SOFTWARE ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL QUEST SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF QUEST SOFTWARE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Quest Software makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Quest Software does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Quest Software Inc.

Attn: LEGAL Dept

4 Polaris Way

Aliso Viejo, CA 92656

Refer to our Web site (<https://www.quest.com>) for regional and international office information.

Patents

Quest Software is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <https://www.quest.com/legal>.

Trademarks

Quest, the Quest logo, and Join the Innovation are trademarks and registered trademarks of Quest Software Inc. For a complete list of Quest marks, visit <https://www.quest.com/legal/trademark-information.aspx>. All other trademarks and registered trademarks are property of their respective owners.

Legend

-  **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.
-  **IMPORTANT, NOTE, TIP, MOBILE, or VIDEO:** An information icon indicates supporting information.

Privilege Manager for Windows Release Notes
Updated - May 2020
Version - 4.4